# DPO2000 and MSO2000 Series Programmer Manual





DPO2000 and MSO2000 Series Programmer Manual



Copyright © Tektronix. All rights reserved. Licensed software products are owned by Tektronix or its subsidiaries or suppliers, and are protected by national copyright laws and international treaty provisions.

Tektronix products are covered by U.S. and foreign patents, issued and pending. Information in this publication supersedes that in all previously published material. Specifications and price change privileges reserved.

TEKTRONIX and TEK are registered trademarks of Tektronix, Inc.

#### **Contacting Tektronix**

Tektronix, Inc. 14200 SW Karl Braun Drive P.O. Box 500 Beaverton, OR 97077 USA

For product information, sales, service, and technical support:

- In North America, call 1-800-833-9200.
- Worldwide, visit www.tektronix.com to find contacts in your area.

# **Table of Contents**

Getting Started	1-1
Setting Up Remote Communications	1-1
Command Syntax	2-1
Command and Query Structure	2-1
Clearing the oscilloscope	2-4
Command Entry	2-4
Constructed Mnemonics	2-6
Argument Types	2-7
Command Groups	2-1
Acquisition Command Group	2-1
Alias Command Group	2-12
Bus Command Group	2-13
Calibration and Diagnostic Command Group	2-16
Cursor Command Group	2-17
Display Command Group	2-18
Ethernet Command Group	2-19
File System Command Group	2-20
FilterVu Command Group	2-2
Hard Copy Command Group	2-22
Horizontal Command Group	2-23
Mark Command Group.	2-23
Math Command Group	2-25
Measurement Command Group	2-26
Miscellaneous Command Group	2-29
PictBridge Command Group	2-30
Save and Recall Command Group	2-3
Search Command Group	2-33
Status and Error Command Group	2-3
Trigger Command Group	2-38
Vertical Command Group	2-45
Waveform Transfer Command Group	2-48
Zoom Command Group	2-55
Commands Listed in Alphabetical Order	2-57
Status and Events	3-2
Registers	3-2
Queues	3-4
Event Handling Sequence	3-:
Synchronization Methods	3-7
Messages	3_1′

#### **Table of Contents**

Appendix A: Character Set	A-1
Appendix B: Waveform Data in DPO/MSO2000 Series Instruments	B-1
Appendix C: Reserved Words	C-1
Index	

# **Getting Started**

This manual explains the use of commands for remotely controlling your oscilloscope. With this information, you can write computer programs to perform functions, such as setting the front-panel controls, taking measurements, performing statistical calculations, and exporting data for use in other programs.

# **Setting Up Remote Communications**

You can remotely communicate between your oscilloscope and PC via the Ethernet, USB, and, GPIB using the TEK-USB-488 Adapter.

#### **Ethernet**

If you are using Ethernet, start by connecting an appropriate Ethernet cable to the Ethernet port (RJ-45 connector) on the rear panel of your oscilloscope. This connects the oscilloscope to a 10/100 Base-T local area network.



To change the Ethernet settings on your oscilloscope, do the following:

- 1. On the front panel, push Utility.
- 2. Push Utility Page.
- **3.** Select **I/O** with the Multipurpose knob.
- 4. Push Ethernet Network Settings.
- **5.** On the side-bezel menu, if you are on a DHCP Ethernet network and using a through cable, set DHCP/BOOTP to **On**.
- **6.** If you are using a cross-over cable, set DHCP/BOOTP to **Off**, and set a hard coded TCPIP address.

USB If you are using USB, start by connecting an appropriate USB cable to the USB 2.0 high-speed device port on the rear panel of your oscilloscope.



With USB, the system automatically configures itself. To verify that the USB is enabled:

- 1. On the front panel, push Utility.
- 2. Push Utility Page.
- **3.** Select **I/O** with the Multipurpose knob.
- **4.** Push **USB**, and verify that USB is enabled.
- 5. If USB is not enabled, push **Enabled** on the side-bezel menu.

After connection, the host will list the oscilloscope as a USB device with the following parameters. (See Table 1-1.)

**Table 1-1: USB Device Parameters** 

Parameter	Value
Manufacturer ID	0x0699 (decimal 1689)
Product ID	0x0372 DPO2012
	0x0373 DPO2014
	0x0374 DPO2024
	0x0376 MSO2012
	0x0377 MSO2014
	0x0378 MSO2024
Serial number	Serial number
Manufacturer description	"Tektronix"
Interface description	"USBTMC-USB488"

**GPIB** To use GPIB, start by connecting an appropriate USB cable to the USB 2.0 high-speed device port on the rear panel of your oscilloscope. Connect the other end to the TEK-USB-488 Adapter host port. Then connect a GPIB cable from the TEK-USB-488 Adapter to your PC.

Supply power to the Adapter in either of these two ways:

- 1. Use the optional 5  $V_{DC}$  power adapter connected to the 5  $V_{DC}$  power input on the Adapter.
- 2. Use an appropriate USB cable connected to a powered USB host port on your PC and the Device port on the TEK-USB-488 Adapter.

The oscilloscope has a USB 2.0 high-speed device port to control the oscilloscope through USBTMC or GPIB with a TEK-USB-488 Adapter. The USBTMC protocol allows USB devices to communicate using IEEE488 style messages. This lets you run your GPIB software applications on USB hardware.



Before setting up the oscilloscope for remote communication using the electronic (physical) GPIB interface, you should familiarize yourself with the following GPIB requirements:

- A unique device address must be assigned to each device on the bus. No two devices can share the same device address.
- No more than 15 devices can be connected to any one line.
- Only one device should be connected for every 6 feet (2 meters) of cable used.
- No more than 65 feet (20 meters) of cable should be used to connect devices to a bus.
- At least two-thirds of the devices on the network should be powered on while using the network.
- Connect the devices on the network in a star or linear configuration. Do not use loop or parallel configurations.

To function correctly, your oscilloscope must have a unique device address. The default setting for the GPIB configuration is GPIB Address 1.

To change the GPIB address settings, do the following:

- 1. On the front panel, push Utility.
- 2. Push Utility Page.
- **3.** Select **I/O** with the Multipurpose knob.
- 4. Push GPIB.
- **5.** Enter the GPIB address on the side-bezel menu, using the multipurpose knob. This will set the GPIB address on an attached TEK-USB-488 Adapter

The oscilloscope is now set up for bidirectional communication with your controller.

#### **Documentation**

The following documents are available for download on the Manuals Finder Web site at *www.tektronix.com*:

**DPO/MSO2000 Series User Manual**. Information about installing and operating the oscilloscope.

*Getting Started with OpenChoice* <sup>TM</sup> *Solutions Manual*. Options for getting data from your oscilloscope into any one of several available analysis tools.

**DPO/MSO2000 Series Technical Reference**. Oscilloscope specifications and a performance verification procedure.

*TekVISA Programmer Manual.* Description of TekVISA, the Tektronix implementation of the VISA Application Programming Interface (API). TekVISA is industry-compliant software for writing interoperable oscilloscope drivers in a variety of Application Development Environments (ADEs).

# **Command Syntax**

You can control the operations and functions of the oscilloscope through the Ethernet port or the USB 2.0 device port using commands and queries. The related topics listed below describe the syntax of these commands and queries. The topics also describe the conventions that the oscilloscope uses to process them. See the *Command Groups* topic in the table of contents for a listing of the commands by command group, or use the index to locate a specific command.

# Backus-Naur Form Notation

This documentation describes the commands and queries using Backus-Naur Form (BNF) notation. Refer to the following table for the symbols that are used.

Table 2-1: Symbols for Backus-Naur Form

Symbol	Meaning
<>	Defined element
=	Is defined as
	Exclusive OR
{}	Group; one element is required
[]	Optional; can be omitted
	Previous element(s) may be repeated
()	Comment

## **Command and Query Structure**

Commands consist of set commands and query commands (usually called commands and queries). Commands modify oscilloscope settings or tell the oscilloscope to perform a specific action. Queries cause the oscilloscope to return data and status information.

Most commands have both a set form and a query form. The query form of the command differs from the set form by its question mark at the end. For example, the set command ACQuire: MODe has a query form ACQuire: MODe?. Not all commands have both a set and a query form. Some commands have set only and some have query only.

#### Messages

A command message is a command or query name followed by any information the oscilloscope needs to execute the command or query. Command messages may contain five element types, defined in the following table.

**Table 2-2: Command Message Elements** 

Symbol	Meaning
<header></header>	This is the basic command name. If the header ends with a question mark, the command is a query. The header may begin with a colon (:) character. If the command is concatenated with other commands, the beginning colon is required. Never use the beginning colon with command headers beginning with a star (*).
<mnemonic></mnemonic>	This is a header subfunction. Some command headers have only one mnemonic. If a command header has multiple mnemonics, a colon (:) character always separates them from each other.
<argument></argument>	This is a quantity, quality, restriction, or limit associated with the header. Some commands have no arguments while others have multiple arguments. A <space> separates arguments from the header. A <comma> separates arguments from each other.</comma></space>
<comma></comma>	A single comma is used between arguments of multiple-argument commands. Optionally, there may be white space characters before and after the comma.
<space></space>	A white space character is used between a command header and the related argument. Optionally, a white space may consist of multiple white space characters.

#### Commands

Commands cause the oscilloscope to perform a specific function or change one of the settings. Commands have the structure:

[:]<Header>[<Space><Argument>[<Comma> <Argument>]...]

A command header consists of one or more mnemonics arranged in a hierarchical or tree structure. The first mnemonic is the base or root of the tree and each subsequent mnemonic is a level or branch off the previous one. Commands at a higher level in the tree may affect those at a lower level. The leading colon (:) always returns you to the base of the command tree.

#### Queries

Queries cause the oscilloscope to return status or setting information. Queries have the structure:

- [:]<Header>
- [:]<Header>[<Space><Argument> [<Coma><Argument>]...]


You can specify a query command at any level within the command tree unless otherwise noted. These branch queries return information about all the mnemonics below the specified branch or level.

#### **Headers**

Use the HEADer command to control whether the oscilloscope returns headers as part of the query response. If header is on, the query response returns command headers, then formats itself as a valid set command. When header is off, the response includes only the values. This may make it easier to parse and extract the information from the response. The table below shows the difference in responses.

Table 2-3: Comparison of Header Off and Header On Responses

Query	Header Off	Header On
TIME?	14:30:00	:TIME "14:30:00"
ACQuire:NUMAVg?	100	:ACQUIRE:NUMAVG 100



## Clearing the oscilloscope

You can clear the Output Queue and reset the oscilloscope to accept a new command or query by using the selected Device Clear (DCL) function.

# **Command Entry**

The following rules apply when entering commands:

- You can enter commands in upper or lower case.
- You can precede any command with white space characters. White space characters include any combination of the ASCII control characters 00 through 09 and 0B through 20 hexadecimal (0 through 9 and 11 through 32 decimal).
- The oscilloscope ignores commands consisting of any combination of white space characters and line feeds.

#### **Abbreviating**

You can abbreviate many oscilloscope commands. Each command in this documentation shows the minimum acceptable abbreviations in capitals. For example, you can enter the command ACQuire:NUMAvg simply as ACQ:NUMA or acq:numa.

Abbreviation rules may change over time as new oscilloscope models are introduced. Thus, for the most robust code, use the full spelling.

If you use the HEADer command to have command headers included as part of query responses, you can further control whether the returned headers are abbreviated or are full-length with the VERBose command.

#### Concatenating

You can concatenate any combination of set commands and queries using a semicolon (;). The oscilloscope executes concatenated commands in the order received.

When concatenating commands and queries, you must follow these rules:

 Separate completely different headers by a semicolon and by the beginning colon on all commands except the first one. For example, the commands TRIGGer: MODE NORMal and ACQuire: NUMAVg 8, can be concatenated into the following single command:

TRIGger: MODe NORMal;: ACQuire: NUMAVg 8

2. If concatenated commands have headers that differ by only the last mnemonic, you can abbreviate the second command and eliminate the beginning colon. For example, you can concatenate the commands ACQuire: MODe AVErage and ACQuire: NUMAVq 8 into a single command:

ACQuire: MODe AVErage; NUMAVg 8

The longer version works equally well:

ACQuire:MODe AVErage;:ACQuire:NUMAVg 8

**3.** Never precede a star (\*) command with a colon:

ACQuire:STATE 1;\*OPC

Any commands that follow will be processed as if the star command was not there so the commands, ACQuire:MODe ENVelope; \*OPC; NUMAVg 8 will set the acquisition mode to envelope and set the number of acquisitions for averaging to 8.

- **4.** When you concatenate queries, the responses to all the queries are concatenated into a single response message.
- **5.** Set commands and queries may be concatenated in the same message. For example,

ACQuire: MODe SAMple; NUMAVg?; STATE?

is a valid message that sets the acquisition mode to sample. The message then queries the number of acquisitions for averaging and the acquisition state. Concatenated commands and queries are executed in the order received.

Here are some invalid concatenations:

HORizontal:SCAle 400E-9;ACQuire:NUMAVg 8 (no colon before ACQuire)

DISPlay:GRAticule FULL;:\*TRG (colon before a star (\*) command)

MATH:HORizontal:SCAle 1.0e-1;HORizontal:POSition 5.0el (levels of the mnemonics are different; either remove the second use of HORizontal: or place:MATH in front of HORizontal:POSition)

**Terminating** 

This documentation uses <EOM> (End of Message) to represent a message terminator.

**Table 2-4: End of Message Terminator** 

Symbol	Meaning
<eom></eom>	Message terminator

The end-of-message terminator must be the END message (EOI asserted concurrently with the last data byte). The last data byte may be an ASCII line feed (LF) character.

This oscilloscope does not support ASCII LF only message termination. The oscilloscope always terminates outgoing messages with LF and EOI.

#### **Constructed Mnemonics**

Some header mnemonics specify one of a range of mnemonics. For example, a channel mnemonic can be CH1, CH2, CH3, or CH4. You use these mnemonics in the command just as you do any other mnemonic. For example, there is a CH1:POSition command, and there is also a CH2:POSition command. In the command descriptions, this list of choices is abbreviated as CH<x>.

#### Cursor Position Mnemonics

When cursors are displayed, commands may specify which cursor of the pair to use.

**Table 2-5: Channel Mnemonics** 

Symbol	Meaning
CH <x></x>	A channel specifier; <x> is 1 through 4.</x>

**Table 2-6: Cursor Mnemonics** 

Symbol	Meaning
CURSOR <x></x>	A cursor selector; <x> is either 1 or 2.</x>
POSITION <x></x>	A cursor selector; <x> is either 1 or 2.</x>
HPOS <x></x>	A cursor selector; <x> is either 1 or 2.</x>

#### **Math Specifier Mnemonics**

Commands can specify the mathematical waveform to use as a mnemonic in the header.

**Table 2-7: Math Specifier Mnemonics** 

Symbol	Meaning
Math <x></x>	A math waveform specifier; <x> is 1.</x>

# Measurement Specifier Mnemonics

Commands can specify which measurement to set or query as a mnemonic in the header. Up to four automated measurements may be displayed.

**Table 2-8: Measurement Specifier Mnemonics** 

Symbol	Meaning
MEAS <x></x>	A measurement specifier; <x> is 1 through 4.</x>

#### **Channel Mnemonics**

Commands specify the channel to use as a mnemonic in the header.

#### Reference Waveform Mnemonics

Commands can specify the reference waveform to use as a mnemonic in the header.

Table 2-9: Reference Waveform Mnemonics

Symbol	Meaning
REF <x></x>	A reference waveform specifier; <x> 1 or 2. The DPO/MSO2000 series provides only two REF waveforms regardless of whether the instrument is a 2 or 4 channel model.</x>

## **Argument Types**

#### Numeric

Many oscilloscope commands require numeric arguments. The syntax shows the format that the oscilloscope returns in response to a query. This is also the preferred format when sending the command to the oscilloscope though any of the formats will be accepted. This documentation represents these arguments as described below.

**Table 2-10: Numeric Arguments** 

Symbol	Meaning
<nr1></nr1>	Signed integer value
<nr2></nr2>	Floating point value without an exponent
<nr3></nr3>	Floating point value with an exponent
<bin></bin>	Digital data in binary format

Most numeric arguments will be automatically forced to a valid setting, by either rounding or truncating,, when an invalid number is input, unless otherwise noted in the command description.

#### **Quoted String**

Some commands accept or return data in the form of a quoted string, which is simply a group of ASCII characters enclosed by a single quote (') or double quote ("). The following is an example of a quoted string: "This is a quoted string". This documentation represents these arguments as follows:

**Table 2-11: Quoted String Argument** 

Symbol	Meaning
<qstring></qstring>	Quoted string of ASCII text

A quoted string can include any character defined in the 7-bit ASCII character set. Follow these rules when you use quoted strings:

- 1. Use the same type of quote character to open and close the string. For example: "this is a valid string".
- **2.** You can mix quotation marks within a string as long as you follow the previous rule. For example: "this is an 'acceptable' string".
- **3.** You can include a quote character within a string by repeating the quote. For example: "here is a "" mark".
- **4.** Strings can have upper or lower case characters.
- **5.** If you use a GPIB network, you cannot terminate a quoted string with the END message before the closing delimiter.
- **6.** A carriage return or line feed embedded in a quoted string does not terminate the string. The return is treated as another character in the string.
- 7. The maximum length of a quoted string returned from a query is 1000 characters.

Here are some invalid strings:


- "Invalid string argument' (quotes are not of the same type)
- "test<EOI>" (termination character is embedded in the string)

# **Block** Several oscilloscope commands use a block argument form, as defined in the table below.

**Table 2-12: Block Argument** 

Symbol	Meaning	
<nzdig></nzdig>	A nonzero digit character in the range of 1–9	
<dig></dig>	A digit character, in the range of 0–9	
<dchar></dchar>	A character with the hexadecimal equivalent of 00 through FF (0 through 255 decimal)	
<block></block>	A block of data bytes defined as: <block> ::= {#<nzdig><dig>[<dig>][<dchar>]  #0[<dchar>]<terminator>}</terminator></dchar></dchar></dig></dig></nzdig></block>	

<sup>&</sup>lt;NZDig> specifies the number of <Dig> elements that follow. Taken together, the <NZDig> and <Dig> elements form a decimal integer that specifies how many <DChar> elements follow.



# **Command Groups**

This manual lists the DPO/MSO2000 series IEEE488.2 commands in two ways. First, it presents them by functional groups. Then, it lists them alphabetically. The functional group list starts below. The alphabetical list provides detail on each command. (See page 2-57, *Commands Listed in Alphabetical Order*.)

## **Acquisition Command Group**

Use the commands in the Acquisition Command Group to set up the modes and functions that control how the oscilloscope acquires signals input to the channels, and processes them into waveforms.

Using the commands in this group, you can do the following:

- Start and stop acquisitions.
- Control whether each waveform is simply acquired, averaged over successive acquisitions of that waveform.
- Set the controls or conditions that start and stop acquisitions.
- Control acquisition of channel waveforms.
- Set acquisition parameters.

**Table 2-13: Acquisition Commands** 

Command	Description	
ACQuire?	Returns acquisition parameters	
ACQuire:MAXSamplerate?	Returns the maximum real-time sample rate	
ACQuire:MODe	Sets or returns the acquisition mode	
ACQuire:NUMACq?	Returns number of acquisitions that have occurred	
ACQuire:NUMAVg	Sets or returns the number of acquisitions for an averaged waveform	
ACQuire:STATE	Starts or stops the acquisition system	
ACQuire:STOPAfter	Sets or returns whether the acquisition is continuous or single sequence	

## **Alias Command Group**

Use the Alias commands to define new commands as a sequence of standard commands. You may find this useful when repeatedly using the same commands to perform certain tasks like setting up measurements.

Aliases are similar to macros but do not include the capability to substitute parameters into alias bodies. The alias mechanism obeys the following rules:

- The alias name must consist of a valid IEEE488.2 message unit, which may not appear in a message preceded by a colon, comma, or a command or query program header.
- The alias name may not appear in a message followed by a colon, comma, or question mark.
- An alias name must be distinct from any keyword or keyword short form.
- An alias name cannot be redefined without first being deleted using one of the alias deletion functions.
- Alias names do not appear in response messages.

Table 2-14: Alias Commands

Command	Description
ALlas	Sets or returns the alias state
ALIas:CATalog?	Returns a list of the currently defined alias labels
ALIas:DEFine	Assigns a sequence of program messages to an alias label
ALIas:DELEte	Removes a specified alias
ALIas:DELEte:ALL	Deletes all existing aliases
ALIas:DELEte[:NAMe]	Removes a specified alias
ALlas[:STATE]	Sets or returns the alias state

# **Bus Command Group**

Use the Bus commands when working with serial bus measurements.

- Install the DPO2EMBD application module when working with I<sup>2</sup>C or SPI bus signals.
- Install the DPO2AUTO module when working with CAN or LIN bus signals.
- Install the DPO2COMP module when working with RS232 bus signals.

Table 2-15: Bus Commands

Commands	Description
BUS	Returns the parameters for each bus
BUS:B <x>:CAN:BITRate</x>	Sets or returns the bit rate for the CAN bus
BUS:B <x>:CAN:PRObe</x>	Sets or returns the probing method used to probe the CAN bus
BUS:B <x>:CAN:SAMPLEpoint</x>	Sets or returns the sample point (in %) to sample during each bit period
BUS:B <x>:CAN:SOUrce</x>	Sets or returns the CAN data source
BUS:B <x>:DISplay:FORMAt</x>	Sets the display format for the numerical information in the specified bus waveform
BUS:B <x>:I2C:ADDRess:RWINClude</x>	Sets and returns whether the read/write bit is included in the address
BUS:B <x>:I2C{:CLOCK :SCLK}:SOUrce</x>	Sets or returns the I2C SCLK source
BUS:B <x>:I2C{:DATA :SDATA}:SOUrce</x>	Sets or returns the I2C SDATA source
BUS:B <x>:LABel</x>	Sets or returns the waveform label for the specified bus
BUS:B <x>:LIN:BITRate</x>	Sets or returns the bit rate for LIN
BUS:B <x>:LIN:IDFORmat</x>	Sets or returns the LIN ID format
BUS:B <x>:LIN:POLARity</x>	Sets or returns the LIN polarity
BUS:B <x>:LIN:SAMPLEpoint</x>	Sets or returns the sample point (in %) at which to sample during each bit period
BUS:B <x>:LIN:SOUrce</x>	Sets or returns the LIN data source
BUS:B <x>:LIN:STANDard</x>	Sets or returns the LIN standard
BUS:B <x>:PARallel:BIT<x>:SOUrce</x></x>	Sets or returns the parallel bit <x> source</x>
BUS:B <x>:PARallel:CLOCK:EDGE</x>	Sets or returns the parallel clock edge for bus <x></x>
BUS:B <x>:PARallel:CLOCK:ISCLOCKed</x>	Sets or returns whether the parallel bus is clocked
BUS:B <x>:PARallel:CLOCK:SOUrce</x>	Sets or returns the parallel bus <x> clock source</x>
BUS:B <x>:PARallel:WIDth</x>	Sets or returns the number of bits used for the width of the parallel bus <x></x>

Table 2-15: Bus Commands (cont.)

Commands	Description
BUS:B <x>:POSition</x>	Sets or returns the position of the specified bus waveform
BUS:B <x>:RS232C:BITRate</x>	Sets or returns the RS232 bit rate for the specified bus
BUS:B <x>:RS232C:DATABits</x>	Sets or returns the number of bits for the data frame
BUS:B <x>:RS232C:DELIMiter</x>	Sets or returns the RS232 delimiting value for a packet on the specified bus
BUS:B <x>:RS232C:DISplaymode</x>	Sets or returns the display mode for the specified bus display and event table
BUS:B <x>:RS232C:PARity</x>	Sets or returns parity for RS232 data
BUS:B <x>:RS232C:POLarity</x>	Sets or returns the RS232C polarity for the specified bus
BUS:B <x>:RS232C:RX:SOUrce</x>	Sets or returns the RS232 RX source
BUS:B <x>:RS232C:TX:SOUrce</x>	Sets or returns the RS232 TX Source
BUS:B <x>:SPI{:CLOCK :SCLK}:POLARity</x>	Sets or returns the SPI SCLK polarity
BUS:B <x>:SPI{:CLOCK :SCLK}:SOUrce</x>	Sets or returns the SPI SCLK source
BUS:B <x>:SPI:DATA{:IN :MISO}:POLARity</x>	Sets or returns the SPI MISO polarity
BUS:B <x>:SPI:DATA{:IN :MISO}:SOUrce</x>	Sets or returns the SPI MISO source
BUS:B <x>:SPI:DATA{:OUT :MOSI}: POLARity</x>	Sets or returns the SPI MOSI polarity
BUS:B <x>:SPI:DATA{:OUT :MOSI}:SOUrce</x>	Sets or returns the SPI MOSI source
BUS:B <x>:SPI{:SELect :SS}:POLARity</x>	Sets or returns the SPI SS polarity
BUS:B <x>:SPI{:SELect :SS}:SOUrce</x>	Sets or returns the SPI SS source
BUS:B <x>:SPI:BITOrder</x>	Sets or returns the bit order for the specified SPI bus
BUS:B <x>:SPI:DATA:SIZe</x>	Sets or returns the number of bits per word for the specified SPI bus
BUS:B <x>:SPI:FRAMING</x>	Sets or returns the type of SPI framing
BUS:B <x>:SPI:IDLETime</x>	Sets or returns the SPI bus idle time in seconds for the specified SPI bus
BUS:B <x>:STATE</x>	Turns the specified bus on and off
BUS:B <x>:TYPE</x>	Sets or returns the specified bus type
BUS:LOWerthreshold:CH <x></x>	Sets or returns the lower threshold for each channel
BUS:THReshold:CH <x></x>	Sets or returns the threshold for a channel
BUS:UPPerthreshold:CH <x></x>	Sets or returns the upper threshold for each channel
BUS:THReshold:D <x></x>	Sets or returns the threshold for digital channel

Table 2-15: Bus Commands (cont.)

Commands	Description
SEARCH:SEARCH <x>:TRIGger:A:BUS?</x>	Returns the serial search type
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:LIN:CONDition</x></x>	Sets or returns the search condition for a LIN search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:LIN:DATa:HIVALue</x></x>	Sets or returns the binary data string
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:LIN:DATa:QUALifier</x></x>	Sets or returns the LIN data qualifier
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:LIN:DATa:SIZe</x></x>	Sets or returns the length of the data string in bytes
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:LIN:DATa:VALue</x></x>	Sets or returns the binary data string used for a LIN search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:LIN:ERRTYPE</x></x>	Sets or returns the error type used for a LIN Search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:LIN:IDentifier:VALue</x></x>	Sets or returns the binary address string used for LIN search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:CONDition</x></x>	Sets or returns the trigger condition for a RS232 trigger
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:RX:DATa:SIZe</x></x>	Sets or returns the length of the data string for a RS232 RX trigger
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:RX:DATa:VALue</x></x>	Sets or returns the binary data string for a RX RS232 trigger
TRIGger:A:BUS:B <x>:LIN:CONDition</x>	Sets or returns the trigger condition for LIN
TRIGger:A:BUS:B <x>:LIN:DATa:HIVALue</x>	Sets or returns the binary data string to be used for LIN trigger
TRIGger:A:BUS:B <x>:LIN:DATa:QUALifier</x>	Sets or returns the LIN data qualifier
TRIGger:A:BUS:B <x>:LIN:DATa:SIZe</x>	Sets or returns the length of the data string in bytes to be used for LIN trigger
TRIGger:A:BUS:B <x>:LIN:DATa:VALue</x>	Sets or returns the binary data string
TRIGger:A:BUS:B <x>:LIN:ERRTYPE</x>	Sets or returns the error type
TRIGger:A:BUS:B <x>:LIN:IDentifier:VALue</x>	Sets or returns the binary address string used for LIN trigger
TRIGger:A:BUS:B <x>:RS232C:RX:DATa: SIZe</x>	Sets or returns the length of the data string for a RX RS232 trigger
TRIGger:A:BUS:B <x>:RS232C:RX:DATa: VALue</x>	Sets or returns the binary data string for a RX RS232 trigger
TRIGger:A:BUS:B <x>:RS232C:TX:DATa: SIZe</x>	Sets or returns the length of the data string to be used for a TX RS232 Trigger
TRIGger:A:BUS:B <x>:RS232C:TX:DATa: VALue</x>	Sets or returns the binary data string to be used for a TX RS232 trigger

# **Calibration and Diagnostic Command Group**

The Calibration and Diagnostic commands provide information about the current state of oscilloscope calibration. They also initiate internal signal path calibration (SPC) or execute diagnostic tests. Commands that are specific to factory calibration are not described in this manual. They are described in the Service manual, located on the DPO2000 Documentation CD-ROM in PDF format. You can also order a printed copy.

**Table 2-16: Calibration and Diagnostic Commands** 

Command	Description
*CAL?	Instructs the oscilloscope to perform self-calibration and returns the oscilloscope self calibration status
CALibrate:FACtory	Provides the controls for starting and stopping the factory calibration process
CALibrate:FACtory:STATus?	Returns the factory calibration status value saved in nonvolatile memory
CALibrate:INTERNal	Starts a signal path compensation
CALibrate:INTERNal:STARt	Starts the internal signal path calibration
CALibrate:INTERNal:STATus?	Returns the current status of the internal signal path calibration
CALibrate:RESults?	Returns the status of all calibration subsystems without performing an SPC operation
CALibrate:RESults:FACtory?	Returns the status of internal and factory calibration
CALibrate:RESults:SPC?	Returns the results of the last SPC operation
CALibrate:TEMPerature?	Returns 0 as DPO/MSO2000 series does not support recording of oscilloscope temperature
DIAg:LOOP:OPTion	Sets the self-test loop option
DIAg:LOOP:OPTion:NTIMes	Sets the self-test loop option to run N times
DIAg:LOOP:STOP	Stops the self-test at the end of the current loop
DIAg:RESUlt:FLAg?	Returns the pass/fail status from the last self-test sequence execution
DIAg:RESUlt:LOG?	Returns the internal results log from the last self-test sequence execution
DIAg:SELect: <function></function>	Selects one of the available self-test areas
DIAg:STATE	Sets the oscilloscope operating state
DIAg:SELect	Runs self tests on the specified system subsystem

# **Cursor Command Group**

Use the commands in the Cursor Command Group to control the cursor display and readout. You can use these commands to control the setups for cursor 1 and cursor 2, such as cursor position.

You can also use the commands to select one of the following cursor functions:

- Off. Turns off the display of all cursors.
- Waveform Cursors. Consists of two cursors. Waveform cursors enable you to conveniently measure waveform amplitude and time.
- Screen Cursors. Consists of two pairs of independent horizontal and vertical cursors. You can use these cursors to indicate an arbitrary position within the waveform display area.

**Table 2-17: Cursor Commands** 

Command	Description
CURSor?	Returns cursor settings
CURSor:FUNCtion	Sets or returns the cursor type
CURSor:HBArs?	Returns hbar cursor settings
CURSor:HBArs:DELTa?	Returns hbars cursors vertical difference
CURSor:HBArs:POSITION <x></x>	Sets or returns the hbar cursor <x> vertical position</x>
CURSor:HBArs:UNIts	Returns hbar cursor units
CURSor:HBArs:USE	Sets the horizontal bar cursor measurement scale
CURSor:MODe	Sets or returns whether cursors move in unison or separately
CURSor:VBArs?	Sets or returns the position of vertical bar cursors
CURSor:VBArs:ALTERNATE <x>?</x>	Returns the alternate readout for the waveform (Vbar) cursors
CURSor:VBArs:DELTa?	Returns the difference between vbar cursors
CURSor:VBArs:HPOS <x>?</x>	Returns the horizontal value of the specified vertical bar ticks
CURSor:VBArs:POSITION <x></x>	Sets or returns the vbar cursor <x> horizontal position</x>
CURSor:VBArs:UNIts	Sets or returns the units for vbar cursors
CURSor:VBArs:USE	Sets the vertical bar cursor measurement scale
CURSor:VBArs:VDELTa?	Returns the vertical difference between the two vertical bar cursor ticks
CURSor:XY:POLar:RADIUS:DELta?	Returns the difference between the cursors X radius and the cursor Y radius

**Table 2-17: Cursor Commands (cont.)** 

Command	Description
CURSor:XY:POLar:RADIUS:POSITION <x>?</x>	Returns the polar radius of the specified cursor
CURSor:XY:POLar:RADIUS:UNIts?	Returns the polar radius units
CURSor:XY:POLar:THETA:DELta?	Returns the XY cursor polar coordinate delta
CURSor:XY:POLar:THETA:POSITION <x>?</x>	Returns the cursor X or cursor Y polar coordinate
CURSor:XY:POLar:THETA:UNIts?	Returns the cursor polar coordinate units
CURSor:XY:PRODUCT:DELta?	Returns the difference between the cursors X position and cursor Y position
CURSor:XY:PRODUCT:POSITION <x>?</x>	Returns the position of the X or Y cursor used to calculate the X × Y cursor measurement
CURSor:XY:PRODUCT:UNIts?	Returns the XY cursor product units
CURSor:XY:RATIO:DELta?	Returns the ratio of the difference between the cursor X position and cursor Y position
CURSor:XY:RATIO:POSITION <x>?</x>	Returns the X or Y position for the specified cursor
CURSor:XY:RATIO:UNIts?	Returns the X and Y cursor units for the ratio measurement
CURSor:XY:RECTangular:X:DELta?	Returns the cursor X delta value in rectangular coordinates
CURSor:XY:RECTangular:X:POSITION <x></x>	Sets or returns the cursor X rectangular coordinates
CURSor:XY:RECTangular:X:UNIts?	Returns the Cursor X rectangular units
CURSor:XY:RECTangular:Y:DELta?	Returns The cursor Y delta value in rectangular coordinates
CURSor:XY:RECTangular:Y:POSITION <x>&gt;</x>	Sets or returns the cursor Y rectangular coordinates
CURSor:XY:RECTangular:Y:UNIts?	Returns the cursor Y rectangular units

# **Display Command Group**

Use the commands in the Display Command Group to change the graticule style, the displayed intensities, and to set the characteristics of the waveform display.

Use these commands to set the style that best displays your waveforms and graticule display properties. Note that the mode you choose globally affects all displayed waveforms.

**Table 2-18: Display Commands** 

Command	Description
DISplay?	Returns current display settings

Table 2-18: Display Commands (cont.)

Description
Sets or returns the display of the date/time stamp
Sets or returns the height of the digital display and the number of waveforms that you can display
Sets or returns the display format
Sets or returns the type of graticule that is displayed
Returns all display intensity settings
Sets or returns the backlight intensity for the display
Sets or returns the graticule intensity for the display
Sets or returns the intensity of the waveforms
Sets or returns display persistence setting
Sets or returns the size and position of the message window
Removes the message text from the message window
Clears the contents of the message window
Controls the display of the message window

# **Ethernet Command Group**

Use the commands in the Ethernet Command Group to set up the Ethernet remote interface.

**Table 2-19: Ethernet Commands** 

Command	Description
ETHERnet:DHCPbootp	Sets or returns the network initialization search for a DHCP/BOOTP server
ETHERnet:DNS:IPADDress	Sets or returns the network Domain Name Server (Dns) IP address
ETHERnet:DOMAINname	Sets or returns the network domain name
ETHERnet:ENET:ADDress?	Returns the Ethernet address value assigned to the oscilloscope
ETHERnet:GATEWay:IPADDress	Sets or returns the remote interface gateway IP address
ETHERnet:HTTPPort	Sets or returns the remote interface HTTP port value

**Table 2-19: Ethernet Commands (cont.)** 

Command	Description
ETHERnet:IPADDress	Sets or returns the IP address assigned to the oscilloscope
ETHERnet:NAME	Sets or returns the network name assigned to the oscilloscope
ETHERnet:PASSWord	Sets or returns the Ethernet access password
ETHERnet:PING	Causes the oscilloscope to ping the gateway IP address
ETHERnet:PING:STATUS?	Returns the results from pinging the gateway IP address
ETHERnet:SUBNETMask	Sets or returns the remote interface subnet mask value

# **File System Command Group**

Use the commands in the File System Command Group to access USB media. You can use the commands to do the following:

- List the contents of a directory
- Create, rename and delete directories
- Create, read, rename, or delete a file
- Format media

When using these commands, keep the following points in mind:

- File arguments are always enclosed within double quotes: "E:/MYDIR/TEK00001.SET"
- File names follow the non-case sensitive, MSDOS format: [DRIVE:][\PATH\]filename
- File names for commands and queries are not case sensitive. Save commands translate all file names to uppercase for storage

For Example: SAVE:WAVEFORM CH1,"ch1.isf" results in Ch1 being saved to a file named CH1.ISF.

RECALL: WAVEFORM "Ch1.isf", REF1 would recall the waveform from the file CH1.ISF to the REF1 internal waveform storage location.

- Path separators may be either forward slashes (/) or back slashes (\)
- The file and directory names have no more than eight characters as the base name, and no more than three characters as the extension as in 8.3 format

**NOTE.** Using back slash as a path separator may produce some unexpected results, depending on how your application treats escaped characters. Many applications recognize the sequence of back slash followed by an alphabetic character as an escaped character, and, as such, interpret that alphabetic character as a control character. For example, the sequence "\n" may be interpreted as a newline character; "\t" may be interpreted as a tab character. To ensure that this interpretation does not occur, you can use double back slashes. For example, "E:\\testfile.txt".

Table 2-20: File System Commands

Command	Description
FILESystem	Returns the file system state
FILESystem:CWD	Sets or returns the current working directory for FILESystem commands.
FILESystem:DELEte	Deletes a named file or directory
FILESystem:DIR?	Returns a list of directory contents
FILESystem:FORMat	Formats a named drive
FILESystem:FREESpace?	Returns the number of bytes of free space on the current drive
FILESystem:MKDir	Creates a new directory
FILESystem:READFile	Writes the contents of the specified file to the specified interface
FILESystem:REName	Assigns a new name to an existing file
FILESystem:RMDir	Deletes a named directory
FILESystem:WRITEFile	Writes the specified block data to the oscilloscope current working directory

## FilterVu Command Group

Use the commands in the FilterVu Command Group to set up the FilterVu feature. FilterVu provides a variable low pass filter to block unwanted noise while still displaying high frequency events. The oscilloscope does this by superimposing a filtered foreground waveform over a glitch capture background waveform.

Table 2-21: FilterVuCommands

Command	Description
DISplay:GLITch	Controls the display of the glitch capture waveform
DISplay:INTENSITy:GLITch	Sets the glitch intensity on the display

Table 2-21: FilterVuCommands (cont.)

Command	Description
FILTERVu:FREQuency	Sets or queries the FilterVu frequency
FILTERVu:FREQuency:AVAILable?	Returns a comma separated list of filter frequencies available based on the current instrument settings

For more information, refer to Appendix B: Waveform Data in DPO/MSO2000 Series Instruments. (See page 3-1.)

# **Hard Copy Command Group**

Use the commands in the Hard Copy Command Group to make hard copies.

Table 2-22: Hard Copy Commands

Command	Description
HARDCopy	Sends a copy of the screen display to the selected printer
HARDCopy:INKSaver	Changes hard copy output to print color traces and graticule on a white background
HARDCopy:PREVIEW	Previews the current screen contents with the InkSaver palette applied

# **Horizontal Command Group**

Use the commands in the Horizontal Command Group to control the oscilloscope time bases. You can set the time-per-division of the main time base. You can also use the Horizontal commands to set the scale, horizontal position, and reference of the time base.

**Table 2-23: Horizontal Commands** 

Command	Description
HORizontal?	Returns settings for the horizontal commands
HORizontal:ACQLENGTH?	Returns the record length
HORizontal:DELay:MODe	Sets or returns the horizontal delay mode
HORizontal:DELay:TIMe	Sets or returns the horizontal delay time
HORizontal:DIGital:RECOrdlength:MAIN?	Returns the record length of the main digital acquisition
HORizontal:DIGital:SAMPLERate:MAIN?	Returns the sample rate of the main digital acquisition
HORizontal:POSition	Sets or returns the horizontal position
HORizontal:PREViewstate?	Returns whether or not the acquisition system is in the preview state
HORizontal:RECOrdlength	Sets the horizontal record length to the number of data points in each frame
	Or returns the current horizontal record length
HORizontal:RESOlution	Sets or returns the horizontal record length to the number of data points in each frame
HORizontal:SAMPLERate	Sets or returns the current horizontal sample rate
HORizontal:SCAle	Sets or returns the time base horizontal scale
HORizontal:TRIGger:POSition	Sets the horizontal position when delay mode is OFF

# **Mark Command Group**

Use the commands in the Mark Command Group to identify areas of the acquired waveform that warrant further investigation.

**Table 2-24: Mark Commands** 

Command	Description
MARK	Move to the next or previous mark on the waveform or returns all learnable settings from the mark commands

Table 2-24: Mark Commands (cont.)

Command	Description
MARK:CREATE	Creates a mark on a particular waveform or all waveforms in a column
MARK:DELEte	Deletes a mark on a particular waveform, all waveforms in a column, or all marks
MARK:FREE?	Returns how many marks are free to be used
MARK:SELected:END?	Returns the end of the selected mark, in terms of 0 to 100% of the waveform
MARK:SELected:FOCUS?	Returns the focus of the selected mark, in terms of 0 to 100% of the waveform
MARK:SELected:MARKSINCOLumn?	Returns how many marks are in the current zoom pixel column
MARK:SELected:OWNer?	Returns the owner of the selected mark
MARK:SELected:SOURCE?	Returns the source waveform of the selected mark
MARK:SELected:STARt?	Returns the start of the selected mark, in terms of 0 to 100% of the waveform
MARK:SELected:STATe?	Returns the on or off state of the selected mark
MARK:SELected:ZOOm:POSition?	Returns the position of the selected mark, in terms of 0 to 100% of the upper window
MARK:TOTal?	Returns how many marks are used

## **Math Command Group**

Use the commands in the Math Command Group to create and define a math waveform. Use the available math functions to define your math waveform.

The math waveform you create depends on sources listed in the math expression. If you change these sources, the math waveform you previously defined will be affected.

Math expressions can be simple without any mathematical computations. For example: CH1, which specifies that a waveform shows the signal source of Channel 1.

The acquisition of a live waveform can stop for several reasons: You can turn off the channel, stop the waveform, or stop the trigger. When you turn off the channel, math continues and data is acquired but is not displayed. When you stop either the waveform or the trigger, the math calculation stops, and the last math calculation performed is displayed.

When a live waveform update or reference waveform is altered, math waveforms containing those waveforms as sources are also updated to reflect the changes. Remember that sources must exist, but do not need to be displayed, to be used in and to update math waveforms.

**Table 2-25: Math Commands** 

Command	Description
MATH[1]?	Returns the definition of the math waveform
MATH[1]:DEFine	Sets or returns the current math function as a text string
MATH[1]:HORizontal:POSition	Sets or returns the math horizontal display position for FFT or (non-live) math reference waveforms
MATH[1]:HORizontal:SCAle	Sets or returns the math horizontal display scale for FFT or for Dual Math waveforms
MATH[1]:HORizontal:UNIts	Returns the math waveform horizontal unit value
MATH[1]:LABel	Sets or queries the waveform label for the math waveform
MATH[1]:SPECTral:GATing:INDICators	Enables or disables the display of indicators that show the portion of the source waveform record used to compute the math FFT waveform
MATH[1]:SPECTral:GATing:INDICators: END?	Returns the ending point in the source waveform record used for computing the FFT
MATH[1]:SPECTral:GATing:INDICators: STARt?	Returns the starting point in the source waveform record used for computing the FFT
MATH[1]:SPECTral:MAG	Sets or returns the units of spectral magnification in the math string

Table 2-25: Math Commands (cont.)

Command	Description
MATH[1]:SPECTral:NYQUISTFreq?	Returns the Nyquist frequency of the FFT math waveform
MATH[1]:SPECTral:WINdow	Sets or returns the window function for math waveform spectral input data
MATH[1]:TYPe	Sets or returns the math waveform mode type
MATH[1]:VERTical:POSition	Sets or returns the vertical position of the currently selected math type
MATH[1]:VERTical:SCAle	Sets or returns the vertical scale of the currently selected math type
MATH[1]:VERTical:UNIts?	Returns the math waveform vertical units

## **Measurement Command Group**

Use the commands in the Measurement Command Group to control the automated measurement system.

Up to four automated measurements can be displayed on the screen. In the commands, these measurement readouts are named MEAS<x>, where <x> is the measurement number.

In addition to the four displayed measurements, the measurement commands let you specify an additional measurement, IMMed. The immediate measurement has no front-panel equivalent. Immediate measurements are never displayed. Because they are computed only when needed, immediate measurements slow the waveform update rate less than displayed measurements.

Whether you use displayed or immediate measurements, use the VALue query to obtain measurement results.

Measurement commands can set and query measurement parameters. You can assign some parameters, such as waveform sources, differently for each measurement. Other parameters, such as reference levels, have only one value, which applies to all measurements.

**Table 2-26: Measurement Commands** 

Command	Description
MEASUrement?	Returns all measurement parameters
MEASUrement:CLEARSNapshot	Removes the measurement snapshot display
MEASUrement:GATing	Sets or returns the measurement gating
MEASUrement:IMMed?	Returns all immediate measurement setup parameters

Table 2-26: Measurement Commands (cont.)

Command	Description
MEASUrement:IMMed:DELay?	Returns information about the immediate delay measurement
MEASUrement:IMMed:DELay:DIRection	Sets or returns the search direction to use for immediate delay measurements
MEASUrement:IMMed:DELay:EDGE <x></x>	Sets or returns the slope of the edge used for immediate delay "from" and "to" waveform measurements
MEASUrement:IMMed:SOUrce1	Sets or returns the "from" source for all single channel immediate measurements
MEASUrement:IMMed:SOUrce2	Sets or returns the source to measure "to" for phase or delay immediate measurements
MEASUrement:IMMed:TYPe	Sets or returns the type of the immediate measurement
MEASUrement:IMMed:UNIts?	Returns the units of the immediate measurement
MEASUrement:IMMed:VALue?	Returns the value of the immediate measurement
MEASUrement:INDICators?	Returns all measurement indicator parameters
MEASUrement:INDICators:HORZ <x>?</x>	Returns the position of the specified horizontal measurement indicator
MEASUrement:INDICators:NUMHORZ?	Returns the number of horizontal measurement indicators currently being displayed
MEASUrement:INDICators:NUMVERT?	Returns the number of vertical measurement indicators currently being displayed
MEASUrement:INDICators:STATE	Sets or returns the state of visible measurement indicators
MEASUrement:INDICators:VERT <x>?</x>	Returns the value of the specified vertical measurement indicator
MEASUrement:MEAS <x>?</x>	Returns all measurement parameters
MEASUrement:MEAS <x>:COUNt?</x>	Returns the number of values accumulated since the last statistical reset
MEASUrement:MEAS <x>:DELay?</x>	Returns the delay measurement parameters for the specified measurement
MEASUrement:MEAS <x>:DELay:DIRection</x>	Sets or returns the search direction to use for delay measurements
MEASUrement:MEAS <x>:DELay:EDGE<x></x></x>	Sets or returns the slope of the edge to use for delay "from" and "to" waveform measurements
MEASUrement:MEAS <x>:MAXimum?</x>	Returns the maximum value found since the last statistical reset

**Table 2-26: Measurement Commands (cont.)** 

Command	Description
MEASUrement:MEAS <x>:MEAN?</x>	Returns the mean value accumulated since the last statistical reset
MEASUrement:MEAS <x>:MINImum?</x>	Returns the minimum value found since the last statistical reset
MEASUrement:MEAS <x>:SOURCE[1]</x>	Sets or returns the channel from which measurements are taken
MEASUrement:MEAS <x>:SOURCE2</x>	Sets or returns the channel to which measurements are sent
MEASUrement:MEAS <x>:STATE</x>	Sets or returns whether the specified measurement slot is computed and displayed
MEASUrement:MEAS <x>:STDdev?</x>	Returns the standard deviation of values accumulated since the last statistical reset
MEASUrement:MEAS <x>:TYPe</x>	Sets or returns the measurement <x> type</x>
MEASUrement:MEAS <x>:UNIts?</x>	Returns measurement <x> units</x>
MEASUrement:MEAS <x>:VALue?</x>	Returns the value of measurement <x></x>
MEASUrement:METHod	Sets or returns the method used for calculating reference levels
MEASUrement:REFLevel?	Returns the current reference level parameters
MEASUrement:REFLevel:ABSolute:HIGH	Sets or returns the top reference level for rise time
MEASUrement:REFLevel:ABSolute:LOW	Sets or returns the low reference level for rise time
MEASUrement:REFLevel:ABSolute:MID	Sets or returns the mid reference level for measurements
MEASUrement:REFLevel:ABSolute:MID2	Sets or returns the mid reference level for delay "to" measurements
MEASUrement:REFLevel:METHod	Sets or returns the method for assigning high and low reference levels
MEASUrement:REFLevel:PERCent:HIGH	Sets or returns the top reference percent level for rise time
MEASUrement:REFLevel:PERCent:LOW	Sets or returns the low reference percent level for rise time
MEASUrement:REFLevel:PERCent:MID	Sets or returns the mid reference percent level for waveform measurements
MEASUrement:REFLevel:PERCent:MID2	Sets or returns the mid reference percent level for second waveform measurements
MEASUrement:SNAPShot	Displays the measurement snapshot list
MEASUrement:IMMed:SOUrce <x></x>	Sets or returns the source for the current single channel measurement

**Table 2-26: Measurement Commands (cont.)** 

Command	Description
MEASUrement:MEAS <x>:SOUrce<x></x></x>	Sets or returns the source for the specified measurement.
MEASUrement:REFLevel:ABSolute:MID <x></x>	Sets or returns the mid reference level for the specified channel in absolute volts
MEASUrement:REFLevel:PERCent:MID <x></x>	Sets or returns the mid reference level for the specified channel in percent

## **Miscellaneous Command Group**

Use the commands in the Miscellaneous Command Group to perform actions that do not fit into other categories.

Several commands and queries are common to all 488.2-1987 devices. The 488.2-1987 standard defines these commands. The common commands begin with an asterisk (\*) character.

Table 2-27: Miscellaneous Commands

Command	Description
AUTOSet	Sets the vertical, horizontal and trigger controls to provide a stable display of the selected waveform
CLEARMenu	Clears the current menu from the display
DATE	Sets or returns the date displayed by the oscilloscope
*DDT	Sets or returns the commands that will be executed by the group execute trigger
FPAnel:PRESS	Simulates the action of pressing a specified front-panel button
FPAnel:TURN	Duplicates the action of turning a specified front-panel control knob
GPIBUsb:ID?	Returns the identification string of the connected adaptor module and firmware version
HEADer	Sets or returns the Response Header Enable State
ID?	Returns identifying information about the oscilloscope and its firmware
*IDN?	Returns the same information as the ID? command except the data is formatted according to Tektronix Codes & Formats
LANGuage	Sets or returns the user interface display language

Table 2-27: Miscellaneous Commands (cont.)

Command	Description
LOCk	Sets or returns the front panel lock state
*LRN?	Returns a listing of oscilloscope settings
MESSage	Sets or queries message parameters
NEWpass	Changes the password for user protected data
PASSWord	Enables the *PUD and NEWpass set commands
REM	Specifies a comment, which is ignored by the oscilloscope
SET?	Returns a listing of oscilloscope settings
TEKSecure	Initializes both waveform and setup memories
TIME	Sets or returns the time displayed by the oscilloscope
TOTaluptime?	Returns the total number of hours that the oscilloscope has been turned on since the nonvolatile memory was last programmed
*TRG	Performs the group execute trigger (GET)
*TST?	Tests the interface and returns the status
UNLock	Unlocks front panel
USBTMC	Returns the USBTMC information
USBTMC:PRODUCTID:DECimal?	Returns the product ID in decimal format
USBTMC:PRODUCTID:HEXadecimal?	Returns the product ID in hexadecimal format
USBTMC:SERIALnumber?	Returns the instrument serial number
USBTMC:VENDORID:DECimal?	Returns the vendor ID in decimal format
USBTMC:VENDORID:HEXadecimal?	Returns the vendor ID in hexadecimal format
VERBose	Sets or returns the verbose state

# **PictBridge Command Group**

Use the commands in the PictBridge to store the printer settings.

Table 2-28: PictBridge Commands

Command	Description
PICTBridge:DATEPrint	Enables or disables printing the date on the print output
PICTBridge:DEFault	Sets the arguments for all PictBridge commands to their default values

Table 2-28: PictBridge Commands (cont.)

Command	Description
PICTBridge:IDPrint	Enables or disables printing the oscilloscope model and serial number on the print output
PICTBridge:IMAGESize	Sets or returns the image print size
PICTBridge:PAPERSize	Sets the output print paper size
PICTBridge:PAPERType	Sets or returns the paper type
PICTBridge:PRINTQual	Sets or returns the output print quality
USBDevice:CONFigure	Enables or disables the rear USB port for use with Pictbridge printers

## **Save and Recall Command Group**

Use the commands in the Save and Recall Command Group to store and retrieve internal waveforms and settings. When you save a setup, you save all the settings of the oscilloscope. When you recall a setup, the oscilloscope restores itself to the state it was in when you originally saved the setting.

Table 2-29: Save and Recall Commands

Command	Description
FACtory	Resets the oscilloscope to factory default settings
*RCL	Recalls saved oscilloscope settings
RECAll:SETUp	Recalls saved oscilloscope settings
RECAII:WAVEform	Recalls a stored waveform to a reference location
REF <x>:SCAle</x>	Sets or returns the vertical scale for the channel specified by <x>, where x is the reference channel number</x>
*SAV	Stores the state of the oscilloscope to a specified memory location
SAVe:ASSIgn:TYPe	Sets or returns the assignment of the data to be saved
SAVe:EVENTtable:BUS <x></x>	Saves event table data from bus <x> to a specified file and location</x>
SAVe:IMAGe	Saves a capture of the screen image into the specified file
SAVe:IMAGe:FILEFormat	Sets or returns the file format to use for saving screen images when the file type cannot be determined from the given file name or when screen images are captured by using the front panel

Table 2-29: Save and Recall Commands (cont.)

Command	Description
SAVe:IMAGe:LAYout	Sets or returns the layout to use for saved screen images
SAVe:SETUp	Saves the state of the oscilloscope to a specified memory location or file
SAVe:WAVEform	Saves a waveform to one of four reference memory locations or a file
SAVe:WAVEform:FILEFormat	Sets or returns the format for saved waveforms
SAVe:WAVEform:GATIng	Specifies whether save waveform operations should save the entire waveform or a specified portion of the waveform
SAVe:WAVEform:SPREADSheet: RESOlution	Specifies whether to save the full (LRL) or reduced (thumb) resolution waveform to a CSV file.
SETUP <x>:DATE?</x>	Returns the date when the specified oscilloscope setup was saved
SETUP <x>:LABEL</x>	Sets or returns the specified oscilloscope setup label
SETUP <x>:TIME?</x>	Returns the time when the specified oscilloscope setup was saved

# **Search Command Group**

Use the commands in the Search Commands Group to seek out information in waveform records.

#### **Search Commands**

Returns all search-related settings  Copies the search criteria to the trigger, or
the trigger criteria to the search.
Sets the search state to on or off
Returns the total number of matches for search <x></x>
Sets or returns the search condition for CAN search
Sets or returns the CAN search condition to be valid on a READ, WRITE or either
Sets or returns the CAN data qualifier
Sets or returns the length of the data string in bytes to be used for CAN search
Sets or returns the binary data string to be used for CAN search
Sets or returns the CAN Frame Type to be used
Sets or returns the CAN addressing mode to standard or extended format
Sets or returns the binary address string to be used for CAN search
Sets or returns the search condition for a LIN search
Sets or returns the binary data string
Sets or returns the LIN data qualifier
Sets or returns the length of the data string in bytes
Sets or returns the binary data string used for a LIN search
Sets or returns the error type used for a LIN Search
Sets or returns the binary address string used for LIN search

Command	Description
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:I2C:ADDRess:MODe</x></x>	Sets or returns the I2C address mode to 7 or 10-bit
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:I2C:ADDRess:TYPe</x></x>	Sets or returns the I2C address type to I2C special addresses
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:I2C:ADDRess:VALue</x></x>	Sets or returns the binary address string to be used for I2C search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:I2C:CONDition</x></x>	Sets or returns the search condition for I2C search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:I2C:DATa:DIRection</x></x>	Sets or returns the I2C search condition to be valid on a READ, WRITE or either
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:I2C:DATa:SIZe</x></x>	Sets or returns the length of the data string in bytes to be used for I2C search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:I2C:DATa:VALue</x></x>	Sets or returns the binary data string to be used for I2C search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:PARallel:VALue</x></x>	Sets or returns the binary data string to be used for a parallel trigger search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:CONDition</x></x>	Sets or returns the trigger condition for a RS232 trigger
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:RX:DATa:SIZe</x></x>	Sets or returns the length of the data string for a RS232 trigger, if the trigger condition is RX
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:RX:DATa:VALue</x></x>	Sets or returns the binary data string for a RS232 trigger, if the condition involves RX
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:TX:DATa:SIZe</x></x>	Sets or returns the length of the data string to be used for a RS232 Trigger, if the Trigger condition is TX
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:RS232C:TX:DATa:VALue</x></x>	Sets or returns the binary data string to be used for a RS232 trigger, if the condition involves RX
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:SPI:CONDition</x></x>	Sets or returns the search condition for SPI search
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:SPI:DATa{:MISO :IN}:VALue</x></x>	Sets or returns the binary data string to be used for SPI search if the search condition is MISO or MISOMOSI.
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:SPI:DATa{:MOSI :OUT}:VALue</x></x>	Sets or returns the binary data string for an SPI search if the search condition is MISO or MISOMOSI
SEARCH:SEARCH <x>:TRIGger:A:BUS: B<x>:SPI:DATa:SIZe</x></x>	Sets or returns the length of the data string in bytes to be used for SPI search
SEARCH:SEARCH <x>:TRIGger:A:BUS: SOUrce</x>	Sets or returns the bus for a serial search
SEARCH:SEARCH <x>:TRIGger:A:EDGE: SLOpe</x>	Sets or returns the slope for an edge search

Command	Description
SEARCH:SEARCH <x>:TRIGger:A:EDGE: SOUrce</x>	Sets or returns the source waveform for an edge search
SEARCH:SEARCH <x>:TRIGger:A:LEVel</x>	Sets or returns the level for an edge search
SEARCH:SEARCH <x>:TRIGger:A:LEVel: CH<x></x></x>	Sets or returns the level for an edge search of the specified channel
SEARCH:SEARCH <x>:TRIGger:A:LEVel: MATH</x>	Sets or returns the math waveform level for edge search
SEARCH:SEARCH <x>:TRIGger:A:LEVel: REF<x></x></x>	Sets or returns the reference waveform level for edge search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: FUNCtion</x>	Sets or returns the logic operator for the logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: INPut:CH<x></x></x>	Sets or returns the Boolean logic criteria for the logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: INPut:CLOCk:EDGE</x>	Sets or returns whether the clock edge is rise or fall for a logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: INPut:CLOCk:SOUrce</x>	Sets or returns the clock source definition for logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: INPut:MATH</x>	Sets or returns the Boolean logic criteria for the logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: INPut:REF<x></x></x>	Sets or returns the Boolean logic criteria for the logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: PATtern:INPut:CH<x></x></x>	Sets or returns the Boolean logic criteria for the logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: INPut:D<x></x></x>	Sets or returns the waveform logic criteria for a trigger search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: PATtern:INPut:MATH</x>	Sets or returns the Boolean logic criteria for the logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: PATtern:INPut:D<x></x></x>	Sets or returns the logic criteria for a logic pattern search to determine where to place a mark
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: PATtern:INPut:REF<x></x></x>	Sets or returns the Boolean logic criteria for the logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: PATtern:WHEn</x>	Sets or returns the condition for generating a logic pattern search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: PATtern:WHEn:LESSLimit</x>	Sets or returns the maximum time that the selected pattern may be true
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: PATtern:WHEn:MORELimit</x>	Sets or returns the minimum time that the selected pattern may be true
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: THReshold:CH<x></x></x>	Sets or returns the channel threshold level for an logic search
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: THReshold:MATH</x>	Sets or returns the math waveform threshold level for logic search

Command	Description
SEARCH:SEARCH <x>:TRIGger:A:LOGIc: THReshold:REF<x></x></x>	Sets or returns the reference waveform threshold level for logic search
SEARCH:SEARCH <x>:TRIGger:A: LOWerthreshold:CH<x></x></x>	Sets or returns the lower waveform threshold level for all channel waveform searches
SEARCH:SEARCH <x>:TRIGger:A: LOWerthreshold:MATH</x>	Sets or returns the lower waveform threshold level for all math waveform searches
SEARCH:SEARCH <x>:TRIGger:A: LOWerthreshold:REF<x></x></x>	Sets or returns the lower waveform threshold level for all reference waveform searches
SEARCH:SEARCH <x>:TRIGger:A: PULSEWidth:POLarity</x>	Sets or returns the polarity for a pulse search
SEARCH:SEARCH <x>:TRIGger:A: PULSEWidth:SOUrce</x>	Sets or returns the source waveform for a pulse search
SEARCH:SEARCH <x>:TRIGger:A: PULSEWidth:WHEn</x>	Sets or returns the condition for generating a pulse width search
SEARCH:SEARCH <x>:TRIGger:A: PULSEWidth:WIDth</x>	Sets or returns the pulse width setting for a pulse width search
SEARCH:SEARCH <x>:TRIGger:A:RUNT: POLarity</x>	Sets or returns the polarity setting for a runt search
SEARCH:SEARCH <x>:TRIGger:A:RUNT: SOUrce</x>	Sets or returns the source setting for a runt search
SEARCH:SEARCH <x>:TRIGger:A:RUNT: WHEn</x>	Sets or returns the condition setting for a runt search
SEARCH:SEARCH <x>:TRIGger:A:RUNT: WIDth</x>	Sets or returns the width setting for a runt search
SEARCH:SEARCH <x>:TRIGger:A: SETHold:CLOCk:EDGE</x>	Sets or returns the clock slope setting for a setup/hold search
SEARCH:SEARCH <x>:TRIGger:A: SETHold:CLOCk:SOUrce</x>	Sets or returns the clock source setting for an setup/hold search
SEARCH:SEARCH <x>:TRIGger:A: SETHold:CLOCk:THReshold</x>	Sets or returns the clock threshold setting for an setup/hold search
SEARCH:SEARCH <x>:TRIGger:A: SETHold:DATa:SOUrce</x>	Sets or returns the data source setting for an setup/hold search
SEARCH:SEARCH <x>:TRIGger:A: SETHold:DATa:THReshold</x>	Sets or returns the data threshold setting for an setup/hold search
SEARCH:SEARCH <x>:TRIGger:A: SETHold:THReshold:CH<x></x></x>	Sets or returns the trigger search setup and hold lower threshold to determine where to place a mark. Ch <x> is the channel number</x>
SEARCH:SEARCH <x>:TRIGger:A: SETHold:THReshold{:MATH :MATH1}</x>	Sets or returns the trigger search setup and hold lower threshold to determine where to place a mark

Command	Description
SEARCH:SEARCH <x>:TRIGger:A: SETHold:THReshold:REF<x></x></x>	Sets or returns the trigger search setup and hold lower threshold to determine where to place a mark. Ref <x> is the reference waveform number</x>
SEARCH:SEARCH <x>:TRIGger:A: SETHold:HOLDTime</x>	Sets or returns the hold time setting for an setup/hold search
SEARCH:SEARCH <x>:TRIGger:A: SETHold:SETTime</x>	Sets or returns the setup time setting for an setup/hold search
SEARCH:SEARCH <x>:TRIGger:A{: TRANsition :RISEFall}:DELTatime</x>	Sets or returns the transition time setting for an transition search
SEARCH:SEARCH <x>:TRIGger:A{: TRANsition :RISEFall}:POLarity</x>	Sets or returns the polarity setting for an transition search
SEARCH:SEARCH <x>:TRIGger:A{: TRANsition :RISEFall}:SOUrce</x>	Sets or returns the source setting for an transition search
SEARCH:SEARCH <x>:TRIGger:A{: TRANsition :RISEFall}:WHEn</x>	Sets or returns the condition setting for an transition search
SEARCH:SEARCH <x>:TRIGger:A:TYPe</x>	Sets or returns the trigger type setting for a search
SEARCH:SEARCH <x>:TRIGger:A: UPPerthreshold:CH<x></x></x>	Sets or returns the waveform upper threshold level for all channel waveform searches
SEARCH:SEARCH <x>:TRIGger:A: UPPerthreshold:MATH</x>	Sets or returns the waveform upper threshold level for all math waveform searches
SEARCH:SEARCH <x>:TRIGger:A: UPPerthreshold:REF<x></x></x>	Sets or returns the waveform upper threshold level for all reference waveform searches

# **Status and Error Command Group**

Use the commands in the Status and Error Command Group to determine the status of the oscilloscope and control events.

Several commands and queries used with the oscilloscope are common to all IEEE488.2 compliant devices. The IEEE Std 488.2-1987 defines these commands and queries. The common commands begin with an asterisk (\*) character.

Table 2-30: Status and Error Commands

Command	Description	
ALLEv?	Returns all events and their messages	
BUSY?	Returns oscilloscope status	
*CLS	Clears status	
DESE	Sets or returns the bits in the Device Event Status Enable Register	

Table 2-30: Status and Error Commands (cont.)

Command	Description
*ESE	Sets or returns the bits in the Event Status Enable Register
*ESR?	Returns the contents of the Standard Event Status Register
EVENT?	Returns event code from the event queue
EVMsg?	Returns event code, message from the event queue
EVQty?	Return number of events in the event queue
*OPC	Generates the operation complete message in the standard event status register when all pending operations are finished
	Or returns "1" when all current operations are finished
*PSC	Sets or returns the power on status flag
*PUD	Sets or returns a string of protected user data
*RST	Resets the oscilloscope to factory default settings
*SRE	Sets or returns the bits in the Service Request Enable Register
*STB?	Returns the contents of the Status Byte Register
*WAI	Prevents the oscilloscope from executing further commands until all pending operations finish

## **Trigger Command Group**

Use the commands in the Trigger Command Group to control all aspects of triggering for the oscilloscope.

There are two triggers: A and B. Where appropriate, this command set has parallel construction between triggers.

You can set the A or B triggers to edge mode. Edge triggering lets you display a waveform at or near the point where the signal passes through a voltage level of your choosing.

You can also set A triggers to pulse, logic, or video modes. With pulse triggering, the oscilloscope triggers whenever it detects a pulse of a certain width or height. Logic triggering lets you logically combine the signals on one or channels. The oscilloscope then triggers when it detects a certain combination of signal levels. Video triggering enables you to trigger on the most common Standard Definition video standards.

**Table 2-31: Trigger Commands** 

Command	Description
TRIGger	Forces a trigger event to occur
TRIGger:FREQuency?	Returns the available trigger frequency in hertz.
TRIGger:A	Sets A trigger level to 50% or returns current A trigger parameters
TRIGger:A:BUS	Sets or returns the serial trigger type
TRIGger:A:BUS:B <x>:CAN:CONDition</x>	Sets or returns the CAN condition
TRIGger:A:BUS:B <x>:CAN:DATa:DIRection</x>	Sets or returns the CAN trigger condition to be valid on a READ, WRITE, or either
TRIGger:A:BUS:B <x>:CAN:DATa:QUALifier</x>	Sets or returns the CAN data qualifier
TRIGger:A:BUS:B <x>:CAN:DATa:SIZe</x>	Sets or returns the length of the data string in bytes to be used for CAN trigger
TRIGger:A:BUS:B <x>:CAN:DATa:VALue</x>	Sets or returns the binary data string to be used for CAN trigger
TRIGger:A:BUS:B <x>:CAN:FRAMEtype</x>	Sets or returns the CAN trigger frame type
TRIGger:A:BUS:B <x>:CAN{:IDentifier :ADDRess}:MODe</x>	Sets or returns the CAN addressing mode
TRIGger:A:BUS:B <x>:CAN{:IDentifier :ADDRess}:VALue</x>	Sets or returns the binary address string used for the CAN trigger
TRIGger:A:BUS:B <x>:LIN:CONDition</x>	Sets or returns the trigger condition for LIN
TRIGger:A:BUS:B <x>:LIN:DATa:HIVALue</x>	Sets or returns the binary data string to be used for LIN trigger
TRIGger:A:BUS:B <x>:LIN:DATa:QUALifier</x>	Sets or returns the LIN data qualifier
TRIGger:A:BUS:B <x>:LIN:DATa:SIZe</x>	Sets or returns the length of the data string in bytes to be used for LIN trigger
TRIGger:A:BUS:B <x>:LIN:DATa:VALue</x>	Sets or returns the binary data string
TRIGger:A:BUS:B <x>:LIN:ERRTYPE</x>	Sets or returns the error type

Table 2-31: Trigger Commands (cont.)

Command	Description
TRIGger:A:BUS:B <x>:LIN:IDentifier:VALue</x>	Sets or returns the binary address string used for LIN trigger
TRIGger:A:BUS:B <x>:I2C:ADDRess:MODe</x>	Sets or returns the I2C address mode to 7 or 10-bit
TRIGger:A:BUS:B <x>:I2C:ADDRess:TYPe</x>	Sets or returns the I2C address type to USER
TRIGger:A:BUS:B <x>:I2C:ADDRess:VALue</x>	Sets or returns the binary address string used for the I2C trigger
TRIGger:A:BUS:B <x>:I2C:CONDition</x>	Sets or returns the trigger condition for I2C trigger
TRIGger:A:BUS:B <x>:I2C:DATa:DIRection</x>	Sets or returns the I2C trigger condition valid on a READ, WRITE, or either
TRIGger:A:BUS:B <x>:I2C:DATa:SIZe</x>	Sets or returns the length of the data string in bytes to be used for I2C trigger
TRIGger:A:BUS:B <x>:I2C:DATa:VALue</x>	Sets or returns the binary data string used for I2C triggering
TRIGger:A:BUS:B <x>:PARallel:VALue</x>	Sets or returns the binary data string to be used for a parallel trigger
TRIGger:A:BUS:B <x>:RS232C:CONDition</x>	Sets or returns the condition for a RS232C trigger
TRIGger:A:BUS:B <x>:RS232C:RX:DATa:SIZe</x>	Sets or returns the length of the data string in Bytes for a RX RS232 Trigger
TRIGger:A:BUS:B <x>:RS232C:RX:DATa:VALue</x>	Sets or returns the binary data string for a RX RS232 trigger
TRIGger:A:BUS:B <x>:RS232C:TX:DATa:SIZe</x>	Sets or returns the length of the data string for a TX RS232 trigger
TRIGger:A:BUS:B <x>:RS232C:TX:DATa:VALue</x>	Sets or returns the binary data string for a RS232 trigger if the trigger condition involves TX
TRIGger:A:BUS:B <x>:SPI:CONDition</x>	Sets or returns the trigger condition for SPI triggering
TRIGger:A:BUS:B <x>:SPI:DATa{:IN :MISO}:VALue</x>	Sets or returns the binary data string to be used for SPI trigger

Table 2-31: Trigger Commands (cont.)

Command	Description
TRIGger:A:BUS:B <x>:SPI:DATa{:OUT :MOSI}:VALue</x>	Sets or returns the binary data string used for the SPI trigger
TRIGger:A:BUS:B <x>:SPI:DATa:SIZe</x>	Sets or returns the length of the data string in bytes to be used for SPI trigger
TRIGger:A:BUS:SOUrce	Sets or returns the source for a bus trigger
TRIGger:A:EDGE?	Returns the source, coupling and source for the A edge trigger
TRIGger:A:EDGE:COUPling	Sets or returns the type of coupling for the A edge trigger
TRIGger:A:EDGE:SLOpe	Sets or returns the slope for the A edge trigger
TRIGger:A:EDGE:SOUrce	Sets or returns the source for the A edge trigger
TRIGger:A:HOLDoff?	Returns the A trigger holdoff parameters
TRIGger:A:HOLDoff:TIMe	Sets or returns the A trigger holdoff time
TRIGger:A:LEVel	Sets or returns the trigger level for the A trigger
TRIGger:A:LEVel:AUXin	Sets or returns the trigger level for the AUXIN port
TRIGger:A:LEVel:CH <x></x>	Specifies or returns the trigger level for the specified trigger channel
TRIGger:A:LEVel:D <x></x>	Sets or returns the trigger level for the specified digital channel <x>, where x is the channel number</x>
TRIGger:A:LOGIc?	Returns all A trigger logic settings
TRIGger:A:LOGIc:CLAss	Sets or returns the type of A trigger logic
TRIGger:A:LOGIc:FUNCtion	Sets or returns the logical combination of the input channels for the A logic trigger
TRIGger:A:LOGIc:INPut?	Returns the logic input values for all channels

Table 2-31: Trigger Commands (cont.)

Command	Description
TRIGger:A:LOGIc:INPut:CH <x></x>	Specifies or returns the logic setting for the specified channel
TRIGger:A:LOGIc:INPut:D <x></x>	Sets or returns the logic pattern for a trigger on digital channel <x>, where x is the channel number</x>
TRIGger:A:LOGIc:INPut:CLOCk:EDGE	Sets the polarity of the clock channel.
TRIGger:A:LOGIc:INPut:CLOCk:SOUrce	Sets or returns the channel to use as the clock source
TRIGger:A:LOGIc:PATtern?	Returns the conditions for generating an A logic pattern trigger
TRIGger:A:LOGIc:PATtern:DELTatime	Sets or returns the pattern trigger delta time value
TRIGger:A:LOGIc:PATtern:INPut:D <x></x>	Sets or returns the A logic trigger input for the specified digital channel <x>, where x is the channel number.</x>
TRIGger:A:LOGIc:PATtern:WHEn	Sets or returns the pattern logic condition on which to trigger the oscilloscope
TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit	Sets or returns the maximum time that the selected pattern may be true and still generate an A logic pattern trigger
TRIGger:A:LOGIc:PATtern:WHEn:MORELimit	Sets or returns the minimum time that the selected pattern may be true and still generate an A logic pattern trigger
TRIGger:A:LOGIc:THReshold:(CH <x> D<x>)</x></x>	Sets or queries the logic trigger threshold voltage for the specified channel
TRIGger:A:LOWerthreshold:CH <x></x>	Sets or returns the lower threshold for the channel selected
TRIGger:A:LOWerthreshold{:EXT :AUX}	Sets or returns the lower threshold for the Auxiliary input.
TRIGger:A:MODe	Sets or returns the A trigger mode
TRIGger:A:PULse?	Returns the A pulse trigger parameters

Table 2-31: Trigger Commands (cont.)

Command	Description
TRIGger:A:PULse:CLAss	Sets or returns the type of pulse on which to trigger
TRIGger:A:PULSEWIDth?	Returns the trigger A pulse width parameters
TRIGger:A:PULSEWidth:POLarity	Sets or returns the polarity for the A pulse width trigger
TRIGger:A:PULSEWidth:SOUrce	Sets or returns the source for the pulse width trigger
TRIGger:A:PULSEWidth:WHEn	Sets or returns the criteria for width specification of pulse width trigger events
TRIGger:A:PULSEWidth:WIDth	Sets or returns the width setting for the pulse width trigger
TRIGger:A:RUNT?	Returns the current A runt pulse trigger logic parameters
TRIGger:A:RUNT:POLarity	Sets or returns the polarity for the A pulse runt trigger
TRIGger:A:RUNT:SOUrce	Sets or returns the source for the A pulse trigger
TRIGger:A:RUNT:WHEn	Sets or returns the type of pulse width the trigger checks for when it uncovers a runt
TRIGger:A:RUNT:WIDth	Sets or returns the minimum width for A pulse runt trigger
TRIGger:A:SETHold?	Returns settings for setup and hold violation triggering
TRIGger:A:SETHold:CLOCk?	Returns clock edge polarity, voltage threshold and source input for setup/hold triggering
TRIGger:A:SETHold:CLOCk:EDGE	Sets or returns the clock edge polarity for setup and hold triggering
TRIGger:A:SETHold:CLOCk:SOUrce	Sets or returns the clock source for the A logic trigger setup and hold input
TRIGger:A:SETHold:CLOCk:THReshold	Sets or returns the clock voltage threshold for setup and hold trigger

Table 2-31: Trigger Commands (cont.)

Command	Description
TRIGger:A:SETHold:DATa?	Returns the voltage threshold and data source for the setup/hold trigger
TRIGger:A:SETHold:DATa:SOUrce	Sets or returns the data source for the setup and hold trigger
TRIGger:A:SETHold:DATa:THReshold	Sets or returns the data voltage threshold for setup and hold trigger
TRIGger:A:SETHold:HOLDTime	Sets or returns the hold time for the setup and hold violation triggering
TRIGger:A:SETHold:SETTime	Sets or returns the setup time for setup and hold violation triggering
TRIGger:A:SETHold:THReshold:CH <x></x>	Sets or queries the threshold for the channel
TRIGger:A:UPPerthreshold:CH <x></x>	Sets the upper threshold for the channel selected
TRIGger:A{:TRANsition :RISEFall}?	Returns the delta time, polarity, and both upper and lower threshold limits for the transition time trigger
TRIGger:A{:TRANsition :RISEFall}:DELTatime	Sets or returns the delta time used in calculating the transition value
TRIGger:A{:TRANsition :RISEFall}:POLarity	Sets or returns the polarity for the A pulse transition trigger
TRIGger:A{:TRANsition :RISEFall}:SOUrce	Sets or returns the source for transition trigger
TRIGger:A{:TRANsition :RISEFall}:WHEn	Sets or returns the relationship of delta time to transitioning signal
TRIGger:A:TYPe	Sets or returns the type of A trigger
TRIGger:A:VIDeo?	Returns the video parameters for the A trigger
TRIGger:A:VIDeo:HOLDoff:FIELD	Sets or returns the video trigger holdoff
TRIGger:A:VIDeo:LINE	Sets or returns the video line number on which the oscilloscope triggers

Table 2-31: Trigger Commands (cont.)

Command	Description
TRIGger:A:VIDeo:POLarity	Sets or returns the polarity of the A video trigger
TRIGger:A:VIDeo:SOUrce	Sets or returns the polarity of the video trigger
TRIGger:A:VIDeo:STANdard	Sets or returns the video standard
TRIGger:A:VIDeo{:SYNC :FIELD}	Sets or returns the video field trigger
TRIGger:EXTernal?	Returns external trigger parameters
TRIGger:EXTernal:PRObe	Sets or returns the attenuation factor value of the external probe connector
TRIGger:EXTernal:YUNIts?	Returns the external trigger vertical (Y) units value
TRIGger:STATE?	Returns the current state of the triggering system

## **Vertical Command Group**

Use the commands in the Vertical Command Group to control the vertical setup of all live (channel) waveforms for acquisition and to display of channel, reference, and math waveforms.

**Table 2-32: Vertical Commands** 

Command	Description
AUXin?	Returns auxiliary input parameters
AUXin:PRObe	Returns all information concerning the probe attached to auxiliary input
AUXin:PRObe:AUTOZero	Sets the TekVPI probe attached to the auxiliary input to autozero
AUXin:PRObe:COMMAND	Sets the state of the specified probe control
AUXin:PRObe:DEGAUss	Starts a degauss/autozero cycle on a TekVPI current probe attached to the auxiliary input
AUXin:PRObe:DEGAUss:STATE?	Returns the degauss state of the TekVPI current probe attached to the auxiliary input
AUXin:PRObe:FORCEDRange	Sets or returns the range of the TekVPI probe attached to the auxiliary input
AUXin:PRObe:GAIN	Sets or returns the gain factor of the probe that is attached to the auxiliary input

**Table 2-32: Vertical Commands (cont.)** 

Command	Description
AUXin:PRObe:ID:SERnumber?	Returns the serial number of the probe that is attached to the auxiliary input
AUXin:PRObe:ID:TYPE?	Returns the type of probe that is attached to the auxiliary input
AUXin:PRObe:RESistance?	Returns the resistance of the probe that is attached to the Auxiliary input
AUXin:PRObe:SIGnal	Sets or returns the input bypass setting on VPI probes that support input bypass
AUXin:PRObe:UNIts?	Returns the units of measure of the probe that is attached to the auxiliary input
CH <x>?</x>	Returns vertical parameters for the specified channel
CH <x>:BANdwidth</x>	Sets or returns the bandwidth of the specified channel
CH <x>:COUPling</x>	Sets or returns the coupling setting for the specified channel
CH <x>:DESKew</x>	Sets or returns the deskew time for the specified channel
CH <x>:IMPedance</x>	Sets or returns channel <x> input impedance</x>
CH <x>:INVert</x>	Sets or returns the invert function for the specified channel
CH <x>:LABel</x>	Sets or returns the waveform label for channel <x></x>
CH <x>:OFFSet</x>	Sets or returns the channel offset
CH <x>:POSition</x>	Sets or returns the channel vertical position
CH <x>:PRObe?</x>	Returns the gain, resistance, units, and ID of the probe that is attached to the specified channel
CH <x>:PRObe:AUTOZero</x>	Sets the TekVPI probe attached to the specified channel input to autozero
CH <x>:PRObe:COMMAND</x>	Sets the state of the specified probe control
CH <x>:PRObe:DEGAUss</x>	Starts a degauss/autozero cycle on a TekVPI current probe attached to the specified channel input
CH <x>:PRObe:DEGAUss:STATE?</x>	Returns the state of the probe degauss
CH <x>:PRObe:FORCEDRange</x>	Sets or returns the range on a TekVPI probe attached to the specified channel
CH <x>:PRObe:GAIN</x>	Sets or returns the gain factor of the probe that is attached to the specified channel
CH <x>:PRObe:ID?</x>	Returns the type and serial number of the probe that is attached to the specified channel

Table 2-32: Vertical Commands (cont.)

Command	Description
CH <x>:PRObe:ID:SERnumber?</x>	Returns the serial number of the probe that is attached to the specified channel
CH <x>:PRObe:ID:TYPE?</x>	Returns the type of probe that is attached to the specified channel
CH <x>:PRObe:RESistance?</x>	Returns the resistance of the probe that is attached to the specified channel
CH <x>:PRObe:SIGnal</x>	Sets or returns the input bypass setting of channel <x>TekVPI probe</x>
CH <x>:PRObe:UNIts?</x>	Returns the units of measure of the probe that is attached to the specified channel
CH <x>:SCAle</x>	Sets or returns the vertical scale of the specified channel
CH <x>:TERmination</x>	Sets or returns channel input termination
CH <x>:VOLts</x>	Sets or returns the vertical sensitivity for channel <x></x>
CH <x>:YUNits</x>	Sets or returns the units for the specified channel to a custom string
REF <x>?</x>	Returns reference waveform data for channel <x></x>
REF <x>:DATE?</x>	Returns the date that a reference waveform was stored
REF <x>:HORizontal:DELay:TIMe</x>	Sets or returns the horizontal position of the specified reference waveform in percent of the waveform that is displayed to the right of the center vertical graticule
REF <x>:HORizontal:SCAle</x>	Sets or returns the horizontal scale for a reference waveform
REF <x>:LABel</x>	Sets or returns the specified reference waveform label
REF <x>:POSition</x>	Sets or returns the vertical position for channel <x>, where x is the reference channel number</x>
REF <x>:TIMe?</x>	Returns the time that a reference waveform was stored
REF <x>:VERTical:POSition</x>	Sets or returns the vertical position of the specified reference waveform
REF <x>:VERTical:SCAle</x>	Sets or returns the reference waveform vertical scale in vertical units/div
SELect	Returns information on which waveforms are on or off and which waveform is selected.

Table 2-32: Vertical Commands (cont.)

Command	Description
SELect:BUS <x></x>	Turns on or off the specified bus waveform or returns whether the specified bus channel is on or off
SELect:CH <x></x>	Turns on or off the specified waveform or returns whether the specified channel is on or off
SELect:D <x></x>	Turns on the display of the digital channel <x> and resets the acquisition. <x> is the channel number</x></x>
SELect:CONTROI	Sets or returns the waveform that is selected as the implied recipient of channel-related commands
SELect:MATH[1]	Turns on or off the math waveform or returns whether the math waveform is on or off
SELect:REF <x></x>	Turns on or off the specified reference waveform or returns whether the specified reference waveform is on or off

# **Waveform Transfer Command Group**

Use the commands in the Waveform Transfer Command Group to transfer waveform data points to and from the oscilloscope. Waveform data points are a collection of values that define a waveform. One data value usually represents one data point in the waveform record. When working with envelope waveforms, each data value is either the minimum or maximum of a min/max pair.

**NOTE.** The source waveform (as specified by the DATa:SOUrce) must be turned on for the following queries to return a response:

CURVe?

DATa: COMPosition: AVAILable?

WAVFrm?

WFMOutpre: RECOrdlength?

WFMOutpre:FILTERFreq?

WFMOutpre:NR Pt?

WFMOutpre:PT Fmt?

WFMOutpre:PT ORder?

WFMOutpre:XUNit?

WFMOutpre:XINcr?

WFMOutpre:XZEro?

WFMOutpre:PT Off?

WFMOutpre: YUNit?

WFMOutpre: YMUlt?

WFMOutpre: YOFf?

WFMOutpre: YZEro?

Before you transfer waveform data, you must specify the data format, composition, resolution, record length, and waveform source or destination. For more information on the waveform transfer features which are unique to the DPO/MSO2000 series, refer to Appendix B: Waveform Data in DPO/MSO2000 Series Instructions.(See page 3-1.)

#### **Data Formats**

All data points for DPO models are signed integer format only. Valid data widths for CH1–CH4, MATH, and REF1, REF2 are 1 and 2-byte widths. The valid data widths for the digital collection (MSO models) is either 4 or 8-byte widths.

The oscilloscope can transfer waveform data in either ASCII or binary format. You specify the format with the DATa:ENCdg command.

**ASCII Data.** ASCII data is represented by signed integer values. The range of the values depends on the byte width specified. One byte wide data ranges from -128 to 127. Two byte wide data ranges from -32768 to 32767.

Each data value requires two to seven characters. This includes one to five characters to represent the value, another character, if the value is negative, to represent a minus sign, and a comma to separate the data points.

An example ASCII waveform data string may look like this:

**NOTE.** You can use ASCII to obtain a readable and easier to format output than binary. However, the oscilloscope may require bytes to send the same values with ASCII than with binary, reducing transmission speed.

The use of ASCII for waveform data transfer is inefficient. ASCII-formatted Waveform (WAVFRM?) and Curve (CURVE?) queries, exceeding 1 M points, are not supported.

**Binary Data.** Binary data is represented by signed integer or positive integer values. The range of the values depends on the byte width specified. When the byte width is one, signed integer data ranges from -128 to 127, and positive integer values range from 0 to 255. When the byte width is two, the values range from -32768 to 32767. and positive integer values range from 0 to 65,535.

Table 2-33: Binary data ranges

Byte width	Signed integer range	Positive integer range
1	-128 to 127	0 to 255
2	32,768 to 32,767	0 to 65,535

The defined binary formats also specify the order in which the bytes are transferred. The four binary formats are RIBinary, RPBinary, SRIbinary, and SRPbinary.

RIBinary is signed integer where the most significant byte is transferred first, and RPBinary is positive integer where the most significant byte is transferred first. SRIbinary and SRPbinary correspond to RIBinary and RPBinary respectively but use a swapped byte order where the least significant byte is transferred first. The byte order is ignored when DATa: WIDth is set to 1.

### Waveform Data and Record Lengths

You can transfer multiple points for each waveform record. You can transfer a portion of the waveform or you can transfer the entire record. You can use the DATa:STARt and DATa:STOP commands to specify the first and last data points of the waveform record.

When transferring data into the oscilloscope, you must first specify the record length of the destination waveform record. You do this with the WFMInpre:NR Pt

command. Next, specify the first data point within the waveform record. For example, when you set DATa:STARt to 1, data points will be stored starting with the first point in the record. The oscilloscope will ignore the value set by DATa:STOP when reading in data. It will stop reading data when there is no data to read or when it has reached the specified record length.

When transferring data from the oscilloscope, you must specify the first and last data points in the waveform record. Setting DATa:STARt to 1 and DATa:STOP to the record length will always return the entire waveform.

# Waveform Data Locations and Memory Allocation

The DATa:SOUrce command specifies the waveform source when transferring a waveform from the oscilloscope. You can only transfer one waveform at a time. Waveforms sent to the oscilloscope are always stored in one of the reference memory locations. Use the DATa:DESTination command to specify a reference memory location.

#### **Waveform Preamble**

Each waveform you transfer has an associated waveform preamble, which contains information such as horizontal scale, vertical scale, and the other settings in effect when the waveform was created. Refer to the individual WFMInpre and WFMOutpre commands for information.

#### **Scaling Waveform Data**

Once you transfer the waveform data to the controller, you can convert the data points into voltage values for analysis using information from the waveform preamble.

### Transferring Waveform Data from the Oscilloscope

You can transfer waveforms from the oscilloscope to an external controller using the following sequence:

- 1. Select the waveform source(s) using DATa:SOUrce.
- 2. Specify the waveform data format using DATa:ENCdg.
- 3. Specify the number of bytes per data point using WFMOutpre:BYT Nr.
- **4.** Specify the portion of the waveform that you want to transfer using DATa:STARt and DATa:STOP.
- **5.** Transfer waveform preamble information using the WFMOutpre? query.
- **6.** Transfer waveform data from the oscilloscope using the CURVe? query.

# Transferring Waveform Data to the Oscilloscope

You can transfer waveforms to the oscilloscope from an external controller using the following sequence:

- 1. Specify the reference waveform using DATa:DESTination.
- 2. Specify the record length of the reference waveform using WFMPre:NR Pt.
- 3. Specify the waveform data format using WFMInpre:ENCdg.
- **4.** Specify the number of bytes per data point using WFMInpre:BYT\_Nr.
- 5. Specify first data point in the waveform record using DATa:STARt.
- **6.** Transfer waveform preamble information using WFMInpre.
- 7. Transfer waveform data to the oscilloscope using CURVe.

**Table 2-34: Waveform Transfer Commands** 

specified by DATa:DESTination) The query format transfers waveform data from oscilloscope specified by the DATa:SOUrce command  DATa  Sets the format and location of the waveform data that is transferred with the CURVe Command Or returns the format and location of the waveform data that is transferred with the CURVe Command  DATa:COMPosition  DATa:COMPosition  DATa:COMPosition:AVAILable?  Lists the waveform data types that are available for return from the instrument under the current instrument settings  DATa:DESTination  DATa:DESTination  Sets or returns the reference waveform for storing waveform data sent to the oscilloscope  DATa:ENCdg  Sets or returns the format of outgoing waveform data  DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform	Command	Description
data from oscilloscope specified by the DATa:SOUrce command  DATa  Sets the format and location of the waveform data that is transferred with the CURVe Command  Or returns the format and location of the waveform data that is transferred with the CURVe? command  DATa:COMPosition  DATa:COMPosition:AVAILable?  Lists the waveform data types that are available for return from the instrument under the current instrument settings  DATa:DESTination  DATa:ENCdg  DATa:ENCdg  Sets or returns the format of outgoing waveform data  DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  DATa:STARt  Sets or returns the starting point in waveform	CURVe	data to the oscilloscope (reference waveform
data that is transferred with the CURVe Command  Or returns the format and location of the waveform data that is transferred with the CURVe? command  DATa:COMPosition  Sets or returns the type of data that the CURVe? query returns  DATa:COMPosition:AVAILable?  Lists the waveform data types that are available for return from the instrument under the current instrument settings  DATa:DESTination  Sets or returns the reference waveform for storing waveform data sent to the oscilloscope  DATa:ENCdg  Sets or returns the format of outgoing waveform data  DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform		data from oscilloscope specified by the
waveform data that is transferred with the CURVe? command  DATa:COMPosition  Sets or returns the type of data that the CURVe? query returns  DATa:COMPosition:AVAILable?  Lists the waveform data types that are available for return from the instrument under the current instrument settings  DATa:DESTination  Sets or returns the reference waveform for storing waveform data sent to the oscilloscope  DATa:ENCdg  Sets or returns the format of outgoing waveform data  DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform	DATa	data that is transferred with the CURVe
DATa:COMPosition:AVAILable?  Lists the waveform data types that are available for return from the instrument under the current instrument settings  DATa:DESTination  Sets or returns the reference waveform for storing waveform data sent to the oscilloscope  DATa:ENCdg  Sets or returns the format of outgoing waveform data  DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform		waveform data that is transferred with the
available for return from the instrument under the current instrument settings  DATa:DESTination  Sets or returns the reference waveform for storing waveform data sent to the oscilloscope  DATa:ENCdg  Sets or returns the format of outgoing waveform data  DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform	DATa:COMPosition	
for storing waveform data sent to the oscilloscope  DATa:ENCdg  Sets or returns the format of outgoing waveform data  DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform	DATa:COMPosition:AVAILable?	available for return from the instrument under
DATa:RESOlution  Sets or returns whether the CURVE query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce  Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform	DATa:DESTination	for storing waveform data sent to the
returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).  DATa:SOUrce Sets or returns the location of waveform data transferred from the oscilloscope  DATa:STARt Sets or returns the starting point in waveform	DATa:ENCdg	
transferred from the oscilloscope  DATa:STARt  Sets or returns the starting point in waveform	DATa:RESOlution	returns full resolution records (acquired data) or reduced resolution records
	DATa:SOUrce	Sets or returns the location of waveform data transferred from the oscilloscope
"unioioi	DATa:STARt	Sets or returns the starting point in waveform transfer

Table 2-34: Waveform Transfer Commands (cont.)

Command	Description
DATa:STOP	Sets or returns the ending data point in waveform transfer
WAVFrm?	Returns a branch query containing waveform data in either binary or ASCII format, waveform formatting data, and the location of the waveform data source
WFMInpre?	Returns the waveform formatting specification to be applied to the next incoming CURVE command data
WFMInpre:BIT_Nr	Sets or returns the number of bits per binary waveform point for the incoming waveform
WFMInpre:BN_Fmt	Sets or returns the format of binary data for the incoming waveform
WFMInpre:BYT_Nr	Sets or returns the data width for the incoming waveform
WFMInpre:BYT_Or	Sets or returns the byte order of waveform points for the incoming waveform
WFMInpre:COMPosition	Sets and queries the type of waveform data to be transferred to the instrument with the CURVe? command.
WFMInpre:FILTERFreq	Sets or returns the byte order of waveform points for the outgoing waveform
WFMInpre:ENCdg	Sets or returns the type of encoding for incoming waveform data
WFMInpre:NR_Pt	Sets or returns the number of points in the incoming waveform record
WFMInpre:PT_Fmt	Sets or returns the point format of incoming waveform data
WFMInpre:PT_Off	This query always returns a 0
WFMInpre:XINcr	Sets or returns the horizontal sampling interval between incoming waveform points
WFMInpre:XUNit	Sets or returns the horizontal units of the incoming waveform
WFMInpre:XZEro	Sets or returns the time of the first point in the incoming waveform
WFMInpre:YMUIt	Sets or returns the vertical scale factor, per digitizing level, of the incoming waveform points
WFMInpre:YOFf	Sets or returns the vertical position of the incoming waveform in digitizing levels
WFMInpre:YUNit	Sets or returns the vertical units of the incoming waveform

Table 2-34: Waveform Transfer Commands (cont.)

Command	Description
WFMInpre:YZEro	Sets or returns the vertical offset of the incoming waveform
WFMOutpre?	Returns the waveform formatting data for the waveform specified by the DATa:SOUrce command
WFMOutpre:BYT_Or	Sets or returns which byte of binary waveform data is transmitted first, during a waveform data transfer, when data points require more than one byte.
WFMOutpre:BIT_Nr	Sets or returns the number of bits per waveform point that outgoing waveforms contain
WFMOutpre:BN_Fmt	Sets or returns the format of binary data for the outgoing waveform
WFMOutpre:BYT_Nr	Sets or returns the data width for the outgoing waveform
WFMOutpre:COMPosition	Controls or indicates the type of data used by the CURVe? query.
WFMOutpre:ENCdg	Sets or returns the type of encoding for outgoing waveforms
WFMOutpre:FILTERFreq?	Specifies or returns the FilterVu low pass filter frequency, which was applied to the waveform being sent to the instrument.
WFMOutpre:NR_Pt?	Returns the number of points for the waveform transmitted in response to a CURVe? query
WFMOutpre:PT_Fmt?	Returns the point format for the outgoing waveform
WFMOutpre:PT_Off?	This query always returns a 0 if the waveform specified by DATA:SOUrce is on or displayed
WFMOutpre:PT_ORder?	This query always returns LINEAR.
WFMOutpre:RECOrdlength?	Returns the record length for the source waveform as specified by the DATa:SOUrce command.
WFMOutpre:WFld?	Returns a string describing the acquisition parameters for the outgoing waveform
WFMOutpre:XINcr?	Returns the horizontal sampling interval for the outgoing waveform
WFMOutpre:XUNit?	Returns the horizontal units for the outgoing waveform
WFMOutpre:XZEro?	Returns the time of the first point in the outgoing waveform

Table 2-34: Waveform Transfer Commands (cont.)

Command	Description
WFMOutpre:YMUIt?	Returns the vertical scale factor per digitizing level for the outgoing waveform
WFMOutpre:YOFf?	Returns the vertical position in digitizing levels for the outgoing waveform
WFMOutpre:YUNit?	Returns the vertical units for the outgoing waveform
WFMOutpre:YZEro?	Returns the vertical offset for the outgoing waveform

For more information, refer to Appendix B: Waveform Data in DPO/MSO2000 Series Instructions.(See page 3-1.)

## **Zoom Command Group**

Use the commands in the Zoom Command Group to expand and position the waveform display horizontally and vertically, without changing the time base.

**Table 2-35: Zoom Commands** 

Description
Returns the current horizontal positioning and scaling of the display
Sets or returns the zoom mode
Returns the current horizontal positioning and scaling of the display
Returns the zoom factor of a particular zoom box
Sets or returns the horizontal zoom position for the specified waveform in the specified zoom
Sets or returns the horizontal zoom scale of the specified waveform in the specified zoom
Sets or returns the horizontal zoom position for the specified waveform in the specified zoom
Sets or returns the horizontal zoom scale of the specified waveform in the specified zoom
Specifies or returns a trace as zoomed, on or off

# **Commands Listed in Alphabetical Order**

## **ACQuire?** (Query Only)

Returns the following current acquisition parameters:

- Stop after
- Acquisition state
- Mode
- Number of averages
- Sampling mode

**Group** Acquisition

Syntax ACQuire?

Related Commands ACQuire:MODe, ACQuire:NUMACq?, ACQuire:NUMAVg,

ACQuire:STOPAfter

**Examples** ACQuire? might return ACQUIRE:STOPAFTER RUNSTOP;STATE 1;MODE

SAMPLE; NUMAVG 16; SAMPLINGMODE RT

## **ACQuire: MAXSamplerate? (Query Only)**

Returns the maximum real-time sample rate, which is the same across all

DPO/MSO2000 series models.

**Group** Acquisition

**Syntax** ACQuire:MAXSamplerate?

**Examples** ACQUIRE: MAXSAMPLERATE? might return 1.0000E+9 in a DPO2024 instrument

indicating that the maximum real-time sample rate is 1 GS/s.

ACQuire:MODe

Sets or returns the acquisition mode of the oscilloscope for all live waveforms.

Waveforms are the displayed data point values taken from acquisition intervals. Each acquisition interval represents a time duration set by the horizontal scale (time per division). The oscilloscope sampling system always samples at the maximum rate, so the acquisition interval may include than one sample.

The acquisition mode (which you set using this ACQuire:MODe command) determines how the final value of the acquisition interval is generated from the many data samples.

**Group** Acquisition

**Syntax** ACQuire:MODe {SAMple|AVErage}

ACQuire:MODe?

Related Commands ACQuire: NUMAVg, CURVe

**Arguments** 

SAMple specifies that the displayed data point value is the first sampled value that is taken during the acquisition interval. In sample mode, all waveform data has 8 bits of precision. You can request 16 bit data with a CURVe query but the lower-order 8 bits of data will be zero. SAMple is the default mode.

AVErage specifies averaging mode, in which the resulting waveform shows an average of SAMple data points from several separate waveform acquisitions. The oscilloscope processes the number of waveforms you specify into the acquired waveform, creating a running exponential average of the input signal. The number of waveform acquisitions that go into making up the average waveform is set or queried using the ACQuire:NUMAVg command.

**Examples** 

ACQUIRE: MODE AVErage sets an average acquisition mode indicating that the resulting waveform is the average of the specified number of waveform acquisitions.

ACQUIRE: MODE? might return: ACQUIRE: MODE AVERAGE indicating that the displayed waveform is the average of the specified number of waveform acquisitions.

## ACQuire: NUMACq? (Query Only)

The acquisition number will continue to increase while acquisitions are running until there is a reset. Starting and stopping acquisitions do not cause this number to reset. For example, if acquisitions are running, the acquisition count will increase (assuming the oscilloscope is triggering). If you stop the acquisitions, the acquisition number will freeze at a given number (For example: 5000). If you

start acquisitions again, it will continue from 5000. The number will reset to 0 only if you change the horizontal scale while acquisitions are running.

**Group** Acquisition

**Syntax** ACQuire: NUMACq?

Related Commands ACQuire: STATE

Returns ACQuire: NUMACq? might return: ACQUIRE: NUMACQ 350 indicating that 350

acquisitions have occurred.

**ACQuire:NUMAVg** 

Sets or returns the number of waveform acquisitions that make up an averaged waveform. Use the ACQuire:MODe command to enable the Average mode. Sending this command is equivalent to turning a multipurpose knob to enter the

number of waveform acquisitions to average.

**Group** Acquisition

Syntax ACQuire: NUMAVg < NR1>

ACQuire: NUMAVg?

Related Commands ACQuire:MODe

**Arguments** <NR1> is the number of waveform acquisitions to average. The range of values is

from 2 to 512 in powers of two.

**Examples** ACQUIRE: NUMAVG 16 specifies that 16 waveform averages will be performed

before exponential averaging starts.

ACQUIRE: NUMAVG? might return: ACQUIRE: NUMAVG 64 indicating that there

are 64 acquisitions specified for averaging.

**ACQuire:STATE** 

Starts or stops acquisitions. When state is set to ON or RUN, a new acquisition will be started. If the last acquisition was a single acquisition sequence, a new

single sequence acquisition will be started. If the last acquisition was continuous, a new continuous acquisition will be started.

If RUN is issued in the middle of completing a single sequence acquisition (for example, averaging or enveloping), the acquisition sequence is restarted, and any accumulated data is discarded. Also, the oscilloscope resets the number of acquisitions. If the RUN argument is issued while in continuous mode, acquisition continues.

**Group** Acquisition

Syntax ACQuire:STATE {OFF|ON|RUN|STOP|<NR1>}

ACQuire:STATE?

**Related Commands** ACQuire:STOPAfter

**Arguments** OFF stops acquisitions.

STOP stops acquisitions.

ON starts acquisitions.

RUN starts acquisitions.

<NR1> = 0 stops acquisitions; any other value starts acquisitions.

**Examples** ACQUIRE: STATE RUN starts the acquisition of waveform data.

ACQUIRE: STATE? might return: ACQUIRE: STATE 0 indicating that the

acquisition is stopped.

### **ACQuire:STOPAfter**

Sets or returns whether the oscilloscope continually acquires acquisitions or

acquires a single sequence.

**Group** Acquisition

Syntax ACQuire:STOPAfter {RUNSTop|SEQuence}

ACQuire:STOPAfter?

Related Commands ACQuire:STATE

**Arguments** RUNSTop specifies that the oscilloscope will continually acquire data, if

ACQuire: STATE is turned on.

**SEQuence** specifies that the next acquisition will be a single-sequence acquisition.

**Examples** ACQUIRE: STOPAFTER RUNSTop sets the oscilloscope to continually acquire data.

ACQUIRE: STOPAFTER? might return: ACQUIRE: STOPAFTER SEQUENCE indicating that the next acquisition the oscilloscope makes will be of the

single-sequence type.

**ALlas** 

Sets or returns the state of alias functionality. Use Alias commands to define new commands as a sequence of standard commands. You may find this useful when repeatedly using the same commands to perform certain tasks like setting up measurements. Aliases are similar to macros but do not include the capability to

substitute parameters into alias bodies.

To use Alias commands, first define the alias, then turn on the alias state.

**Group** Alias

Syntax ALIas {OFF|ON|<NR1>}

ALIas?

Related Commands ALIas:DEFine

ALIas[:STATE]

#### **Arguments**

OFF turns alias expansion off. If a defined alias is sent when ALIas is off, a command error (110) will be generated.

ON turns alias expansion on. When a defined alias is received, the specified command sequence is substituted for the alias and executed.

<NR1> = 0 disables alias mode; any other value enables alias mode.

#### **Examples**

ALIAS ON turns the alias feature on. When a defined alias is received, the specified command sequence is substituted for the alias and executed.

ALIAS? might return: ALIAS 1 indicating that the alias feature is on.

## ALIas:CATalog? (Query Only)

Returns a list of the currently defined alias labels, separated by commas. If no aliases are defined, the query returns the string "".

**Group** Alias

**Syntax** ALIas:CATalog?

#### **Examples**

ALIAS:CATALOG? might return the string :ALIAS:CATALOG "SETUP1", "TESTMENU1", "DEFAULT" showing that there are three aliases named SETUP1, TESTMENU1, and DEFAULT.

#### **ALlas:DEFine**

Assigns a sequence of program messages to an alias label. These messages are then substituted for the alias whenever it is received as a command or query, provided that ALIas:STATE has been turned on. The query form of this command returns the definitions of a selected alias.

**NOTE.** Attempting to give two aliases the same name causes an error. To give a new alias the name of an existing alias, the existing alias must first be deleted.

**Group** Alias

Syntax ALIas:DEFine <QString><,>{<QString>|<Block>}

ALIas:DEFine? <QString>

#### **Related Commands** ALIas[:STATE]

**Arguments** The first **<QString>** is the alias label.

This label cannot be a command name. Labels must start with a letter and can contain only letters, numbers, and underscores; other characters are not allowed. The label must be less than or equal to 12 characters.

The second<QString> or <Block> is a complete sequence of program messages.

The messages can contain only valid commands that must be separated by semicolons and must follow all rules for concatenating commands. The sequence must be less than or equal to 256 characters.

Examples AL3

ALIAS:DEFINE "ST1",":RECALL:SETUP 5;:AUTOSET

EXECUTE;:SELECT:CH1 ON" defines an alias named "ST1" that sets

up the oscilloscope.

ALIAS:DEFINE? "ST1" returns :ALIAS:DEFINE "ST1",#246 :RECALL:SETUP 5;:AUTOSET EXECUTE;:SELECT:CH1 ON

## ALIas:DELEte (No Query Form)

Removes a specified alias and is identical to ALIas:DELEte:NAMe. An error message is generated if the named alias does not exist.

**Group** Alias

Syntax ALIas:DELEte <QString>

Related Commands \*ESR?, ALIas:DELEte:ALL

**Arguments** <QString> is the name of the alias to be removed. Using ALIas:DELEte

without specifying an alias causes an execution error. <QString> must be a

previously defined value.

**Examples** ALIAS: DELETE "SETUP1" deletes the alias named SETUP1.

## ALIas:DELEte:ALL (No Query Form)

Deletes all existing aliases.

**Group** Alias

Syntax ALIas:DELEte:ALL

**Related Commands** ALIas:DELEte, ALIas:DELEte[:NAMe]

**Examples** ALIAS: DELETE: ALL deletes all existing aliases.

## ALIas:DELEte[:NAMe] (No Query Form)

Removes a specified alias. This command is identical to ALIas:DELEte

**Group** Alias

Syntax ALIas:DELEte[:NAMe] <QString>

**Arguments** <QString> is the name of the alias to remove. Using ALIas:DELEte[:NAMe]

without specifying an alias causes an execution error. <QString> must be an

existing alias.

**Examples** ALIAS:DELETE[:NAME] "STARTUP" deletes the alias named STARTUP.

ALIas[:STATE]

Turns aliases on or off. This command is identical to the ALIas command.

**Group** Alias

Syntax ALIas[:STATE] {<NR1>|OFF|ON}

ALIas[:STATE]?

**Arguments** OFF or  $\langle NR1 \rangle = 0$  turns alias expansion off. If a defined alias is sent when

ALIas:STATE is OFF, a command error (102) is generated.

ON or <NR1>0 turns alias expansion on. When a defined alias is received, the

specified command sequence is substituted for the alias and executed.

**Examples** ALIAS[:STATE] OFF turns the command alias feature off.

ALIAS[:STATE]? returns 0 when the alias feature is off.

### **ALLEv? (Query Only)**

Prompts the oscilloscope to return all events and their messages (delimited by commas), and removes the returned events from the Event Queue. Use the \*ESR? query to enable the events to be returned. This command is similar to repeatedly sending \*EVMsg? queries to the oscilloscope.

**Group** Status and Error

Syntax ALLEV?

**Related Commands** \*ESR?, EVMsg?

**Examples** ALLEV? might return: ALLEV 2225, "Measurement error, No waveform

to measure; "420,"Query UNTERMINATED;"

# **AUTOSet (No Query Form)**

Sets the vertical, horizontal, and trigger controls of the oscilloscope to automatically acquire and display the selected waveform.

**Group** Miscellaneous

**Syntax** AUTOSet {EXECute|UNDo}

**Arguments** EXECute autosets the displayed waveform.

UNDo restores the oscilloscope settings to those present prior to the autoset

execution.

**Examples** AUTOSET EXECUTE vertical, horizontal, and trigger controls of the oscilloscope to

automatically acquire and display the selected waveform.

#### **AUTOSet:ENAble**

Enables or disables the autoset.

Group Miscellaneous

AUTOSet:ENAble {OFF|ON} AUTOSet:ENAble? **Syntax** 

**Related Commands AUTOSet** 

> **Arguments** ON enables the autoset feature.

> > OFF disables the autoset feature.

**Examples** AUTOSET: ENABLE? might return AUTOSET: ENABLE 1 indicating that autoset is

enabled.

AUTOSET: ENABLE OFF disables autoset.

**AUXin?** (Query Only)

Returns all auxiliary input parameters.

Group Vertical

**Syntax** AUXin?

AUXin:PRObe

Returns all information concerning the probe attached to auxiliary input.

Group Vertical

AUXin:PRObe **Syntax** 

AUXin: PRObe?

#### **Examples**

AUXIN:PROBE? might return AUXIN:PROBE:ID:TYPE "No Probe Detected";SERNUMBER "";:AUXIN:PROBE:UNITS "";RESISTANCE 1.0000E+6 giving information about the probe attached to the AUX In input.

## AUXin:PRObe:AUTOZero (No Query Form)

Sets the TekVPI probe attached to the Aux In input to autozero. The oscilloscope will ignore this command if the Auxiliary input does not have a TekVPI probe connected to it.

**Group** Vertical

**Syntax** AUXin:PRObe:AUTOZero {EXECute}

**Arguments** EXECute sets the probe to autozero.

Examples AUXin:PROBE:AUTOZERO EXECUTE

## AUXin:PRObe:COMMAND (No Query Form)

Sets the state of the probe control specified with the first argument to the state specified with the second argument. The commands and states are unique to the attached probe type. Only certain VPI probes support this command. See the probe documentation for how to set these string arguments.

**Group** Vertical

Syntax AUXin:PRObe:COMMAND <QString>, <QString>

**Arguments** <QString> are quoted strings specifying the probe command and value to set in

the probe attached to the auxiliary input.

**Examples** AUXIN: PROBE: COMMAND "OUTPUT", "ON" turns the output of a Tektronix

VPI-DPG probe on.

 ${\tt AUXIN:PROBE:COMMAND~``MODE",~``4-4V1MHz"} \ sets \ a \ Tektronix \ VPI-DPG$ 

probe to the 4-4V1MHz mode.

AUXIN: PROBE: COMMAND? "MODE" might return AUXIN: PROBE: COMMAND

"MODE", "4-4V1MHZ".

## AUXin:PRObe:DEGAUss (No Query Form)

Starts a degauss/autozero cycle on a TekVPI current probe attached to the Aux In input. If you send this command to a probe that does not support this function, it is ignored

**Group** Vertical

Syntax AUXin:PRObe:DEGAUSS {EXECute}

**Arguments** EXECute starts a probe degauss cycle.

**Examples** AUXin:PROBE:DEGAUSS EXECUTE degausses the probe attached to the Aux

In input.

### AUXin:PRObe:DEGAUss:STATE? (Query Only)

Returns the state of the probe degauss (NEEDED, RECOMMENDED, PASSED, FAILED, RUNNING). The command will return PASSED for probes that do not support degauss operations.

**Group** Vertical

**Syntax** AUXin:PRObe:DEGAUSS:STATE?

**Examples** AUXin:PROBE:DEGAUSS:STATE? might return:

AUXin:PROBE:DEGAUSS:STATE PASSED indicating that the probe has been

degaussed.

## AUXin:PRObe:FORCEDRange

Changes or returns the range on a TekVPI probe attached to the Aux In input.

**Group** Vertical

Syntax AUXin:PRObe:FORCEDRange <NR3>

AUXin: PRObe: FORCEDRange?

**Arguments** <NR3> is the probe range, which is probe dependent.

AUXin:PRObe:GAIN

Sets or returns the gain factor of a probe that is attached to the Aux In input.

**Group** Vertical

Syntax AUXin:PRObe:GAIN <NR3>

AUXin:PRObe:GAIN?

**Arguments** <NR3> is the probe gain, which is probe dependent.

Examples AUXin:PROBE:GAIN? might return:AUXin:PROBE:GAIN 100.0000E-3

indicating that the attached 10x probe delivers 0.1 V to the Aux In BNC for every

1.0 V applied to the probe input.

# AUXin:PRObe:ID:SERnumber? (Query Only)

Returns the serial number of the probe that is attached to the auxiliary input.

**Group** Vertical

Syntax AUXin:PRObe:ID:SERnumber?

## AUXin:PRObe:ID:TYPE? (Query Only)

Returns the type of probe that is attached to the auxiliary input.

**Group** Vertical

Syntax AUXin:PRObe:ID:TYPE?

## AUXin:PRObe:RESistance? (Query Only)

Returns the resistance of the probe attached to the front panel Aux In connector.

Vertical Group

AUXin: PRObe: RESistance? Syntax

**Examples** 

AUXin:PRObe:RESistance? might return :AUXin:PROBE:RESISTANCE 1.0000E+6 indicating that the input resistance of the probe attached to the front

panel Aux In connector is 1 M $\Omega$ .

**NOTE.** This query will return 0.0 if no probe is attached or the attached probe

does not report the input resistance.

#### AUXin:PRObe:SIGnal

This command changes the input bypass setting on VPI probes that support input bypass, for example the TCP0001. If sent to a probe that does not support input bypass, it is ignored.

Group Vertical

AUXin:PRObe:SIGnal {BYPass|PASS} Syntax

AUXin: PRObe: SIGnal?

BYPass sets the probe to Bypass mode. **Arguments** 

PASS sets the probe to Pass mode.

## AUXin:PRObe:UNIts? (Query Only)

Returns a string describing the units of measure of the probe attached to the Aux

In input.

Vertical Group

AUXin: PRObe: UNIts? **Syntax** 

**Examples** AUXin:PROBE:UNITS? might return: :AUXin:PROBE:UNITS "V" indicating

that the units of measure for the attached probe are volts.

#### **BUS**

Sets or returns the parameters for each bus. These parameters affect either the

Serial Trigger Setup or the Bus Display.

**Conditions** This command requires a DPO2AUTO, DPO2EMBD, or DPO2COMP application

module.

**Group** Bus

Syntax BUS

#### BUS:B<x>:CAN:BITRate

Sets or returns the bit rate for CAN bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:CAN:BITRate <NR1>

BUS:B<x>:CAN:BITRate?

**Arguments** <NR1> sets the bit rate to the closest bit rate supported by the instrument.

**Returns** The query always returns the numerical bit rate value.

#### BUS:B<x>:CAN:PRObe

Sets or returns the probing method to probe CAN bus  $\langle x \rangle$ , where x is the bus

number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:CAN:PRObe {CANH|CANL|RX|TX|DIFFerential}

BUS:B<x>:CAN:PRObe?

**Arguments** CANH specifies the single-ended CANH signal, as specified by the CAN standard.

CANL specifies the single-ended CANL signal, as specified by the CAN standard.

RX specifies the receive signal on the bus side of the CAN transceiver.

TX specifies the transmit signal.

DIFFerential specifies the differential CAN signal.

## BUS:B<x>:CAN:SAMPLEpoint

Sets or returns the sampling point during each bit period for bus  $\langle x \rangle$ , where x

is the bus number

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:CAN:SAMPLEpoint <NR1>

BUS:B<x>:CAN:SAMPLEpoint?

**Arguments** <NR1> is the sample point in percent. Values are limited to 25, 30, ... 70, 75.

### BUS:B<x>:CAN:SOUrce

Sets or returns the CAN bus data source for bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

Group Bus

Syntax BUS:B<x>:CAN:SOUrce {CH1|CH2|CH3|CH4|

 $\verb|D0|| \verb|D1|| \verb|D2|| \verb|D3|| \verb|D4|| \verb|D5|| \verb|D6|| \verb|D7|| \verb|D8|| \verb|D9|| \verb|D10|| \verb|D11|| \verb|D12|| \verb|D13|| \verb|D14|| \verb|D15||$ 

BUS:B<x>:CAN:SOUrce?

**Arguments** CH1-CH4 is the analog channel to use as the data source.

D0-D15 is the digital channel to use as the data source.

### BUS:B<x>:DISplay:FORMAt

Sets or returns the display format for the numerical information in the bus

waveform  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2AUTO, DPO2EMBD, or DPO2COMP application

module.

**Group** Bus

Syntax BUS:B<x>:DISplay:FORMAt {BINary|HEXadecimal|ASCII|MIXed}

BUS:B<x>:DISplay:FORMAt?

**Related Commands** BUS:B<x>:TYPE

**Arguments** BINary specifies a binary data display.

HEXadecimal specifies a hexadecimal data display.

ASCII specifies an ASCII format for RS232 only.

MIXed specifies a mixed format for LIN only.

### BUS:B<x>:I2C:ADDRess:RWINClude

Sets and returns whether the read/write bit is included in the address.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:I2C:ADDRess:RWINClude {<NR1>|OFF|ON}

BUS:B<x>:I2C:ADDRess:RWINClude?

**Arguments**  $\langle NR1 \rangle = 0$  does not include the read/write bit in the address; any other value

includes the read/write bit in the address.

OFF does not include the read/write bit in the address.

ON includes the read/write bit in the address.

**Examples** 

BUS:B1:I2C:ADDRESS:RWINCLUDE ON includes the read/write bit in the

address.

BUS:B1:I2C:ADDRESS:RWINCLUDE? might return

BUS:B1:I2C:ADDRESS:RWINCLUDE 0 indicating that the read/write bit is

not included in the address.

## BUS:B<x>:I2C{:CLOCK|:SCLK}:SOUrce

Sets or returns the I2C SCLK source for bus <x>, where x is the bus number.

**Conditions** 

This command requires a DPO2EMBD application module.

Group

Bus

**Syntax** 

BUS:B<x>:I2C{:CLOCK|:SCLK}:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:I2C{:CLOCK|:SCLK}:SOUrce?

**Arguments** 

CH1-CH4 specifies the analog channel to use as the I2C SCLK source.

D0-D15 specifies the digital channel to use as the I2C SCLK source.

## BUS:B<x>:I2C{:DATA|:SDATA}:SOUrce

Sets or returns the I2C SDATA source for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** 

This command requires a DPO2EMBD application module.

Group

Bus

**Syntax** 

BUS:B<x>:I2C{:DATA|:SDATA}:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:I2C{:DATA|:SDATA}:SOurce?

**Arguments** CH1-CH4 specifies the analog channel to use as the I2C SDATA source.

D0-D15 specifies the digital channel to use as the I2C SDATA source.

BUS:B<x>:LABel

Sets or returns the waveform label for bus < x>, where x is the bus number

1 through 4.

**Group** Bus

Syntax BUS:B<x>:LABel <Qstring>

BUS:B<x>:LABel?

**Arguments** <Qstring> is an alpha-numeric string of text, enclosed in quotes, that contains

the text label information for bus <x>. The text string is limited to 30 characters.

BUS:B<x>:LIN:BITRate

Sets or returns the bit rate for LIN.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:LIN:BITRate <NR1>

BUS:B<x>:LIN:BITRate?

**Arguments** <NR1> is the LIN bit rate.

**Examples** BUS:B1:LIN:BITRATE 9600 sets the bit rate 9600.

BUS:B1:LIN:BITRATE? might return BUS:B1:LIN:BITRATE 2400 indicating

that the bit rate is set to 2400.

BUS:B<x>:LIN:IDFORmat

Sets or returns the LIN ID format.

**Conditions** This command requires a DPO2AUTO application module.

Group Bus

Syntax BUS:B<x>:LIN:IDFORmat {NOPARity|PARity}

BUS:B<x>:LIN:IDFORmat?

**Arguments** NOPARity sets the LIN ID format to no parity.

PARity sets the LIN ID format to parity.

**Examples** BUS:B1:LIN:IDFORMAT PARITY sets the LIN ID format to parity.

BUS:B1:LIN:IDFORMAT? might return BUS:B1:LIN:IDFORMAT NOPARITY

indicating that the LIN ID format is no parity.

## BUS:B<x>:LIN:POLARity

Sets or returns the LIN polarity.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:LIN:POLARity {NORMal|INVerted}

BUS:B<x>:LIN:POLARity?

**Arguments** NORMal specifies normal LIN polarity.

INVerted specifies inverted LIN polarity.

**Examples** BUS:B1:LIN:POLARITY INVERTED sets the LIN polarity to INVERTED.

BUS:B1:LIN:POLARITY? might return BUS:B1:LIN:POLARITY NORMAL

indicating that the LIN polarity is normal.

## BUS:B<x>:LIN:SAMPLEpoint

Sets or returns the sample point (in %) at which to sample during each bit period.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:LIN:SAMPLEpoint <NR1>

BUS:B<x>:LIN:SAMPLEpoint?

**Arguments** <NR1> is the sample point (in %) at which to sample during each bit period.

**Examples** BUS:B1:LIN:SAMPLEPOINT 10 sets the sample point is at 10% of the bit period

BUS:B1:LIN:SAMPLEPOINT? might return BUS:B1:LIN:SAMPLEPOINT 50

indicating that the sample point is at 50% of the bit period

### BUS:B<x>:LIN:SOUrce

Sets or returns the LIN data source.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:LIN:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:LIN:SOUrce?

**Arguments** CH<x> specifies the LIN source channel where x is 1 to 4.

D<x> specifies the LIN source channel where x is 0 to 15.

**Examples** BUS:B1:LIN:SOURCE CH4 sets the LIN source to channel 4.

BUS:B1:LIN:SOURCE? might return BUS:B1:LIN:SOURCE CH1 indicating that

the LIN source is channel 1.

### BUS:B<x>:LIN:STANDard

Sets or returns the LIN standard.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax BUS:B<x>:LIN:STANDard {V1X|V2X|MIXed}

BUS:B<x>:LIN:STANDard?

**Arguments** V1X sets the LIN standard to V1X.

V2X sets the LIN standard to V2X

MIXed sets the LIN standard to MIXED.

**Examples** BUS:B1:LIN:STANDARD V1X sets the LIN standard is V1X.

BUS:B1:LIN:STANDARD? might return BUS:B1:LIN:STANDARD V2X

indicating that the LIN standard is V2X.

#### BUS:B<x>:PARallel:BIT<x>:SOUrce

Sets or returns the parallel bit source for  $B \le x >$ , where x is the bus number and  $Bit \le x >$  is the bit number.

**Group** Bus

Syntax BUS:B<x>:PARallel:BIT<x>:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:PARallel:BIT<x>:SOurce?

**Arguments** CH1-CH4 specifies the bit source B < x >. BIT < x > specifies the bit number.

D0-D15 specifies the bit source B<x>. BIT<x> specifies the bit number.

## BUS:B<x>:PARallel:CLOCK:EDGE

Sets or returns the parallel clock edge for bus <x>, where x is the bus number.

Group Bus

Syntax BUS:B<x>:PARallel:CLOCK:EDGE {EITher|RISing|FALling}

BUS:B<x>:PARallel:CLOCK:EDGE?

**Arguments** EIther specifies either rising or falling edge as the clock edge.

RISing specifies the rising edge as the clock edge.

FALling specifies the falling edge as the clock edge.

#### BUS:B<x>:PARallel:CLOCK:ISCLOCKed

Sets or returns the parallel bus clock function for bus <x>, where x is the bus number.

number

**Group** Bus

Syntax BUS:B<x>:PARallel:CLOCK:ISCLOCKed {YES|NO}

BUS:B<x>:PARallel:CLOCK:ISCLOCKed?

**Arguments** YES specifes that the parallel bus is clocked.

NO specifes that the parallel bus is not clocked.

#### BUS:B<x>:PARallel:CLOCK:SOUrce

Sets or returns the parallel bus source  $\langle x \rangle$ , where x is the bus number.

**Group** Bus

Syntax BUS:B<x>:PARallel:CLOCK:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:PARallel:CLOCK:SOurce?

**Arguments** CH1-CH4 specifies the channel to use as the parallel bit source.

D0-D15 specifies the digital channel to use as the parallel bit source.

### BUS:B<x>:PARallel:WIDth

Sets or returns the number of bits used for the width of the parallel bus <x>,

where x is the bus number.

**Group** Bus

Syntax BUS:B<x>:PARallel:WIDth <NR1>

BUS:B<x>:PARallel:WIDth?

**Arguments** <NR1> is the number of bits.

BUS:B<x>:POSition

Sets or returns the position of the bus  $\langle x \rangle$  waveform on the display, where x is

the bus number 1 through 4.

**Conditions** This command requires a DPO2AUTO, DPO2EMBD, or DPO2COMP application

module.

**Group** Bus

Syntax BUS:B<x>:POSition <NR3>

BUS:B<x>:POSition?

**Arguments** <NR3> specifies the position.

BUS:B<x>:RS232C:BITRate

Sets or returns the RS232 bit rate for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Bus

Syntax BUS:B<x>:RS232C:BITRate <NR1>

BUS:B<x>:RS232C:BITRate?

**Arguments** <NR1> is the bit rate in bits-per-second: 50 to 10000000. You can enter any

positive integer, and the instrument will coerce the value to the closest supported

bit rate.

#### BUS:B<x>:RS232C:DATABits

Sets or returns the number of RS232 data bits for bus  $\langle x \rangle$ , where x is the bus

number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Bus

Syntax BUS:B<x>:RS232C:DATABits {7|8|9}

BUS:B<x>:RS232C:DATABits?

**Arguments** 7 specifies seven bits in the RS232 data frame.

8 specifies eight bits in the RS232 data frame.

9 specifies nine bits in the RS232 data frame.

#### BUS:B<x>:RS232C:DELIMiter

Sets or returns the RS232 delimiting value for a packet on bus  $\langle x \rangle$ , where x

is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Bus

Syntax BUS:B<x>:RS232C:DELIMiter {NUL1|LF|CR|SPace|XFF}

BUS:B<x>:RS232C:DELIMiter?

**Arguments** NUL1 specifies 0x00.

LF specifies 0x0A.

CR specifies 0x0D.

XFF specifies 0xFF.

## BUS:B<x>:RS232C:DISplaymode

Sets or returns the display mode for the bus <x> display and event table, where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Bus

Syntax BUS:B<x>:RS232C:DISplaymode {FRAme|PACKET}

BUS:B<x>:RS232C:DISplaymode?

**Arguments** FRAme displays each frame as a single entity.

PACKET displays a group of frames terminated with a single frame defined by the

BUS:B<x>:RS232C:DELImiter command or the front panel.

## BUS:B<x>:RS232C:PARity

Sets or returns the RS232C parity for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Bus

Syntax BUS:B<x>:RS232C:PARity {NONe|EVEN|ODD}

BUS:B<x>:RS232C:PARity?

**Arguments** NONe specifies no parity.

EVEN specifies even parity.

ODD specifies odd parity.

**NOTE.** 9 data bits (BUS:B<x>:DATABITS 9) does not support parity. Changing the parity with the PI while using 9 data bits, has no effect.

## BUS:B<x>:RS232C:POLarity

Sets or returns the RS232C polarity for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

Group Bus

Syntax BUS:B<x>:RS232C:POLarity {NORMal|INVERTed}

BUS:B<x>:RS232C:POLarity?

**Arguments** NORMal sets the RS232C bus polarity to positive.

INVERTEd sets the RS232C bus polarity to negative.

#### BUS:B<x>:RS232C:RX:SOUrce

Sets or returns the RS232 RX source for bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Bus

Syntax BUS:B<x>:RS232C:RX:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:RS232C:RX:SOUrce?

**Arguments** CH1-CH4 specifies the channel to use for the RS232 RX source.

D0-D15 specifies the digital channel to use for the RS232 RX source.

### BUS:B<x>:RS232C:TX:SOUrce

Sets or returns the RS232 TX Source for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Bus

Syntax BUS:B<x>:RS232C:TX:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:RS232C:TX:SOUrce?

**Arguments** CH1-CH4 specifies the channel to use as the RS232 TX source.

D0-D15 specifies the digital channel to use as the RS232 TX source.

### BUS:B<x>:SPI:BITOrder

Sets or returns the bit order for the specified SPI bus.

**Conditions** This command requires a DPO2EMBD application module.

Group Bus

Syntax BUS:B<x>:SPI:BITOrder {LSB|MSB}

BUS:B<x>:SPI:BITOrder?

**Arguments** LSB specifies least significant bit first

MSB specifies most significant bit first

**Examples** BUS:B1:SPI:BITOrder LSB sets the bit order to LSB for the specified bus.

BUS:B1:SPI:BITOrder? might return BUS:B1:SPI:BITOrder MSB

indicating that the returned bit order for the specified bus is MSB.

### BUS:B<x>:SPI{:CLOCK|:SCLK}:POLARity

Sets or returns the SPI SCLK polarity for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI{:CLOCK|:SCLK}:POLARity {FALL|RISe}

BUS:B<x>:SPI{:CLOCK|:SCLK}:POLARity?

**Arguments** FALL specifies the falling edge.

RISe specifies the rising edge.

# BUS:B<x>:SPI{:CLOCK|:SCLK}:SOUrce

Sets or returns the SPI SCLK source for bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI{:CLOCK|:SCLK}:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:SPI{:CLOCK|:SCLK}:SOUrce?

**Arguments** CH1-CH4 is the channel to use as the SPI SCLK source.

D0-D15 is the digital channel to use as the SPI SCLK source.

## BUS:B<x>:SPI:DATA{:IN|:MISO}:POLARity

Sets or returns the SPI MISO polarity for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI:DATA{:IN|:MISO}:POLARity {LOW|HIGH}

BUS:B<x>:SPI:DATA{:IN|:MISO}:POLARity?

**Arguments** LOW specifies an active low polarity.

HIGH specifies an active high polarity.

### BUS:B<x>:SPI:DATA{:IN|:MISO}:SOUrce

Sets or returns the SPI MISO source for bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI:DATA{:IN|:MISO}:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:SPI:DATA{:IN|:MISO}:SOUrce?

**Arguments** CH1-CH4 is the channel to use as the SPI MISO source.

D0-D15 is the digital channel to use as the SPI MISO source.

## BUS:B<x>:SPI:DATA{:OUT|:MOSI}:POLARity

Sets or returns the SPI MOSI polarity for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

Group Bus

Syntax BUS:B<x>:SPI:DATA{:OUT|:MOSI}:POLARity {LOW|HIGH}

BUS:B<x>:SPI:DATA{:OUT|:MOSI}:POLARity?

**Arguments** LOW specifies the active low polarity.

HIGH specifies the active high polarity.

## BUS:B<x>:SPI:DATA{:OUT|:MOSI}:SOUrce

Sets or returns the SPI MOSI source for bus <x, where x is the bus number>.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI:DATA{:OUT|:MOSI}:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:SPI:DATA{:OUT|:MOSI}:SOUrce?

**Arguments** CH1-CH4 is the channel to use as the SPI MISO source.

D0-D15 is the digital channel to use as the SPI MISO source.

### BUS:B<x>:SPI:DATA:SIZe

Sets or returns the number of bits per word for the specified SPI bus.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI:DATA:SIZe <NR1>

BUS:B<x>:SPI:DATA:SIZe?

**Arguments** <NR1> specifies the number of bits per word.

**Examples** BUS:B1:SPI:DATA:SIZe 16 sets the data size to 16.

BUS:B1:SPI:DATA:SIZe? might return BUS:B1:SPI:DATA:SIZe 8

indicating that the data size is 8 bits.

#### BUS:B<x>:SPI:FRAMING

Sets or returns the type of SPI framing.

**Conditions** This command requires a DPO2EMBD application module.

Group Bus

Syntax BUS:B<x>:SPI:FRAMING {SS|IDLEtime}

BUS:B<x>:SPI:FRAMING?

**Arguments** SS specifies framing by SS (non 2-wire).

IDLEtime specifies framing by Idle Time (2-wire).

**Examples** BUS:B1:SPI:FRAMING SS sets the SPI framing type to SS.

BUS:B1:SPI:FRAMING IDLETIME might return BUS:B1:SPI:FRAMING

IDLETIME indicating that the SPI framing type is set to IDLETIME.

#### BUS:B<x>:SPI:IDLETime

Sets or returns the SPI bus idle time in seconds for the specified SPI bus.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI:IDLETime <NR3>

BUS:B<x>:SPI:IDLETime?

**Arguments** <NR3> specifies the idle time in seconds.

**Examples** BUS:B1:SPI:IDLETime? might return BUS:B1:SPI:IDLETime 5.0000E-6

indicating that the idle time is  $5 \mu s$ .

## BUS:B<x>:SPI{:SELect|:SS}:POLARity

Sets or returns the SPI SS polarity for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI{:SELect|:SS}:POLARity {LOW|HIGH}

BUS:B<x>:SPI{:SELect|:SS}:POLARity?

**Arguments** LOW specifies an active low polarity.

HIGH specifies an active high polarity.

## BUS:B<x>:SPI{:SELect|:SS}:SOUrce

Sets or returns the SPI SS source for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Bus

Syntax BUS:B<x>:SPI{:SELect|:SS}:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

BUS:B<x>:SPI{:SELect|:SS}:SOUrce?

**Arguments** CH1-CH4 is the channel to use as the SPI SS source.

D0-D15 is the digital channel to use as the SPI SS source.

#### BUS:B<x>:STATE

Sets or returns the on/off state of bus  $\langle x \rangle$ , where x is the bus number.

**Group** Bus

Syntax BUS:B<x>:STATE {<NR1>|OFF|ON}

BUS:B<x>:STATE?

Related Commands SELect:BUS<x>

**Arguments** ON or  $\langle NR1 \rangle \neq 0$  turns on the bus.

OFF or  $\langle NR1 \rangle = 0$  turns off the bus.

#### BUS:B<x>:TYPE

Sets or returns the bus type for  $\langle x \rangle$ , where x is the bus number.

**Group** Bus

Syntax BUS:B<x>:TYPE {I2C|SPI|CAN|RS232C|PARallel|LIN}

BUS:B<x>:TYPE

**Arguments** I2C specifies the Inter-IC bus.

SPI specifies the Serial Peripheral Interface bus (not available on two-channel

models).

CAN specifies the Controller Area Network bus.

RS232C specifies the RS232C bus.

PARallel specifies the parallel bus.

LIN specifies the LIN bus.

#### BUS:LOWerthreshold:CH<x>

Sets the lower threshold for each channel. This applies to all search and trigger types that use the channel. This command supersedes the :BUS:THReshold:CH<x> above.

**Group** Bus

Syntax BUS:LOWerthreshold:CH<x> {<NR3>|ECL|TTL}

BUS:LOWerthreshold:CH<x>?

**Arguments** <NR3> specifies the threshold in volts.

ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

**Examples** BUS:LOWERTHRESHOLD:CH1 TTL sets the CH1 lower threshold to 800 mV.

BUS:LOWERTHRESHOLD:CH1? might return:BUS:LOWERTHRESHOLD:CH1 -800.0000E-3 indicating that the CH1 lower threshold is -800 mV.

#### BUS:THReshold:CH<x>

Sets or returns the threshold for analog channel <x>, where x is the channel number. This setting applies to all trigger types that use the channel. The threshold value of CH<x> is set to the closest value used by hardware. The threshold settings for both BUS: THReshold:CH<x> and BUS:THRESHOLD:D<x> channels will be rounded to the nearest threshold value used by hardware and not necessarily the value set by the user. For example: If you set the threshold to 2.48 volts and the hardware only supports 2.5 volts, then the threshold value will be 2.5 volts and not 2.48 as set by you.

**Conditions** This command requires a DPO2AUTO, DPO2EMBD, or DPO2COMP application

module.

**Group** Bus

Syntax BUS:THReshold:CH<x> {ECL|TTL|<NR3>}

BUS:THReshold:CH<x>?

**Related Commands** TRIGger:A:LEVel:CH<x>

**Arguments** ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a TTL preset high level of 1.4 V.

<NR3> specifies the threshold level in volts.

### BUS:THReshold:D<x>

Sets or returns the threshold for digital channel <x>, where x is the digital channel number. This will apply to all search and trigger types that use the channel. The threshold value of D<x> is set to the closest value used by hardware.

Digital channel thresholds are set in two groups. One for channels D0–D7 and the other for D8–D15. Setting the thresholds in one of these groups sets the threshold for all the channels in that group.

**Conditions** This command requires a DPO2AUTO, DPO2EMBD, or DPO2COMP application

module.

**Group** Bus

Syntax BUS:THReshold:D<x> {<NR3>|ECL|TTL}

BUS:THReshold:D<x>?

Related Commands TRIGger: A:LEVel: D<x>

**Arguments** ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

<NR3> specifies the threshold level in volts.

### BUS:UPPerthreshold:CH<x>

Sets the upper threshold for each channel. This applies to all search and trigger types that use the channel.

Group Bus

Syntax BUS:UPPerthreshold:CH<x> {<NR3>|ECL|TTL}

BUS:UPPerthreshold:CH<x>?

**Arguments** <NR3> specifies the threshold in volts.

ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

**Examples** BUS:UPPERTHRESHOLD:CH1 800.0000E-3 sets the CH1 upper threshold to

800 mV.

BUS:UPPERTHRESHOLD:CH1? might return:BUS:UPPERTHRESHOLD:CH1-800.0000E-3 indicating that the CH1 upper threshold is set to -800 mV.

## **BUSY?** (Query Only)

Returns the status of the oscilloscope. This command allows you to synchronize the operation of the oscilloscope with your application program.

**Group** Status and Error

Syntax BUSY?

Related Commands \*OPC, \*WAI

**Returns** <NR1> = 0 means the oscilloscope is not busy processing a command whose execution time is extensive.

<NR1> = 1 means the oscilloscope is busy processing one of the commands listed in the table below.

#### Commands that affect BUSY? response

Operation	Command
Single sequence acquisition	ACQuire:STATE ON or ACQuire:STATE RUN or ACQuire:STATE1 (when ACQuire:STOPAfter is set to SEQuence)
Hard copy operation	HARDCopy STArt
Calibration step	Refer to the optional oscilloscope Service Manual.

#### **Examples** BUSY? might return: BUSY 1 indicating that the oscilloscope is currently busy.

See the section titled "Using the BUSY Query" for an example of how to use this query.

## \*CAL? (Query Only)

Performs an internal self-calibration and returns the oscilloscope calibration status.

**NOTE**. Disconnect or otherwise remove all input signals prior to starting self-calibration. The self-calibration can take several minutes to complete.

No other commands are executed until calibration is complete.

**Group** Calibration and Diagnostic

Syntax \*CAL?

**Returns** <NR1> = 1 indicates the calibration did not complete successfully.

<NR1> = 0 indicates the calibration completed without errors.

**Examples** \*CAL? starts the internal signal path calibration and might return 0 to indicate that

the calibration was successful.

## **CALibrate:FACtory (No Query Form)**

Provides the controls for starting and stopping the factory calibration process. The factory calibration process consists of a series of steps.

**Group** Calibration and Diagnostic

Syntax CALibrate:FACtory {STARt|CONTinue|PREVious|ABOrt|DUmp}

**Arguments** STARt initializes the factory calibration sequence and starts the first calibration

step.

**CONTinue** begins the next factory calibration step.

PREVious attempts to run the most recent factory calibration step again.

ABOrt stops the calibration process.

DUmp stops the calibration and prints the calibration constants.

**Examples** CALIBRATE: FACTORY START starts the calibration process.

## CALibrate:FACtory:STATus? (Query Only)

Returns the factory calibration status value saved in nonvolatile memory.

**Group** Calibration and Diagnostic

**Syntax** CALibrate: FACtory: STATus?

**Examples** CALIBRATE: FACTORY: STATUS? might return CALIBRATE: FACTORY: STATUS

PASS indicating that factory calibration passed.

## **CALibrate:INTERNal (No Query Form)**

This command starts a signal path compensation.

**Group** Calibration and Diagnostic

Syntax CALibrate: INTERNal

**Arguments** None

**Examples** CALIBRATE: INTERNAL starts a serial path compensation cycle.

# CALibrate:INTERNal:STARt (No Query Form)

Starts the internal signal path calibration (SPC) of the oscilloscope. You can use the CALibrate:INTERNal:STATus? query to return the current status of the internal signal path calibration of the oscilloscope.

**Group** Calibration and Diagnostic

**Syntax** CALibrate:INTERNal:STARt

**Related Commands** CALibrate: RESults: SPC?

**Examples** CALIBRATE: INTERNAL: START initiates the internal signal path calibration of

the oscilloscope.

## **CALibrate:INTERNal:STATus? (Query Only)**

Returns the current status of the oscilloscope internal signal path calibration for the last SPC operation.

**Group** Calibration and Diagnostic

**Syntax** CALibrate:INTERNal:STATus?

Related Commands \*CAL?

**Returns** This query will return one of the following:

- INIT indicates the oscilloscope has not had internal signal path calibration run.
- PASS indicates the signal path calibration completed successfully.
- FAIL indicates the signal path calibration did not complete successfully.
- RUNNING indicates the signal path calibration is currently running.

#### **Examples** CALIBRATE: INTERNAL: STATUS? might return

:CALIBRATE:INTERNAL:STATUS INIT indicating that the current status of the internal signal path calibration is that it has not been run.

### **CALibrate:RESults? (Query Only)**

Returns the status of internal and factory calibrations, without performing any calibration operations. The results returned do not include the calibration status of attached probes. The CALibrate:RESults? query is intended to support GO/NoGO testing of the oscilloscope calibration readiness: all returned results should indicate PASS status if the oscilloscope is "fit for duty". It is quite common, however, to use uncalibrated probes (particularly when the oscilloscope inputs are connected into a test system with coaxial cables).

**Group** Calibration and Diagnostic

**Syntax** CALibrate:RESults?

Related Commands \*CAL?

## CALibrate:RESults:FACtory? (Query Only)

Returns the status of internal and factory calibration, without performing any calibration operations.

**Group** Calibration and Diagnostic

**Syntax** CALibrate:RESults:FACtory?

# CALibrate:RESults:SPC? (Query Only)

Returns the status of the SPC operation. This query does not initiate a SPC.

**Group** Calibration and Diagnostic

**Syntax** CALibrate:RESults:SPC?

Related Commands \*CAL?

**Returns** INIT indicates that SPC has never successfully completed.

PASS indicates that the last SPC operation passed.
FAIL indicates that the last SPC operation failed.

RUNNING indicates that the SPC operation is running.

**Examples** CALIBRATE: RESULTS: SPC? returns the results of the last SPC operation: either

PASS or FAIL.

### **CALibrate:TEMPerature? (Query Only)**

Returns 0 as the DPO/MSO2000 series instruments do not support recording of oscilloscope temperature.

**Group** Calibration and Diagnostic

**Syntax** CALibrate: TEMPerature?

## CH<x>? (Query Only)

Returns the vertical parameters for channel  $\langle x \rangle$ , where x is the channel number.

**Group** Vertical

Syntax CH<x>?

#### CH<x>:BANdwidth

Sets or returns the selectable low-pass bandwidth limit filter for channel  $\langle x \rangle$ , where x is the channel number.

**Group** Vertical

Syntax CH<x>:BANdwidth {TWEnty|FUL1|<NR3>}

CH<x>:BANdwidth?

**Arguments** TWEnty sets the upper bandwidth limit of channel  $\langle x \rangle$  to 20 MHz.

FUL1 disables any optional bandwidth limiting. The specified channel operates

at its maximum attainable bandwidth.

<NR3> is a double-precision ASCII string. The oscilloscope rounds this value to an available bandwidth using geometric rounding, and then uses this value to

set the upper bandwidth limit.

**NOTE.** Other values may be possible depending on the attached probes.

**Examples** CH1:BANDWIDTH TWENTY sets the bandwidth of channel 1 to 20 MHz.

### CH<x>:COUPling

Sets or returns the input attenuator coupling setting for channel <x>, where x

is the channel number.

**Group** Vertical

**Syntax** CH<x>:COUPling {AC|DC|GND}

CH<x>:COUPling?

**Arguments** AC sets channel <x> to AC coupling.

DC sets channel  $\langle x \rangle$  to DC coupling.

GND sets channel<x> to ground. Only a flat, ground-level waveform will be

displayed.

**Examples** CH2:COUPLING GND sets channel 2 to ground.

CH3: COUPling? might return: CH3: COUPling DC indicating that channel 3

is set to DC coupling.

#### CH<x>:DESKew

Sets or returns the deskew time for channel <x>, where x is the channel number. You can adjust the deskew time to add an independent, channel-based delay time to the delay (set by the horizontal position control and common to all channels) from the common trigger point to first sample taken for each channel. This lets you compensate individual channels for different delays introduced by their individual input hook ups.

**Group** Vertical

Syntax CH<x>:DESKew <NR3>

CH<x>: DESKew?

**Arguments**  $\langle NR3 \rangle$  is the deskew time for channel  $\langle x \rangle$ , ranging from -100 ns to +100 ns

with a resolution of 1 ns.

**Examples** CH4:DESKew 5.0E-9 sets the deskew time for channel 4 to 5 ns.

CH2:DESKew? might return :CH2:DESKEW 2.0000E-09 indicating that the

deskew time for channel 2 is set to 2 ns.

#### CH<x>:IMPedance

Sets or returns the input impedance of channel  $\langle x \rangle$ , where x is the channel

number. This command is provided for compatibilty.

**Group** Vertical

**Syntax** CH<x>:IMPedance

CH<x>:IMPedance?

#### CH<x>:INVert

Sets or returns the invert function for channel <x>, where is the channel number. When on, the invert function inverts the waveform for the specified channel.

**NOTE.** This command inverts the waveform for display purposes only. The oscilloscope does not use an inverted waveform for triggers or trigger logic inputs.

**Group** Vertical

Syntax CH<x>:INVert {ON|OFF}

CH<x>:INVert?

**Arguments** OFF sets the invert function for channel  $\langle x \rangle$  to off.

ON sets the invert function for channel  $\langle x \rangle$  to on.

**Examples** CH4:INVert ON inverts the waveform on channel 4.

CH2:INVERT? might return: CH2:INVERT 0 indicating that channel 2 is not

inverted.

#### CH<x>:LABel

Sets or returns the waveform label for channel  $\langle x \rangle$ , where x is the channel number.

**Group** Vertical

Syntax CH<x>:LABel <Qstring>

CH<x>:LABel?

**Arguments** <Qstring> is an alpha-numeric string of text, enclosed in quotes, that contains

the text label information for the channel <x> waveform. The text string is limited

to 30 characters.

#### CH<x>:OFFSet

Sets or returns the vertical offset for channel <x>, where x is the channel number.

This command offsets the vertical acquisition window (moves the level at the vertical center of the acquisition window) for the specified channel. Visualize offset as scrolling the acquisition window towards the top of a large signal for increased offset values, and scrolling towards the bottom for decreased offset values. The resolution of the vertical window sets the offset increment for this control

Offset adjusts only the vertical center of the acquisition window for channel waveforms to help determine what data is acquired. The oscilloscope always displays the input signal minus the offset value.

The channel offset range depends on the vertical scale factor. The valid ranges for the DPO/MSO2000 series oscilloscopes are (when the probe and external attenuation factor is X1):

- For V/Div settings from 2 mV/div to 200 mV/div, the offset range is +/- 1 V
- For V/Div settings from 202 mV/div to 5 V/div, the offset range is +/- 25 V

Group Vertical

CH<x>:OFFSet <NR3> Syntax 1

CH<x>:OFFSet?

**Related Commands** CH<x>:POSition

> <NR3> is the offset value for the specified channel <x>. **Arguments**

CH3:OFFSet 2.0E-3 sets the offset for channel 3 to 2 mV. **Examples** 

> CH4:OFFSet? might return: CH4:OFFSET 1.0000E-03 indicating that the offset for channel 4 is set to 1 mV.

#### CH<x>:POSition

Sets or returns the vertical position of channel  $\langle x \rangle$ , where x is the channel number. The position value is applied to the signal before it is digitized.

Increasing the position value of a waveform causes the waveform to move up. Decreasing the position value causes the waveform to move down. The position value determines the vertical graticule coordinate at which input signal values, minus the present offset setting for that channel, are displayed. For example,

if the position for Channel 3 is set to 2.0 and the offset is set to 3.0, then input signals equal to 3.0 units are displayed 2.0 divisions above the center of the screen (at 1 V/div).

**Group** Vertical

Syntax CH<x>:POSition <NR3>

CH<x>:POSition?

**Related Commands** CH<x>:OFFSet, REF<x>:VERTical:POSition, MATH[1]:VERTical:POSition

**Arguments**  $\langle NR3 \rangle$  is the position value for channel  $\langle x \rangle$ , in divisions, from the center

graticule. The range is 4 to -4 divisions.

**Examples** CH2: POSition 1.3 positions the Channel 2 input signal 1.3 divisions above the

center graticule.

CH1:POSition? might return : CH1:POSITION -1.3000 indicating that the

current position of Channel 1 is 1.3 divisions below the center graticule.

# CH<x>:PRObe? (Query Only)

Returns all information concerning the probe attached to channel  $\langle x \rangle$ , where x

is the channel number.

**Group** Vertical

**Syntax** CH<x>: PRObe?

## CH<x>:PRObe:AUTOZero (No Query Form)

Sets the TekVPI probe attached to channel  $\langle x \rangle$  to zero, where x is the channel

number

**Group** Vertical

**Syntax** CH<x>:PRObe:AUTOZero EXECute

#### **Arguments** Execute auto zeros the probe.

## CH<x>:PRObe:COMMAND (No Query Form)

Sets the state of the probe control specified with the first argument to the state specified with the second argument. The commands and states are unique to the attached probe type. Only certain VPI probes support this command. See the probe documentation for how to set these string arguments.

**Group** Vertical

Syntax CH<x>:PRObe:COMMAND <QString>, <QString>

**Arguments** <QString> are quoted strings specifying the probe command and value to set in

the probe attached to the specified channel.

**Examples** CH1: PROBE: COMMAND "MODE", "4-4V1MHz" sets a Tektronix VPI-DPG probe

to the 4-4V1MHz mode.

CH1: PROBE: COMMAND "OUTPUT", "ON" turns the output of a Tektronix

VPI-DPG probe on.

CH1: PROBE: COMMAND? "MODE" might return CH1: PROBE: COMMAND

"MODE", "4-4V1MHZ".

## CH<x>:PRObe:DEGAUss (No Query Form)

Starts a degauss auto-zero cycle on a TekVPI current probe attached to the input channel specified by <x>, where x is the channel number.

**Group** Vertical

**Syntax** CH<x>:PRObe:DEGAUSS EXECute

**Arguments** EXECute initiates the degauss operation.

## CH<x>:PRObe:DEGAUss:STATE? (Query Only)

Returns the state of the probe degauss for the channel specified by  $\langle x \rangle$ , where is x is the channel number.

**NOTE.** This command will return PASSED for probes that do not support degauss operations.

**Group** Vertical

**Syntax** CH<x>:PRObe:DEGAUSS:STATE?

**Returns** NEEDED indicates the probe should be degaussed before taking measurements.

RECOMMENDED indicates the measurement accuracy might be improved by degaussing the probe.

PASSED indicates the probe is degaussed.

FAILED indicates the degauss operation failed.

RUNNING indicates the probe degauss operation is currently in progress.

### CH<x>:PRObe:FORCEDRange

Sets or returns the range of a TekVPI probe attached to the channel specified by  $\langle x \rangle$ , where x is the channel number.

**NOTE.** This command will return *PASSED* for probes that do not support degauss operations.

**Group** Vertical

**Syntax** CH<x>:PRObe:FORCEDRange <NR3>

CH<x>: PRObe: FORCEDRange?

**Arguments** <NR3> specifies the range, which is probe specific.

**Returns** This command returns 0.0 for probes that do no support forced range.

#### CH<x>:PRObe:GAIN

Sets or returns the gain factor for the probe attached to the channel specified by  $\langle x \rangle$ , where x is the channel number. The "gain" of a probe is the output divided by the input transfer ratio. For example, a common 10x probe has a gain of 0.1.

**Group** Vertical

Syntax CH<x>:PRObe:GAIN <NR3>

CH<x>:PRObe:GAIN?

Related Commands CH<x>:SCAle

**Arguments** <NR3> is the probe gain. Allowed values depend on the specific probe.

**Examples** CH2: PROBE: GAIN? might return: CH2: PROBE: GAIN 0.1000E+00 indicating

that the attached 10x probe delivers 1 V to the channel 2 BNC for every 10 V

applied to the probe input.

### CH<x>:PRObe:ID? (Query Only)

Returns the type and serial number of the probe attached to channel  $\langle x \rangle$ , where x is the channel number.

**Group** Vertical

**Syntax** CH<x>:PRObe:ID?

**Examples** CH2:PROBE:ID? might return :CH2:PROBE:ID:TYPE "10X";SERNUMBER

"N/A" indicating that a passive 10x probe of unknown serial number is attached

to channel 2.

### CH<x>:PRObe:ID:SERnumber? (Query Only)

Returns the serial number of the probe attached to channel  $\langle x \rangle$ , where x is the channel number.

**NOTE.** For Level 0 and 1 probes, the serial number will be "".

**Group** Vertical

Syntax CH<x>:PRObe:ID:SERnumber?

#### **Examples**

CH1:PROBE:ID:SERNUMBER? might return :CH1:PROBE:ID:SERNUMBER "B010289" indicating that the serial number of the probe attached to channel 1 is B010289.

# CH<x>:PRObe:ID:TYPE? (Query Only)

Returns the type of probe attached to the channel specified by  $\langle x \rangle$ , where x is the channel number. Level 2 (or higher) probes supply their exact product nomenclature; for Level 0 or 1 probes, a generic "No Probe Detected message is returned.

Vertical Group

**Syntax** CH<x>:PRObe:ID:TYPE?

CH1:PROBE:ID:TYPE? might return :CH1:PROBE:ID:TYPE "P6203" **Examples** 

indicating that P6203-type probe is attached to channel 1.

## CH<x>:PRObe:RESistance? (Query Only)

Returns the resistance factor of the probe attached to channel  $\langle x \rangle$ , where x is the channel number.

Vertical Group

**Syntax** CH<x>:PRObe:RESistance?

**Examples** CH2:PRObe:RESistance? might return :CH2:PROBE:RESISTANCE

10.0000E+6 indicating that the input resistance of the probe attached to Channel

2 is 1 M $\Omega$ .

**NOTE.** This query will return 0.0 if no probe is attached or the attached probe

does not report the input resistance.

### CH<x>:PRObe:SIGnal

Sets or returns the input bypass setting of a TekVPI probe attached to channel <x>, where x is the channel number. The probe must support input bypass, for example TCP0001. This command is ignored if sent to an unsupported probe.

**Group** Vertical

Syntax CH<x>:PRObe:SIGnal {BYPass|PASS}

CH<x>:PRObe:SIGnal?

**Arguments** BYPass sets the probe to Bypass mode.

PASS sets the probe to Pass mode.

# CH<x>:PRObe:UNIts? (Query Only)

Returns a string describing the units of measure for the probe attached to channel  $\langle x \rangle$ , where x is the channel number.

**Group** Vertical

Syntax CH<x>:PRObe:UNIts?

**Examples** CH4:PROBE:UNITS? might return :CH4:PROBE:UNITS "V" indicating that the

units of measure for the probe attached to channel 4 are volts.

#### CH<x>:SCAle

Sets or returns the vertical scale for the channel specified by  $\langle x \rangle$ , where x is the channel number.

Each waveform has a vertical scale parameter. For a signal with constant amplitude, increasing the Scale causes the waveform to be displayed smaller. Decreasing the scale causes the waveform to be displayed larger.

Scale affects all waveforms, but affects channel waveforms differently from other waveforms:

- For channel waveforms, this setting controls the vertical size of the acquisition window as well as the display scale. The range and resolution of scale values depends on the probe attached and any other external factors you have specified.
- For reference and math waveforms, this setting controls the display only, graphically scaling these waveforms and having no affect on the acquisition hardware.

**Group** Vertical

Syntax CH<x>:SCAle <NR3>

CH<x>:SCAle?

**Related Commands** CH<x>:OFFSet, CH<x>:POSition, REF<x>:VERTical:SCAle,

MATH[1]: VERTical: SCAle

**Arguments** <NR3> is the vertical channel scale in units-per-division. The value entered here

is truncated to three significant digits.

**Examples** CH4: SCALE 100E-03 sets the channel 4 scale to 100 mV per division.

CH2:SCALE? might return: CH2:SCALE 1.0000 indicating that the current scale

setting of channel 2 is 1 V per division.

### CH<x>:TERmination

Sets the connected-disconnected status of a 50  $\Omega$  resistor, which may be connected between the specified channel's coupled input and oscilloscope ground. The channel is specified by  $\langle x \rangle$ . There is also a corresponding query that requests the termination parameter and translates this enumeration into one of the two float values. This command is maintained for compatibility.

**Group** Vertical

**Syntax** CH<x>:TERmination

CH<x>:TERmination?

#### CH<x>:VOLts

Sets or returns the vertical sensitivity for channel  $\langle x \rangle$ , where x is the channel

number.

**Group** Vertical

Syntax CH<x>:VOLts <NR3>

CH<x>:VOLts?

**Arguments** <NR3> is the vertical sensitivity, in volts.

#### CH<x>:YUNits

Sets or returns the units for the channel specified by <x>, where x is the channel number. String arguments are case insensitive and any unsupported units will generate an error.

Supported units are:

%, /Hz, A, A/A, A/V, A/W, A/dB, A/s, AA, AW, AdB, As, B, Hz, IRE, S/s, V, V/A, V/V, V/W, V/dB, V/s, VV, VW, VdB, Volts, Vs, W, W/A, W/V, W/W, W/dB, W/s, WA, WV, WW, WdB, Ws, dB, dB/A, dB/V, dB/W, dB/dB, dBA, dBV, dBW, dBdB, day, degrees, div, hr, min, ohms, percent, s

**Group** Vertical

Syntax CH<x>:YUNits <QString>

CH<x>:YUNits?

**Arguments** QString is a string of text surrounded by quotes, specifying the supported units.

### **CLEARMenu (No Query Form)**

Clears the current menu from the display. This command is equivalent to pressing the front panel Menu off.

**Group** Miscellaneous

Syntax CLEARMenu

# \*CLS (No Query Form)

Clears the following:

- Event Queue
- Standard Event Status Register
- Status Byte Register (except the MAV bit)

If the \*CLS command immediately follows an <EOI>, the Output Queue and MAV bit (Status Byte Register bit 4) are also cleared. The MAV bit indicates that information is in the output queue. The device clear (DCL) GPIB control message will clear the output queue and thus MAV. \*CLS does not clear the output queue or MAV.

\*CLS can suppress a Service Request that is to be generated by an \*OPC. This will happen if a single sequence acquisition operation is still being processed when the \*CLS command is executed.

**Group** Status and Error

Syntax \*CLS

**Related Commands** DESE, \*ESE, \*ESR?, EVENT?, EVMsg?, \*SRE, \*STB?

**Examples** \*CLS clears the oscilloscope status data structures.

#### **CURSor?**

Returns all of the current cursor settings.

**Group** Cursor

Syntax CURSor?

**Examples** CURSOR? might return the following as the current cursor settings:

:CURSOR:FUNCTION SCREEN; HBARS:POSITION1 0.0000; POSITION2 0.0000; UNITS BASE; :CURSOR: MODE INDEPENDENT; VBARS: POSITION1

-19.0006E-6; POSITION2 -18.9994E-6; UNITS SECONDS

#### **CURSor:FUNCtion**

Sets or returns the cursor type. Cursors are attached to the selected waveform in

Waveform mode and are attached to the display area in Screen mode.

**Group** Cursor

**Syntax** CURSor: FUNCtion {OFF|SCREEN|WAVEform|VBArs|HBArs}

CURSor: FUNCtion?

#### **Arguments**

OFF removes the cursors from the display but does not change the cursor type.

SCREEN specifies both horizontal and vertical bar cursors, which measure the selected waveform in horizontal and vertical units. Use these cursors to measure anywhere in the waveform display area.

WAVEform specifies paired cursors in YT display format for measuring waveform amplitude and time. In XY and XYZ format, these cursors indicate the amplitude positions of an XY pair (Ch1 vs Ch2 voltage, where Ch1 is the X axis and Ch2 is the Y axis) relative to the trigger.

VBArs specifies the vertical bar cursor to measure the selected waveform in vertical units.

HBArs specifies the horizontal bar cursor to measure the selected waveform in horizontal units.

#### **Examples**

CURSOR: FUNCTION WAVEFORM selects the paired cursors for measuring waveform amplitude and time.

CURSOR: FUNCTION? might return: CURSOr: FUNCtion SCREEN indicating that the screen cursors are currently selected.

# CURSor: HBArs? (Query Only)

Returns the current settings for the horizontal bar cursors.

**Group** Cursor

**Syntax** CURSor: HBArs?

**Examples** CURSOR: HBARS? might return the horizontal

bar setting as :CURSOR:HBARS:POSITION1

320.0000E-03;POSITION2-320.0000E-03;UNITS BASE

## CURSor:HBArs:DELTa? (Query Only)

Returns the vertical difference between the two horizontal bar cursors.

**Group** Cursor

Syntax CURSor: HBArs: DELTa?

Related Commands CURSor:HBArs:UNIts

**Returns** A floating point value with an exponent.

**Examples** CURSOR: HBARS: DELTA? might return: CURSOR: HBARS: DELTA 5.0800E+00

indicating that the difference between the two cursors is 5.08.

#### CURSor:HBArs:POSITION<x>

Sets or returns the horizontal bar cursor position relative to ground, which is expressed in vertical units (usually volts). The cursor is specified by x, which can be 1 or 2.

**Group** Cursor

Syntax CURSor:HBArs:POSITION<x> <NR3>

CURSor: HBArs: POSITION < x>?

Related Commands CURSor:FUNCtion

**Arguments** <NR3> specifies the cursor position relative to ground.

**Examples** CURSOR: HBARS: POSITION1 25.0E-3 positions Cursor 1 of the horizontal

cursors at 25 mV.

CURSOR: HBARS: POSITION2? might return: CURSOR: HBARS: POSITION2 -64.0000E-03 indicating that Cursor 2 of the horizontal bar cursors is at -64 mV.

#### **CURSor:HBArs:UNIts**

Sets or returns the units for the horizontal bar cursors.

**Group** Cursor

Syntax CURSor:HBArs:UNIts {BASe|PERcent}

CURSor: HBArs: UNIts?

**Arguments** BASe selects the vertical units for the selected waveform.

PERcent selects ratio cursors.

**Examples** CURSOR: HBARS: UNITS might return: CURSOR: HBARS: UNITS BASE indicating

that the units for the horizontal bar cursors are base.

## CURSor:HBArs:USE (No Query Form)

Sets the horizontal bar cursor measurement scale. This command is only applicable when ratio cursors are on.

**Group** Cursor

Syntax CURSor:HBArs:USE {CURrent|HALFgrat|FIVEdivs}

Related Commands CURSor: HBArs: UNIts

**Arguments** CURrent sets the H Bar measurement scale so that 0% is the current position of the lowest H Bar cursor and 100% is the current position of the highest H Bar cursor.

HALFgrat resets the H bar measurement scale to half the number of divisions (five for some models and four for others) so that 25% is the current position of

the lowest H Bar cursor and 75% is the current position of the highest H Bar.

FIVEdivs sets H Bar measurement scale so that five screen major divisions is 100%, where 0% is -2.5 divisions and 100% is +2.5 divisions from the center

horizontal graticule.

**Examples** CURSOR: HBARS: USE FIVEDIVS sets the H Bar measurement scale so that

5 screen major divisions equals 100%.

**CURSor:MODe** 

Sets or returns whether the two cursors move linked together in unison or

separately. This applies to the Waveform cursors display mode.

**Conditions** This command is only applicable when waveform cursors are displayed.

**Group** Cursor

Syntax CURSor:MODe {TRACk|INDependent}

CURSor: MODe?

**Arguments** TRACk ties the navigational functionality of the two cursors together. For cursor 1

adjustments, this ties the movement of the two cursors together; however, cursor 2

continues to move independently of cursor 1.

INDependent allows independent adjustment of the two cursors.

**Examples** CURSOR: MODE TRACK specifies that the cursor positions move in unison.

CURSOR: MODE? might return: CURSOR: MODE TRACK indicating that the two

cursors move in unison.

# CURSor: VBArs? (Query Only)

Returns the current settings for the vertical bar cursors.

**Group** Cursor

**Syntax** CURSor: VBArs?

**Examples** CURSOR: VBARS? might return the following vertical bar settings

:CURSOR:VBARS:UNITS SECONDS; POSITION1 1.0000E-06; POSITION2

9.0000E-06

# CURSor: VBArs: ALTERNATE < x>? (Query Only)

Returns the alternate readout for the waveform (Vbar) cursors specified by <x>.

This alternate readout is in effect for a bus waveform.

**Group** Cursor

**Syntax** CURSor:VBArs:ALTERNATE<x>?

**Arguments** X = 1 specifies vertical bar cursor 1.

X = 2 specifies vertical bar cursor 2.

# CURSor: VBArs: DELTa? (Query Only)

Returns the horizontal difference between the two vertical bar cursors. The units are specified by the CURSor:VBArs:UNIts command.

This is equivalent to watching the cursor readout in the display while using the appropriate cursor mode.

**Group** Cursor

Syntax CURSor: VBArs: DELTa?

**Related Commands** CURSor: VBArs: UNIts

Returns <NR3>

**Examples** CURSOR: VBARS: DELTA? might return: CURSOR: VBARS: DELTa 1.0640E+00

indicating that the time between the vertical bar cursors is 1.064 s.

## CURSor: VBArs: HPOS < x>? (Query Only)

Returns the horizontal value of the specified vertical bar ticks for cursor <x>.

**Group** Cursor

Syntax CURSor:VBArs:HPOS<x>?

Related Commands CURSor: VBArs: UNIts

**Arguments** <x> specifies the cursor. Valid values are 1 and 2.

**Returns** <NR3> indicates the value of one of the tics. The units are specified by the

CURSor: VBArs: UNIts command.

**Examples** CURSOr: VBArs: HPOS2? might return CURSOR: VBARS: HPOS2 100E-3,

indicating that the value of one vertical bar tick.

#### CURSor: VBArs: POSITION < x >

Sets or returns the horizontal position for the specified vertical bar cursor. The cursor is specified by <x>, which can be 1 or 2. Values are with respect to trigger position or the zero reference point for the designated waveform (if horizontal units are not set to time). Use the CURSor:VBArs:UNIts command to specify units.

**Group** Cursor

Syntax CURSor:VBArs:POSITION<x> <NR3>

CURSor:VBArs:POSITION<x>?

**Related Commands** CURSor:VBArs:UNIts

**Arguments** <NR3> specifies the cursor position.

**Returns** A floating point value with an exponent.

**Examples** CURSor: VBArs: POSITION2 9.00E-6 positions the cursor2 vertical bar cursor

at 9 ms.

CURSOR: VBARS: POSITION1? this command might return :CURSOR: VBARS: POSITION1 1.0000E-06 indicating that the

cursor1 vertical bar is positioned at 1 µs.

#### CURSor: VBArs: UNIts

Sets or returns the units for the vertical bar cursors.

**Group** Cursor

Syntax CURSor:VBArs:UNIts {SEConds|HERtz|DEGrees|PERcent}

CURSor: VBArs: UNIts?

**Arguments** SEConds sets the units of the vertical bar cursors for the time domain (seconds).

HERtz sets the units of the vertical bar cursors for the frequency domain (Hertz).

DEGrees sets the units to degrees for use with an XY display.

PERcent sets the units to percent for use with ratio cursors.

**Returns** SECONDS, HERTZ, DEGREES, or PERCENT, depending on the current vertical bar

cursor units.

**Examples** CURSOR: VBARS: UNITS HERtz sets the units of the VBArs cursors to 1/seconds.

CURSOR: VBARS: UNITS? might return: CURSOR: VBARS: UNITS SECONDS indicating that the units for the vertical bar cursor are currently set to seconds.

## **CURSor:VBArs:USE (No Query Form)**

Sets the vertical bar cursor measurement scale.

**Conditions** This command is only applicable when ratio cursors are on.

**Group** Cursor

Syntax CURSor:VBArs:USE {CURrent|HALFgrat|FIVEdivs}

**Related Commands** CURSor:VBArs:UNIts

**Arguments** CURrent sets the V Bar measurement scale so that 0% is the current position of

the left-most V Bar cursor and 100% is the current position of the right-most

V Bar cursor.

HALFgrat resets the V Bar measurement scale to half the number of divisions (five for some models and four for others) so that 25% is the current position of the lowest V Bar cursor and 75% is the current position of the highest V Bar.

FIVEdivs sets V Bar measurement scale so that five screen major divisions is 100%, where 0% is -2.5 divisions and 100% is +2.5 divisions from the center

vertical graticule.

**Examples** CURSOR: VBARS: USE CURRENT sets the V Bar measurement scale to use the

current cursor positions as 0% and 100% of scale if units are set to %.

### CURSor: VBArs: VDELTa? (Query Only)

Returns the vertical difference between the two vertical bar cursor ticks.

**Group** Cursor

Syntax CURSor: VBArs: VDELTa?

Related Commands CURSor:HBArs:UNIts

**Returns** <NR3> indicates the horizontal difference between the two vertical bar cursors.

**Examples** CURSOR: VBARS: VDELTA? might return CURSOR: VBARS: VDELTA 1.064E+0,

indicating that the vertical difference between the vertical bar cursors ticks is

1.064 units.

# CURSor:XY:POLar:RADIUS:DELta? (Query Only)

Returns the difference between the cursors X radius and the cursor Y radius ( $\Delta Y$ ,  $\Delta X$ ). The ratio is calculated as (cursor 2 Y - cursor 1 Y)  $\div$  (cursor 2 X - cursor 1 X).

**Group** Cursor

**Syntax** CURSor:XY:POLar:RADIUS:DELta?

## CURSor:XY:POLar:RADIUS:POSITION<x>? (Query Only)

Returns the polar radius for the specified cursor, where x can be either 1 or 2.

**Group** Cursor

Syntax CURSor:XY:POLar:RADIUS:POSITION<x>?

### CURSor:XY:POLar:RADIUS:UNIts? (Query Only)

Returns the polar radius units.

**Group** Cursor

Syntax CURSor:XY:POLar:RADIUS:UNIts?

# CURSor:XY:POLar:THETA:DELta? (Query Only)

Returns the XY cursor polar angle delta.

**Group** Cursor

**Syntax** CURSor:XY:POLar:THETA:DELta?

# CURSor:XY:POLar:THETA:POSITION<x>? (Query Only)

Returns the cursor X or cursor Y polar coordinate, where x is either 1 or 2.

**Group** Cursor

Syntax CURSor:XY:POLar:THETA:POSITION<x>?

### CURSor:XY:POLar:THETA:UNIts? (Query Only)

Returns the cursor coordinate units.

**Group** Cursor

**Syntax** CURSor:XY:POLar:THETA:UNIts?

# CURSor:XY:PRODUCT:DELta? (Query Only)

Returns the difference between the cursors X position and cursor Y position. The  $\Delta X \times \Delta Y$  value is calculated as  $(X2 - X1) \times (Y2 - Y1)$ .

**Group** Cursor

**Syntax** CURSor:XY:PRODUCT:DELta?

# CURSor:XY:PRODUCT:POSITION<x>? (Query Only)

Returns the position of the X or Y cursor used to calculate the  $X \times Y$  cursor measurement, Position  $1 = (X1 \times Y1)$ ; Position  $2 = (X2 \times Y2)$ . The cursor is specified by x, which can be 1 or 2.

**Group** Cursor

Syntax CURSor:XY:PRODUCT:POSITION<x>?

## CURSor:XY:PRODUCT:UNIts? (Query Only)

Returns the XY cursor product units.

**Group** Cursor

Syntax CURSor:XY:PRODUCT:UNIts?

### CURSor:XY:RATIO:DELta? (Query Only)

Returns the ratio of the difference between the cursors X position and cursor Y position ( $\Delta Y$ ,  $\Delta X$ ). The ratio is calculated as (Y2 - Y1) / (X2 - X1).

**Group** Cursor

**Syntax** CURSor:XY:RATIO:DELta?

### CURSor:XY:RATIO:POSITION<x>? (Query Only)

Returns the X (horizontal) or Y (vertical) position for the specified cursor, which can be 1 (X) or 2 (Y). The ratio is calculated as Position 1 = (Y1/X1); Position 2 = (Y2/X2).

**Group** Cursor

Syntax CURSor:XY:RATIO:POSITION<x>?

# CURSor:XY:RATIO:UNIts? (Query Only)

Returns the cursor X and cursor Y units for the ratio measurement.

**Group** Cursor

Syntax CURSor:XY:RATIO:UNIts?

# CURSor:XY:RECTangular:X:DELta? (Query Only)

Returns the cursor X delta value in rectangular coordinates.

**Group** Cursor

**Syntax** CURSor:XY:RECTangular:X:DELta?

### CURSor:XY:RECTangular:X:POSITION<x>

Sets or returns the X rectangular coordinate for cursor 1 or cursor 2. Cursors are specified by x and can be either 1 or 2.

**Group** Cursor

Syntax CURSor:XY:RECTangular:X:POSITION<x> <NR3>

CURSor:XY:RECTangular:X:POSITION<x>?

**Arguments** <NR3> is the coordinate in volts.

# CURSor:XY:RECTangular:X:UNIts? (Query Only)

Returns the cursor X rectangular units.

**Group** Cursor

**Syntax** CURSor:XY:RECTangular:X:UNIts?

## CURSor:XY:RECTangular:Y:DELta? (Query Only)

Returns The cursor Y delta value in rectangular coordinates.

**Group** Cursor

**Syntax** CURSor:XY:RECTangular:Y:DELta?

## CURSor:XY:RECTangular:Y:POSITION<x>

Sets or returns the Y rectangular coordinate for cursor 1 or cursor 2. The cursor is specified by x.

**Group** Cursor

Syntax CURSor:XY:RECTangular:Y:POSITION<x> <NR3>

CURSor:XY:RECTangular:Y:POSITION<x>?

**Arguments** <NR3> is the coordinate in volts.

### CURSor:XY:RECTangular:Y:UNIts? (Query Only)

Returns the cursor Y rectangular units.

**Group** Cursor

**Syntax** CURSor:XY:RECTangular:Y:UNIts?

#### **CURVe**

Transfers waveform data to and from the oscilloscope in binary or ASCII format. Each waveform transferred includes a waveform preamble which contains the data format, scale, and associated information.

For analog waveforms, the CURVe? query transfers data from the oscilloscope. The data source is specified by the DATa:SOUrce command. The first and last data points are specified by the DATa:STARt and DATa:STOP commands.

The oscilloscope returns data from the last acquisition if the source is a channel waveform that is being previewed. The data does not reflect the acquisition

preview parameters. The user should always follow acquisition parameter changes with a single sequence OPC command prior to CURVe? to ensure the return data reflects the new acquisition parameters.

The CURVe command transfers waveform data to the oscilloscope. The data is stored in the reference memory location specified by DATa:DESTination, starting with the data point specified by DATa:STARt. Only one waveform can be transferred at a time. The waveform will only be displayed if the reference is displayed.

For CURVe queries, first set DATa:RESOlution and DATa:COMPosition appropriately. For MSO/DPO2000 math FFT CURVe queries, set them to: DATA:RESOLUTION FULL and DATA:COMPOSITION SINGULAR\_YT.

For more information, see: Appendix B: Waveform Data in DPO/MSO2000 Series Instruments.

(See page 3-1.)

**NOTE.** Transferring large volumes of data to or from the oscilloscope takes time. ASCII waveform transfer is very inefficient.

**NOTE.** For MSO models, reduced resolution waveform data is not available for the digital channels.

S

**Group** Waveform Transfer

Syntax CURVe {<Block>|<asc curve>}
 CURVe?

**Related Commands** 

DATa:COMPositionDATa:DESTination, DATa:RESOlutionDATa:SOUrce, DATa:STARt, DATa:STOP, WFMInpre?, WFMInpre:BYT\_Nr, WFMOutpre?, HEADer

**Arguments** 

<Block> is the waveform data in binary format. The waveform is formatted as: #<x><yyy><data><newline>, where:

<x> is the number of y bytes. For example, if <yyy>=500, then <x>=3)

<yyy> is the number of bytes to transfer if samples are one or two bytes wide. Use the WFMInpre:BYT\_Nr command to set the width for waveforms transferred into the oscilloscope. Use WFMOutpre:BYT\_Nr to set the width for waveforms transferred out from the oscilloscope.

<data> is the curve data

<newline> is a single byte new line character at the end of the data.

<asc curve> is the waveform data in ASCII format. The format for ASCII data
is <NR1> [,<NR1>...], where each <NR1> represents a data point.

#### **Examples**

CURVE? with ASCII encoding, start and stop of 1 and 10 respectively, and a width set to 1 might return: CURVE 61,62,61,60,60,-59,-58,-58,-59

**NOTE.** Curve data is transferred from the oscilloscope asynchronously, depending on the length of the curve record. Such transfers may require several seconds to complete. During this period, the oscilloscope will not respond to the user controls. You can interrupt these asynchronous data transfers by sending a device clear message to the oscilloscope or by interrupting the query with another command or query. In order to verify that curve data has been completely transferred, it is recommended that you follow such queries with an \*ESR? query to verify there are no error bits set. You can also check the event queue to determine the cause of the error. If the error was caused by an interrupted query, then the asynchronous data transfer was not complete when the \*ESR? query was sent. In such cases, it may be necessary to increase the program's time-out value to ensure that all data is transferred and read.

#### **DATa**

Sets or returns the format and location of waveform data transferred with the CURVe? query or CURVe command.

**Group** Waveform Transfer

Syntax DATa {INIT|SNAp}
DATa?

**Related Commands** 

CURVe, DATa:STARt, DATa:STOP, DATa:ENCdg, WFMInpre:NR\_Pt, WFMOutpre:NR\_Pt?

**Arguments** 

INIT initializes the waveform data parameters to their factory defaults except for DATa:STOP, which is set to the current acquisition record length.

SNAp sets DATa:STARt and DATa:STOP to match the current waveform cursor positions.

**Examples** DATA? might return : DATA: DESTINATION REF1: ENCOG RIBINARY; SOURCE

CH1;START 1;STOP 500;WIDTH 1

DATA INIT initializes the waveform data parameters to their factory defaults.

#### **DATa: COMPosition**

Sets or returns the type of data that the CURVe? query returns.

**Group** Waveform Transfer

Syntax DATa:COMPosition {COMPOSITE\_YT|COMPOSITE\_ENV|SINGULAR\_YT}

DATa: COMPosition?

**Arguments** COMPOSITE\_YT is of native width 8-bits and is written as 8-bit data in ISF files

and REF waveforms. The data can be queried as 1- or 2-byte data in CURVe?

queries by setting the data width to 1 or 2.

COMPOSITE\_ENV is min/max pair data. Its native width is 8-bits and is written as 8-bit data in ISF files and REF waveforms. The data can be queried as 1- or 2-

byte data in CURVe? queries by setting the data width to 1 or 2.

SINGULAR\_YT is 16-bit data which originates as averaged acquired data or math data. It is written to ISF files and REF waveforms as 16-bit data. The data can be queried as 1- or 2- byte data in CURVe? queries by setting the data width to 1 or 2.

**Examples** DATA: COMPOSITION? might return: DATA: COMPOSITION SINGULAR\_YT

indicating that the data type returned by the CURVe? query is singular waveform.

DATA: COMPOSITIONCOMPOSITE\_YT sets the return data type of CURVe? query

as composite waveform.

# DATa:COMPosition:AVAILable? (Query Only)

Lists the waveform data types that are available for return from the instrument under the current instrument settings.

**Group** Waveform Transfer

**Syntax** DATa:COMPosition:AVAILable?

**Returns** COMPOSITE\_YT for sample data.

COMPOSITE\_ENV for envelope or peak-detect data.

SINGULAR\_YT for sample data.

Examples

DATA: COMPOSITION: AVAILABLE? might return

DATA: COMPOSITION: AVAILABLE COMPOSITE\_YT indicating that the waveform

data type.

### **DATa: DESTination**

Sets or returns the reference memory location for storing waveform data transferred into the oscilloscope by the CURVe command.

**Group** Waveform Transfer

Syntax DATa: DESTination REF<x>

DATa:DESTination?

Related Commands CURVe

**Arguments** REF<x> is the reference location where the waveform will be stored.

**Examples** 

DATA: DESTINATION? might return: DATA: DESTINATION REF2 indicating that reference 2 is the currently selected reference memory location for incoming waveform data. DATA: DESTINATION REF1 indicates that incoming waveform

data be stored in reference 1.

## **DATa:ENCdg**

Sets or returns the format of outgoing waveform data. This command is equivalent to setting WFMOutpre:ENCdg, WFMOutpre:BN\_Fmt, andWFMInpre:FILTERFreq. Setting the DATa:ENGdg value causes the corresponding WFMOutpre values to be updated and conversely.

**NOTE.** This command and query does not apply to incoming waveform data.

**Group** Waveform Transfer

**Syntax** 

DATa: ENCdg

{ASCIi|FAStest|RIBinary|RPBinary|SRIbinary|SRPbinary}

DATa: ENCdg?

**Related Commands** 

WFMOutpre:ENCdg, WFMOutpre:BN\_Fmt, WFMInpre:FILTERFreq

**Arguments** 

ASCIi specifies the ASCII representation for waveform data points. If ASCII is the value, then :BN Fmt and :BYT Or are ignored.

FAStest specifies that the data be sent in the fastest possible manner consistent with maintaining accuracy and is interpreted with respect to the waveform specified by DATa:SOUrce.

RIBinary specifies signed integer data point representation with the most significant byte transferred first.

When :BYT\_Nr is 1, the range is from -128 through 127. When :BYT\_Nr is 2, the range is from -32,768 through 32,767. Center screen is 0 (zero). The upper limit is the top of the screen and the lower limit is the bottom of the screen. This is the default argument.

RPBinary specifies the positive integer data-point representation, with the most significant byte transferred first.

When :BYT\_Nr is 1, the range from 0 through 255. When :BYT\_Nr is 2, the range is from 0 to 65,535. The center of the screen is 127. The upper limit is the top of the screen and the lower limit is the bottom of the screen.

SRIbinary is the same as RIBinary except that the byte order is swapped, meaning that the least significant byte is transferred first. This format is useful when transferring data to IBM compatible PCs.

SRPbinary is the same as RPBinary except that the byte order is swapped, meaning that the least significant byte is transferred first. This format is useful when transferring data to PCs.

Table 2-36: DATa and WFMOutpre Parameter Settings

DATa:ENCdg Setting	WFMOutpre Settings				
	:ENCdg	:BN_Fmt	:BYT_Or	:BYT_NR	
ASCii	ASC	N/A	N/A	1,2	
FAStest	BIN	RI	MSB	1,2	
RIBinary	BIN	RI	MSB	1,2	
RPBinary	BIN	RP	MSB	1,2	
SRIbinary	BIN	RI	LSB	1,2	
SRPbinary	BIN	RP	LSB	1,2	

#### **Examples**

DATA: ENCDG? might return: DATa: ENCDG SRPBINARY for the format of the outgoing waveform data.

DATA: ENCDG RPBinary sets the data encoding format to be a positive integer where the most significant byte is transferred first.

#### **DATa:RESOlution**

Sets or returns whether the CURVe? query returns full resolution records (acquired data) or reduced resolution records (filtered/displayed data).

**Group** Waveform Transfer

Syntax DATa: RESOlution {FULL | REDUCED }

DATa: RESOlution?

#### **Arguments**

FULL sets the instrument to return the full undecimated record acquired by the instrument. The full resolution records are not subject to the effects of FilterVu. Full resolution record lengths are 100,000, 125,000, 1,000,000 or 1,250,000 points.

REDUCed sets the instrument to return short waveforms that are decimated from the full acquisition record. Reduced records are subject to the low pass filtering effects of FilterVu settings. Reduced record lengths range from 800 to 6250 points, depending on the acquisition settings.

#### **Examples**

DATA: RESOLUTION? might return: DATA: RESOLUTION: FULL indicating that the CURVe? query returns full resolution records (acquired data).

DATA: RESOLUTIONREDUCED sets the CURVe? returns to reduced resolution records.

#### **DATa:SOUrce**

Sets or returns the location of the waveform data transferred from the oscilloscope by the CURVe? query.

**Group** Waveform Transfer

Syntax DATa:SOUrce {CH1|CH2|CH3|CH4|MATH|REF1|REF2|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

DATa:SOUrce?

#### Related Commands CURVe

#### **Arguments**

CH1-CH4 specifies which analog channel data will be transferred from the oscilloscope to the controller, channels 1 through 4.

MATH specifies that the Math waveform data will be transferred from the oscilloscope to the controller.

REF1-REF2 specifies which Reference waveform data will be transferred from the oscilloscope to the controller, waveforms, 1 through 4.

D0-D15 specifies that the returned waveform data is packaged as 4 bytes per sample, representing the states of all digital channels (D0-D15) and the logic states of the analog channels (Ch1-Ch4). When the :DATA:SOURCE is set to DIGITAL, the :DATA:WIDTH is automatically set to 4.

The format of the returned 4- byte (32 bit) data is as follows:

BIT	-	Description		
31 (MSB)	_	Unused		
30	_			
29	_	Unused		
28	_			
27	_	<b>.</b>		
26	_	Unused		
25	_	Unused		
24	_	Unused		
23	_	Unused		
22	_	Unused		
21	_	Unused		
20	_	Trigger (only when MagniVu is ON)		
19	_	Ch4 logic state		
18	_	Ch3 logic state		
17	_	Ch2 logic state		
16	_	Ch1 logic state		
15	-	D15 state		
14	_	D14 state		
13	_	D13 state		
12	_	D12 state		
11	_	D11 state		
10	_	D10 state		
09	-	DO9 state		
08	-	DO8 state		
07	-	DO7 state		
06	-	DO6 state		
05	-	DO5 state		
04	-	DO4 state		
03	-	DO3 state		
02	_	DO2 state		
01	-	DO1 state		
00 (LSB)	-	DOO state		

#### **Examples**

DATA: SOURCE? might return: DATA: SOURCE REF2 indicating that the source for the waveform data which is transferred using a CURVe? query is reference 2.

DATA: SOURCE CH1 specifies that the CH1 waveform will be transferred in the next CURVe? query.

# **DATa:STARt**

Sets or returns the starting data point for incoming or outgoing waveform transfer. This command allows for the transfer of partial waveforms to and from the oscilloscope.

**Group** Waveform Transfer

Syntax DATa:STARt <NR1>

DATa:STARt?

Related Commands CURVe, DATa, DATa:STOP, WFMInpre:NR\_Pt, WFMOutpre:NR\_Pt?

**Arguments** <NR1> is the first data point that will be transferred, which ranges from 1 to the

record length. Data will be transferred from <NR1> to DATa:STOP or the record length, whichever is less. If <NR1> is greater than the record length, the last

data point in the record is transferred.

DATa:STARt and DATa:STOP are order independent. When DATa:STOP is greater than DATa:STARt, the values will be swapped internally for the CURVE?

query.

**Examples** DATA: START? might return: DATA: START 214 indicating that data point 214 is

the first waveform data point that will be transferred.

DATA: START 10 specifies that the waveform transfer will begin with data point 10.

**DATa:STOP** 

Sets or returns the last data point that will be transferred when using the CURVe? query. This command allows for the transfer of partial waveforms from the oscilloscope.

Changes to the record length value are not automatically reflected in the DATa:STOP value. As record length is varied, the DATa:STOP value must be explicitly changed to ensure the entire record is transmitted. In other words, curve results will not automatically and correctly reflect increases in record length if the distance from DATa:STARt to DATa:STOP stays smaller than the increased record length.

**Group** Waveform Transfer

Syntax DATa:STOP\_<NR1>

DATa:STOP?

**Related Commands** CURVe, DATa, DATa:STARt, WFMInpre:NR\_Pt, WFMOutpre:NR\_Pt?

#### **Arguments**

<NR1> is the last data point that will be transferred, which ranges from 1 to the record length. If <NR1> is greater than the record length, then data will be transferred up to the record length. If both DATa:STARt and DATa:STOP are greater than the record length, the last data point in the record is returned.

DATa:STARt and DATa:STOP are order independent. When DATa:STOP is less than DATa:STARt, the values will be swapped internally for the CURVE? query.

If you always want to transfer complete waveforms, set DATa:STARt to 1 and DATa:STOP to the maximum record length, or larger.

#### **Examples**

DATA: STOP? might return: DATA: STOP 14900 indicating that 14900 is the last waveform data point that will be transferred.

DATA: STOP 15000 specifies that the waveform transfer will stop at data point 15000.

#### DATa:WIDth

Sets or returns the number of bytes per data point in the waveform transferred using the CURVe command.

**Group** Waveform Transfer

Syntax DATa: WIDth <NR1>

DATa:WIDth?

#### Related Commands CURVe

**Arguments**  $\langle NR1 \rangle = 1$  specifies that there is 1 byte (8 bits) per point.

<NR1> = 2 specifies that there are 2 bytes (16 bits) per point. This format is useful

for AVErage waveforms.

**Examples** DATA:WIDTH 1 sets the data width to 1 byte per data point for CURVe data.

#### **DATE**

Sets or returns the date the oscilloscope displays.

**Group** Miscellaneous

Syntax DATE <QString>

DATE?

Related Commands TIME

**Arguments** <QString> is a date in the form "yyyy-mm-dd" where yyyy refers to a four-digit

year number, mm refers to a two-digit month number from 01 to 12, and dd refers

to a two-digit day number in the month.

**Examples** DATE "2006-01-24" specifies that the date is set to January 24, 2006.

DATE? might return: DATE 2006-01-24 indicating that the current date is set to

January 24, 2006.

\*DDT

Allows you to specify a command or a list of commands that execute when the oscilloscope receives a \*TRG command or the GET IEEE488.2 interface message. Define Device Trigger (\*DDT) is a special alias that the \*TRG command uses.

**Group** Miscellaneous

Syntax \*DDT {<Block>|<QString>}

\*DDT?

Related Commands ALIas, \*TRG

**Arguments** <Block> is a complete sequence of program messages. The messages can contain

only valid commands that must be separated by semicolons and must follow all rules for concatenating commands. The sequence must be less than or equal to 80

characters. The format of this argument is always returned as a query.

<QString> is a complete sequence of program messages. The messages can contain only valid commands that must be separated by semicolons and must follow all rules for concatenating commands. The sequence must be less than or

equal to 80 characters.

**Examples** \*DDT #OACQUIRE:STATE RUN specifies that the acquisition system will be

started each time a \*TRG command is sent.

#### **DESE**

Sets or returns the bits in the Device Event Status Enable Register (DESER). The DESER is the mask that determines whether events are reported to the Standard Event Status Register (SESR), and entered into the Event Queue. For a detailed discussion of the use of these registers, see Registers.

**Group** Status and Error

Syntax DESE <NR1> DESE?

Related Commands \*CLS, \*ESE, \*ESR?, EVENT?, EVMsg?, \*SRE, \*STB?

#### **Arguments**

<NR1> sets the binary bits of the DESER according to this value, which ranges from 1 through 255. For example, DESE 209 sets the DESER to the binary value 11010001 (that is, the most significant bit in the register is set to 1, the next most significant bit to 1, the next bit to 0, etc.).

The power-on default for DESER is all bits set if \*PSC is 1. If \*PSC is 0, the DESER maintains the previous power cycle value through the current power cycle.

**NOTE.** Setting the DESER and ESER to the same value allows only those codes to be entered into the Event Queue and summarized on the ESB bit (bit 5) of the Status Byte Register. Use the \*ESE command to set the ESER.

#### **Examples**

DESE 209 sets the DESER to binary 11010001, which enables the PON, URQ, EXE and OPC bits.

DESE? might return : DESE 186, showing that the DESER contains the binary value 10111010.

### **DIAg:LOOP:OPTion**

Sets the self-test loop option.

**Group** Calibration and Diagnostic

Syntax DIAg:LOOP:OPTion {ALWAYS|FAIL|ONFAIL|ONCE|NTIMES}

**Arguments** ALWAYS continues looping until the self tests (diagnostics) are stopped via the

front panel or by an oscilloscope command.

FAIL causes looping until the first self test (diagnostic) failure or until self tests

(diagnostics) are stopped.

ONFAIL causes looping on a specific test group as long as a FAIL status is

returned from the test.

ONCE executes self test (diagnostics test) sequence once.

NTIMES runs "n" number of loops.

**Examples** DIAG: LOOP: OPTION ONCE runs one loop of self tests.

## DIAg:LOOP:OPTion:NTIMes

Sets the self-test loop option to run N times.

**Group** Calibration and Diagnostic

Syntax DIAg:LOOP:OPTion:NTIMes <NR1>

DIAg:LOOP:OPTion:NTIMes?

**Arguments** <NR1> is the number of self-test loops.

**Examples** DIAG:LOOP:OPTION:NTIMES 3 sets the self-test loop to run three times.

DIAG:LOOP:OPTION:NTIMES? might return:DIAG:LOOP:OPTION:NTIMES 5,

indicating that the self-test loop is set to run five times.

### **DIAg:LOOP:STOP (No Query Form)**

Stops the self-test at the end of the current loop.

**Group** Calibration and Diagnostic

Syntax DIAg:LOOP:STOP

**Examples** DIAG: LOOP: STOP stops the self test at the end of the current loop.

# DIAg:RESUIt:FLAg? (Query Only)

Returns the pass/fail status from the last self-test sequence execution. Use this query to determine which test(s) has failed.

**Group** Calibration and Diagnostic

**Syntax** DIAg:RESUlt:FLAg?

**Related Commands** DIAg:RESUlt:LOG?

**Returns** PASS indicates that all of the selected self (diagnostic) tests have passed.

FAIL indicates that at least one of the selected self (diagnostic) tests has failed.

**Examples** DIAG: RESULT: FLAG? returns either DIAG: RESULT: FLAG PASS or FAIL.

# DIAg:RESUIt:LOG? (Query Only)

Returns the internal results log from the last self-test sequence execution. The list contains all modules and module interfaces that were tested along with the pass/fail status of each.

**Group** Calibration and Diagnostic

**Syntax** DIAg:RESUlt:LOG?

**Related Commands** DIAg:RESUlt:FLAg?

**Returns** <QString> in the following format:

<Status>--<Module name>[,<Status>--<Module name>...]

Examples DIAG: RESULT: LOG? might return :DIAG: RESULT: LOG "NOT RUN--CPU, NOT

RUN--DISPLAY, NOT RUN--FPANEL, NOT RUN--IO, NOT RUN--ACQ, NOT

RUN--RO M, NOT RUN--APPKEY"

## **DIAg:SELect (No Query Form)**

Sets the type of diagnostics grouping.

**Group** Calibration and Diagnostic

Syntax DIAg:SELect {ALL|APPKey|CPU|DISplay|FPAnel|IO|ROM|ACQ}

**Arguments** ALL runs all diagnostic groups.

APPKey runs just the application key diagnostic group.

CPU runs just the CPU diagnostic group.

DISplay runs just the display circuit diagnostic group.

FPAnel runs just the front panel diagnostic group.

IO runs just the IO board diagnostic group.

ROM runs just the IO board diagnostic group.

ACQ runs just the acquisition system diagnostic group.

## **DIAg:SELect:<function> (No Query Form)**

Runs self-tests on the specified system subsystem.

**Group** Calibration and Diagnostic

Syntax DIAg:SELect:<function>

**Arguments** <function> specifies a single oscilloscope subsystem on which to run self tests

(diagnostics). Valid values are:

ACQ tests the acquisition system.

APPKey tests the application keys.

CPU tests the CPU.

DISplay tests the display.

FPAnel tests the front panel controls.

IO tests the IO ports.

ROM tests the system read only memory.

**Examples** DIAG: SELECT: CPU sets the oscilloscope to run just CPU tests.

## **DIAg:STATE (No Query Form)**

This command starts or stops the oscilloscope self-test. Depending on the argument, self-test capabilities are either turned on or off.

**Group** Calibration and Diagnostic

Syntax DIAg:STATE {EXECute|ABORt}

**Arguments** EXECute starts diagnostics.

ABORt stops diagnostics at the end of the current loop.

**Examples** DIAG: STATE EXECUte starts diagnostics.

## DISplay? (Query Only)

Returns the current display settings.

**Group** Display

**Syntax** DISplay?

## DISplay:CLOCk

Sets or returns whether the oscilloscope displays the date and time. The query form of this command returns an ON (1) or an OFF (0).

**NOTE.** For the MSO/DPO2000 series, the enumerations enable control of the date/time display. The query form will return 0 when the control is set to NONe or OFF and will return 1 when the control is set to DATETIME or ON.

**Group** Display

Syntax DISplay:CLOCk {DATEOnly|TIMEOnly|DATETIME|NONe|ON|OFF|<NR1>}

DISplay:CLOCk?

Related Commands DATE, TIME

**Arguments** DATEOnly enables the display of date.

TIMEOnly enables the display of time.

DATETIME or ON enables the display of both date and time.

NONe or OFF disables the display of date and time.

<NR1> = 0 disables the display of date and time; any other value enables the

display of date and time.

**Examples** DISPLAY: CLOCK ON enables display of date and time.

DISPLAY: CLOCK? might return: DISPLAY: CLOCK 1 indicating that the display

of date and time is currently enabled.

## DISplay:DIGital:HEIght

Sets or returns the number of available digital waveform position slots.

**NOTE.** If the number of live digital channels exceeds the number of slots, their height is reduced to a smaller size, allowing all digital channels to be displayed.

**Group** Display

Syntax DISplay:DIGital:HEIght {SMAll|MEDium|LARge}

DISplay:DIGital:HEIght?

**Arguments** SMA11 sets the height to 40.

MEDium sets the height to 20.

LARge sets the height to 10.

# **DISplay:FORMat**

Sets or returns the display format.

**Group** Display

**Syntax** DISplay:FORMat {YT|XY}

DISplay: FORMat?

**Arguments** YT sets the display to a voltage versus time format and is the default mode.

XY argument displays one waveform against another. Selecting one source causes its corresponding source to be implicitly selected, producing a single trace from

the two input waveforms.

**Examples** DISPLAY: FORMAT XY sets the display format to XY.

DISPLAY: FORMAT? might return DISPLAY: FORMAT YT indicating that the

display format is YT.

## DISplay:GLITch

Controls the display of the glitch capture background of the waveform. Set the

intensity with DISplay:INTENSITy:GLITch.

**Group** FilterVu

Syntax DISplay:GLITch {ON|OFF|<NR1>}

DISplay:GLITch?

**Related Commands** DISplay:INTENSITy:GLITch

**Arguments** ON or  $\langle NR1 \rangle \neq 0$  turns on the glitch capture waveform display.

OFF or  $\langle NR1 \rangle = 0$  turns off the glitch capture waveform display.

**Examples** DISPLAY:GLITCH? might return DISPLAY:GLITCH 1 indicating that there is

glitch capture waveform display.

DISPLAY: GLITCH OFF turns off the glitch capture waveform display.

# **DISplay:GRAticule**

Selects or queries the type of graticule the oscilloscope displays.

**Group** Display

Syntax DISplay:GRAticule {CROSSHair|FRAme|FUL1|GRId}

DISplay:GRAticule?

**Arguments** CROSSHair specifies a frame and cross hairs.

FRAme specifies a frame only.

FUL1 specifies a frame, a grid and cross hairs.

GRId specifies a frame and grid only.

**Examples** DISPLAY: GRATICULE FRAme sets the graticule type to display the frame only.

DISPLAY: GRATICULE? might return: DISPLAY: GRATICULE FULL indicating

that all graticule elements are selected.

## **DISplay:INTENSITy?** (Query Only)

Returns the display intensity settings.

**Group** Display

**Syntax** DISplay:INTENSITy?

**Examples** DISPLAY:INTENSITY? might return:DISPLAY:INTENSITY:WAVEFORM

35; GRATICULE 35; BACKLIGHT HIGH; GLITCH CAPTURE BACKGROUND

**INTENSITY 55** 

## DISplay:INTENSITy:BACKLight

Sets and returns the waveform backlight intensity settings.

**Group** Display

Syntax DISplay:INTENSITy:BACKLight {LOW|MEDium|HIGH}

DISplay:INTENSITy:BACKLight?

**Examples** DISPLAY:INTENSITY:BACKLIGHT? might return

:DISPLAY:INTENSITY:BACKLIGHT HIGH

## DISplay:INTENSITy:GLITch

Sets the intensity of the glitch capture background of the waveform display. The intensity can be set from 5 to 100% in increments of 5%. The intensity of the glitch capture background can only be adjusted when the glitch capture background is displayed and FilterVu filtering is in use. Otherwise, the intensity is fixed.

Use DISplay:GLITch to turn the glitch capture background ON and OFF.

Use FILTERVu:FREQuency to enable filtering. Filtering is enabled if the frequency chosen is different than the oscilloscope's full bandwidth.

Group FilterVu

Syntax DISplay:INTENSITy:GLITch {<NR1>}

**Related Commands** 

**Arguments** <NR1> is the glitch intensity and ranges from 5 to 100 percent.

**Examples** DISPLAY: INTENSITY: GLITCH? might return DISPLAY: INTENSITY: GLITCH

5 indicating that the glitch intensity is 5%.

# DISplay:INTENSITy:GRAticule

Sets and returns the display graticule intensity settings.

**Group** Display

Syntax DISplay:INTENSITy:GRAticule <NR1>

DISplay:INTENSITy:GRAticule?

**Arguments** <NR1> is the graticule intensity and ranges from 0 to 100 percent.

**Examples** DISPLAY: INTENSITY: GRATICULE? might return

DISPLAY: INTENSITY: GRATICULE 30

## DISplay:INTENSITy:WAVEform

Sets and returns the display waveform intensity settings.

**Group** Display

Syntax DISplay:INTENSITy:WAVEform <NR1>

DISplay:INTENSITy:WAVEform?

**Arguments** <NR1> is the waveform intensity and ranges from 1 to 100 percent.

**Examples** DISPLAY: INTENSITY: WAVEFORM? might return

DISPLAY: INTENSITY: WAVEFORM 60

as the intensity of the waveforms.

# **DISplay:PERSistence**

Sets or returns the display persistence. This affects the display only.

**NOTE.** When Persistence is set to Infinite, it does not mean that the brightness of any pixel should never decrease. The brightness of a pixel is proportionally dependent on the ratio between its intensity (which does NOT decrease at Infinite Persistence) and the maximum value of intensity of any pixel on the screen. If a particular pixel get hit less often than others, its brightness will decrease over time. It will become less bright relative to the pixels that get hit often.

**Group** Display

Syntax DISplay:PERSistence {<NR3>|CLEAR|AUTO|MINImum|INFInite}

DISplay: PERSistence?

**Arguments** <NR3> specifies the time of the persistence.

CLEAR resets the persist time count down and clears the display of acquired points.

INFInite displays waveform points until a control change resets the acquisition system. When persistence is set to infinite, it does not mean that the brightness of any pixel should never decrease. The brightness of a pixel is proportionally dependent on the ratio between its intensity, which does NOT decrease at infinite persistence, and the maximum value of intensity of any pixel on the screen. Thus, if a particular pixel gets hit less often than others, its brightness will decrease over time. It will become less bright relative to the pixels that get hit often.

AUTO specifies that the oscilloscope automatically determines the best waveform persistence based on the value of waveform intensity

(DISPLAY:INTEnsITY:WAVEFORM)

MINImum specifies that the waveform persistence is set to the minimum value of 0.0E0.

**Examples** 

DISPLAY: PERSISTENCE 3 specifies that the waveform points are displayed fading for 3 seconds before they completely disappear.

**D**<x>

Sets or returns parameters for digital channel <x>, where x is the channel number.

Group MSO

Syntax D<x>

D<x>:LABel

Sets or returns the waveform label for digital channel  $\leq x >$ , where x is the channel number.

Group MSO

Syntax D<x>:LABel <Qstring>

D<x>:LABel?

**Arguments** <Qstring> is an alpha-numeric string of text, enclosed in quotes, that contains

the text label information for the digital channel <x> waveform. The text string is

limited to 30 characters.

**Examples** D4:LABEL? might return:D4:LABEL "Clk wfm 4".

D<x>:POSition

Sets or returns the vertical position for digital channel  $\langle x \rangle$ , where x is the channel

number.

**NOTE.** Unlike analog channels, which use the center baseline as the zero point, digital channels use the bottom logic level as the zero point. Because of the slot model used to describe digital channel position, the oscilloscope rounds off divisions to the nearest slot.

Group MSO

Syntax D<x>:POSition <NR3>

D<x>:POSition?

**Arguments** <NR3> is the position of the digital channel in slot units. Use the oscilloscope

front-panel controls to place the channel; then query the channel to obtain an

exact value for the position.

### D<x>:THREshold

Sets or returns the logical threshold for digital channel  $\langle x \rangle$ , where x is the

channel number.

**Group** MSO

Syntax D<x>:THREshold {ECL|TTL|<NR3>}

D<x>:THREshold?

**Arguments** ECL sets the digital threshold for channel  $\langle x \rangle$  to a preset ECL high level of -1.3V.

TTL sets the digital threshold for channel  $\leq x \geq$  to a preset TTL high level of 1.4V.

<NR3> specifies the digital threshold for channel <x> in volts.

**Examples** D5:THRESHOLD ECL sets the threshold for D5 digital channel to ECL levels.

D14: threshold? might return: D14: THRESHOLD 1.2500 indicating that the

threshold level for the D14 digital channel is 1.25 volts.

\*ESE

Sets and queries the bits in the Event Status Enable Register (ESER). The ESER prevents events from being reported to the Status Byte Register (STB). For a

detailed discussion on how to use registers, see Registers.

**Group** Status and Error

Syntax \*ESE <NR1>

\*ESE?

**Related Commands** 

\*CLS, DESE, \*ESR?, EVENT?, EVMsg?, \*SRE, \*STB?

**Arguments** 

<NR1> specifies the binary bits of the ESER according to this value, which ranges from 0 through 255.

The power-on default for the ESER is 0 if \*PSC is 1. If \*PSC is 0, the ESER maintains the previous power cycle value through the current power cycle.

**NOTE.** Setting the DESER and the ESER to the same values allows only those codes to be entered into the Event Queue and summarized on the ESB bit (bit 5) of the Status Byte Register. Use the DESE command to set the DESER.

**Examples** 

\*ESE 209 sets the ESER to binary 11010001, which enables the PON, URQ, EXE, and OPC bits.

\*ESE? might return 186, showing that the ESER contains the binary value 10111010.

## \*ESR? (Query Only)

Returns the contents of the Standard Event Status Register (SESR). \*ESR? also clears the SESR (reading the SESR clears it). For a detailed discussion on how to use registers, see Registers.

Group

Status and Error

**Syntax** 

\*ESR?

**Related Commands** 

ALLEV?, \*CLS, DESE, \*ESE, EVENT?, EVMsg?, \*SRE, \*STB?

**Examples** 

\*ESR? might return 213, showing that the SESR contains the binary value 11010101.

## ETHERnet:DHCPbootp

Sets or returns the network initialization search for a DHCP/BOOTP server.

Group

Ethernet

**Syntax** ETHERnet:DHCPbootp {ON|OFF}

ETHERnet: DHCPbootp?

**Arguments** 

ON enables the oscilloscope to search the network for a DHCP or BOOTP server in order to automatically assign a dynamic IP address to the oscilloscope.

**NOTE.** Do not use DHCP/BOOTP searching if your oscilloscope has been assigned a static address on a network. If you set this command to ON, the DHCP/BOOTP search will delete or change your static IP address information.

OFF disables the oscilloscope to search the network for a DHCP or BOOTP server.

**Examples** 

ETHERNET: DHCPBOOTP ON sets the oscilloscope to search for a DHCP or BOOTP server and assign a dynamic IP address to the oscilloscope.

### ETHERnet:DNS:IPADDress

Sets or returns the network Domain Name Server (Dns) IP address.

**Group** Ethernet

Syntax ETHERnet:DNS:IPADDress <QString>

ETHERnet:DNS:IPADDress?

**Arguments** <QString> is a standard IP address value, enclosed in quotes.

**Examples** ETHERNET: DNS: IPADDRESS "128.196.13.352" sets the Dns IP address that

the oscilloscope uses to communicate with the network.

## **ETHERnet:DOMAINname**

Sets or returns the network domain name.

**Group** Ethernet

Syntax ETHERnet:DOMAINname <Qstring>

ETHERnet: DOMAINname?

**Arguments** <QString> is the network domain name, enclosed in quotes.

**Examples** ETHERNET: DOMAINNAME "Alpha1. Mycorp.com" sets the domain name that

the oscilloscope uses to communicate with the network.

## ETHERnet:ENET:ADDress? (Query Only)

Returns the Ethernet address value assigned to the oscilloscope. This is assigned

at the factory and can not be changed.

**Group** Ethernet

Syntax ETHERnet:ENET:ADDress?

**Examples** ETHERNET: ENET: ADDRESS? returns an Ethernet address such as

08:00:11:01:02:03

## ETHERnet:GATEWay:IPADDress

Sets or returns the remote interface gateway IP address.

**Group** Ethernet

Syntax ETHERnet:GATEWay:IPADDress <QString>

ETHERnet:GATEWay:IPADDress?

**Arguments** <QString> is a standard IP address value, enclosed in quotes.

**Examples** ETHERNET: GATEWAY: IPADDRESS "128.143.16.1" sets the gateway IP

address.

### **ETHERnet:HTTPPort**

Sets or returns the remote interface HTTP port value.

**Group** Ethernet

Syntax ETHERnet:HTTPPort <QString>

ETHERnet:HTTPPort?

**Arguments** <QString> is an integer port number, enclosed in quotes.

**NOTE.** Consider the following if you are using the e\*Scope<sup>TM</sup> control software. If you don't enter a port address in the URL, then the ETHERnet:HTTPPort value must be set to "80", which is the default port for HTTP protocol. If you use a URL with a port address (for example: http://DPO2004-04WKL4:1234), the port number is specified by the number after the colon. Set the ETHERnet:HTTPPort value to this same number.

**Examples** ETHERNET: HTTPPORT "80" sets the HTTP port value to 80.

### ETHERnet: IPADDress

Sets or returns the IP address assigned to the oscilloscope.

**Group** Ethernet

Syntax ETHERnet:IPADDress <QString>

ETHERnet:IPADDress?

**Arguments** <QString> is a standard IP address value, enclosed in quotes.

**Examples** ETHERNET: IPADDRESS "123.121.13.214" sets the oscilloscope's IP address.

ETHERnet:NAME

Sets or returns the network name assigned to the oscilloscope.

**Group** Ethernet

Syntax ETHERnet:NAME <QString>

ETHERnet: NAME?

**Arguments** <QString> is the network name assigned to the oscilloscope, enclosed in quotes.

**Examples** ETHERNET: NAME "labscope1" sets the oscilloscope's network name.

### ETHERnet:PASSWord

Sets or returns the HTTP Ethernet access password. If a password is set, the user must enter the password before the user's Web browser can access the oscilloscope.

Group Ethernet

ETHERnet:PASSWord <new> **Syntax** 

ETHERnet: PASSWord?

**Arguments** <new> is a new password, enclosed in quotes.

**Examples** ETHERNET: PASSWORD "ZEN53" replaces the current Ethernet password with the

new password ZEN53.

ETHERNET: PASSWORD? might return: ETHERNET: PASSWORD "ZEN53".

# **ETHERnet:PING (No Query Form)**

Causes the oscilloscope to ping the gateway IP address.

Group Ethernet

ETHERnet:PING EXECute **Syntax** 

**Examples** ETHERNET: PING EXECUTE causes the oscilloscope to ping the gateway IP

address.

# ETHERnet:PING:STATUS? (Query Only)

Returns the results from sending the ETHERnet:PING command to ping the

gateway IP address.

Ethernet Group

Syntax ETHERnet:PING:STATUS?

**Returns** OK is returned if the computer at the gateway IP address answers.

NORESPONSE is returned if the computer at the gateway IP address does not

answer.

INPROGRESS is returned if the ping operation is still executing.

### **ETHERnet:SUBNETMask**

Sets or returns the remote interface subnet mask value.

**Group** Ethernet

Syntax ETHERnet:SUBNETMask <QString>

ETHERnet:SUBNETMask?

**Arguments** <QString> is the subnet mask value, enclosed in quotes.

**EXAMPLES** ETHERNET: SUBNETMASK "255.255.0" sets the subnet mask value using

standard IP address notation format.

**EVENT?** (Query Only)

Returns an event code from the Event Queue that provides information about the results of the last \*ESR? read. EVENT? also removes the returned value from

the Event Queue.

**Group** Status and Error

Syntax EVENT?

Related Commands ALLEv?, \*CLS, DESE, \*ESE, \*ESR?, EVMsg?, \*SRE, \*STB?

**Examples** EVENT? might return: EVENT 110, showing that there was an error in a

command header. (See page 3-12, Messages.)

# **EVMsg?** (Query Only)

Removes a single event code from the Event Queue that is associated with the results of the last \*ESR? read and returns the event code along with an explanatory message. For information, see Event Handling.

**Group** Status and Error

**Syntax** EVMsg?

Related Commands ALLEv?

\*CLS, DESE, \*ESE, \*ESR?, EVENT?, \*SRE, \*STB?

**Returns** The event code and message in the following format:

<Event Code><Comma><QString>[<Event

Code><Comma><QString>...]<QString>::= <Message>;[<Command>] where <Command> is the command that caused the error and may be returned when a command error is detected by the oscilloscope. As much of the command will be returned as possible without exceeding the 60 character limit of the <Message> and <Command> string combined. The command string is right-justified.

**Examples** EVMSG? might return : EVMSG 110, "Command header error".

# **EVQty?** (Query Only)

Returns the number of event codes in the Event Queue. This is useful when using the ALLEV? query, which returns the exact number of events.

**Group** Status and Error

Syntax EVQty?

**Related Commands** ALLEv?, EVENT?, EVMsg?

**Examples** EVQTY? might return: EVQTY 3, indicating that the number of event codes in

the Event Oueue.

## **FACtory (No Query Form)**

Resets the oscilloscope to its factory default settings.

This command does the following:

- Clears the Event Status Enable Register
- Clears the Service Request Enable Register
- Sets the Device Event Status Enable Register to 255
- Purges all defined aliases
- Enables all Command Headers
- Sets the macro defined by \*DDT to a "zero-length field"
- Clears the pending operation flag and associated operations

This command does not reset the following:

- Communication settings
- Sate of the VXI-11 (Ethernet IEEE Std 488.2) interface.
- Calibration data that affects device specifications
- Protected user data
- Stored settings
- Power On Status Clear Flag
- Oscilloscope password

**Group** Save and Recall

**Syntax** FACtory

Related Commands \*PSC, \*RCL, RECAll:SETUp, \*RST, \*SAV, SAVe:SETUp

**Arguments** None

**Examples** FACTORY resets the oscilloscope to its factory default settings.

## **FILESystem**

Returns the directory listing of the current working directory and the number of bytes of free space available. This query is the same as the FILESystem:DIR? query and the FILESystem:FREESpace? query.

**Group** File System

Syntax FILESystem FILESystem?

**Related Commands** FILESystem:CWD, FILESystem:DELEte, FILESystem:DIR?,

FILESystem:REName

**Arguments** None

**Examples** FILESYSTEM? might return

:FILESYSTEM:DIR "TEK00000.BMP", "GLITCH1.PNG", "TEMP.TMP", "FILE1.WFM", "FILE2.WFM", "MATH1.WFM", "REF1.WFM", "REF2.WFM"

## FILESystem:CWD

Sets or returns the current working directory (CWD) for FILESystem commands. The default working directory is "E:/". Anytime you use this command to change the directory, the directory that you specify is retained as the current working directory until you either change the directory or you delete the directory. If you delete the current working directory, the oscilloscope resets current working directory to the default directory (E:) the next time the oscilloscope is powered on or the next time you execute a file system command.

This command supports the permutations of file and directory names supported by Microsoft Windows:

- Relative path names; for example, "./temp"
- Absolute path names; for example, "E:/Wfms"
- Implied relative path names; for example "NEWFILE.TXT" becomes "E:/TEKSCOPE/NEWFILE.TXT" if the current working directory is "E:/TEKSCOPE"

**Group** File System

Syntax FILESystem:CWD {<new working directory path>}

**Arguments** < new working directory path> is a quoted string that defines the current

working; a directory name can have up to 8 characters with an extension of up to

3 characters.

**Examples** FILESYSTEM: CWD "E:/TEKSCOPE/IMAGES" sets the current working directory

to images.

FILESYSTEM: CWD? might return

:FILESYSTEM: CWD "E:/TEKSCOPE/WAVEFORMS" indicating that the current

working directory is set to waveforms.

## FILESystem: DELEte (No Query Form)

This command deletes a named file. If you specify a directory name, it will delete the directory and all of its contents, the same as the RMDir command. You can also specify the filename as \*.\* to delete all of the files in the current or specified directory.

**Group** File System

Syntax FILESystem:DELEte <file path>

Related Commands FILESystem: CWD

FILESystem:RMDir

**Arguments** <file path> is a quoted string that defines the file name and path. If the file

path is within the current working directory, you need only specify the file name.

The argument \*.\* will delete all files and subdirectories within the current

working directory.

**Examples** FILESYSTEM: DELETE "NOT\_MINE. SET" deletes the file named

NOT\_MINE.SET from the current working directory.

## FILESystem:DIR? (Query Only)

Returns a list of quoted strings. Each string contains the name of a file or directory in the current working directory.

**Group** File System

Syntax FILESystem:DIR?

Related Commands FILESystem: CWD, FILESystem: MKDir

**Arguments** None

**Returns** FILESystem: DIR? returns a list of files and directories in the current working

directory.

**Examples** FILESYSTEM: DIR? might return

:FILESYSTEM:DIR

"TEK00000.PNG", "CANSETUP.SET", "WFM1.ISF", "MYIMAGES"

## FILESystem:FORMat (No Query Form)

Formats a mass storage device. This command should be used with extreme caution as it causes all data on the specified mass storage device to be lost. Drive letters (e.g., E:) are case sensitive and must be upper case. For all other FILESYSTEM commands, drives letters are not case sensitive. Example: FILES:FORMAT "E:/" Formats the USB flash drive installed in the oscilloscope's front panel USB port.

**Group** File System

Syntax FILESystem: FORMat

**Arguments** <drive name> is a quoted string that defines the drive to format.

**Examples** FILESYSTEM: FORMAT "E:/"

Formats the USB flash drive installed in the oscilloscope's front panel USB port.

## FILESystem:FREESpace? (Query Only)

Returns the number of bytes of free space on the current drive.

**Group** File System

**Syntax** FILESystem: FREESpace?

Related Commands FILESystem:FREESpace?, FILESystem:CWD

# FILESystem: MKDir (No Query Form)

Creates a new folder.

**Group** File System

Syntax FILESystem:MKDir <directory path>

**Related Commands** FILESystem:CWD, FILESystem:DIR?

**Arguments** <directory path> is a quoted string that specifies the directory to create

**Examples** FILESYSTEM: MKDIR "E:/NewDirectory" creates the directory named

*NEWDIRECTORY* at the root of the E drive.

These two commands create the directory MYNEWSUBDIRECTORY within the existing directory mydirectory at the root of the E drive:

FILESYSTEM:CWD "E:/MyDirectory";:FILESYSTEM:MKDIR
"MyNewSubDirectory"

This, of course, assumes that *E:/MYDIRECTORY* already existed and was not a read-only directory.

## FILESystem: READFile (No Query Form)

Writes the contents of the specified file to the specified interface. If the file does not exist or is not readable, an appropriate error event is posted.

**Group** File System

Syntax FILESystem:READFile <QString>

Related Commands FILESystem: CWD

**Arguments** <QString> is a quoted string that defines the file name and path. If the file path is

within the current working directory, specify only the file name.

**Examples** FILESYSTEM: READFILE "E:/TEST\_DATA/TEK00016CH1.CSV" reads the

content of the specified file, if the file exists and is readable, and sends the content

of the file to the current interface.

## FILESystem: REName (No Query Form)

Assigns a new name to an existing file.

**Group** File System

Syntax FILESystem:REName <old file path>,<new file path>

Related Commands FILESystem: CWD

**Arguments** <old file path> is a quoted string that defines the file name and path. If the file

path is within the current working directory, you need only specify the file name.

<new file path> is a quoted string that defines the file name and path. If the file

path is within the current working directory, you need only specify the file name.

**Examples** FILESYSTEM:RENAME "E:/TEK00000.SET", "D:/MYSETTING.SET" gives the

file named TEK00000.SET the new name of MYSETTING.SET. The file remains

in the root directory on the D drive.

## FILESystem:RMDir (No Query Form)

Deletes a named directory. This command deletes the specified directory and all of its contents. The directory must not be a read-only directory.

of its contents. The directory must not be a read-only directory.

**Group** File System

Syntax FILESystem:RMDir <directory path>

**Related Commands** FILESystem:CWD

**Arguments** <directory path> is a quoted string that defines the directory name and path.

If the file path is within the current working directory, you need only specify

the file name.

**Examples** FILESYSTEM:RMDIR "E:/OldDirectory" removes the directory named

olddirectory from the root of the E drive.

## FILESystem: WRITEFile (No Query Form)

Writes the specified block data to a file in the oscilloscope current working directory. If the specified file does not exist or is not readable, an appropriate error event is posted. The maximum length of the block data is 262144 bytes.

**Group** File System

Syntax FILESystem:WRITEFile <file path>, <data>

Related Commands FILESystem:CWD

**Arguments** <file path> is the quoted string that defines the file name and path. If the path

is within the current working directory, specify the file name only.

<data> can be either DEFINITE LENGTH encoding or INDEFINITE LENGTH ARBITRARY BLOCK PROGRAM DATA encoding as described in IEEE488.2.

# FILTERVu:FREQuency

Sets or queries the FilterVu frequency to the closest value supported with the

current acquisition settings.

**Group** FilterVu

**Syntax** FILTERVu: FREQuency?

FILTERVu: FREQuency < NR3>

**Related Commands** FILTERVu:FREQuency:AVAILable?

**Arguments** <NR3> is the integer format for the current FilterVu frequency setting.

**Examples** FILTERVU: FREQUENCY? might return FILTERVU: FREQUENCY 100000000

indicating that the FilterVu frequency is 100 MHz.

## FILTERVu:FREQuency:AVAILable? (Query Only)

Returns a comma separated list of filter frequencies available based on the current instrument settings. The source waveform (as specified by the DATa:SOUrce) must be turned on for this query to generate a response.

**Group** FilterVu

**Syntax** FILTERVu:FREQuency:AVAILable?

Related Commands FILTERVu:FREQuency

**Examples** FILTERVU: FREQUENCY: AVAILABLE? might

return FILTERVU:FREQUENCY:AVAILABLE

20000000, 150000000, 75000000, 42000000, 21000000 indicating that the available FilterVu frequencies are 200 MHz, 150 MHz, 75 MHz, 42

MHz and 21 MHz.

## FPAnel:PRESS (No Query Form)

Simulates the action of pressing a specified front-panel button.

When the front panel is locked, the front-panel button and multipurpose knob operations are suspended. The FPAnel: PRESS and the FPAnel: TURN commands will also not work. You can work around this by using the appropriate programmatic interface commands, instead of the front-panel commands.

**Group** Miscellaneous

Syntax FPAnel:PRESS <button>

**Arguments** <br/> <br/> <br/> <br/> <br/> dutton> is the name of a front-panel button. Most of the argument names

associate directly with their front panel buttons. For example, AUTOSet is for the Autoset button. The <button> enumeration arguments and their associations

with the front panel buttons are listed below.

Table 2-37: FPAnel:PRESS arguments

Argument	Description
ACQuire	Acquire button
SAVERecall	Save/Recall <b>Menu</b> button
MEASurement	Measure button
UTILity	Utility button
SEArch	Search button
TESt	Test button
MATh	M button
REF	R button
TRIGger	Trigger <b>Menu</b> button
CH1	Channel1 select button
CH2	Channel2 select button
CH3	Channel2 select button
CH4	Channel4 select button
B1	Bus1 select button
B2	Bus2 select button
D15D0	Digital channels select buttons
DEFaultsetup	Default Setup button
MENUOff	Menu Off button
SELect	Select button
FINe	Fine button
CURsor	Cursors button
INTensity	Intensity button
MARk	Mark Set/Clear button
PREv	Previous arrow button
PAUse	Play/pause button
NEXt	Next arrow button
RUnstop	Run/Stop button
SINGleseq	Single button
AUTOset	Autoset button
SETTO50	Set Trigger to 50%
FORCetrig	Force Trig button
HARDcopy	Hardcopy button
SAVEBUtton	Save button
BMENU1	Screen left-most bottom menu button
BMENU2	Screen bottom menu button
BMENU3	Screen bottom menu button
BMENU4	Screen bottom menu button

Table 2-37: FPAnel:PRESS arguments (cont.)

Argument	Description
BMENU5	Screen bottom menu button
BMENU6	Screen bottom menu button
BMENU7	Screen right-most bottom menu button
RMENU1	Screen top-most side menu button
RMENU2	Screen side menu button
RMENU3	Screen side menu button
RMENU4	Screen side menu button
RMENU5	Screen bottom-most side menu button
MAGnify	Magnify (zoom) button (not the zoom/pan knob)
FITERVu (2000 series only)	FilterVu frequency button
WFMOnly (2000 series only)	Waveform data button

**Examples** FPANEL: PRESS AUTOSET executes the oscilloscope Autoset function.

## FPAnel:TURN (No Query Form)

Simulates the action of turning a specified front-panel control knob.

When the front panel is locked, the front-panel button and multipurpose knob operations are suspended. The FPAnel:PRESS and FPAnel:TURN commands will also not work, and, they will not generate an error. You can work around this by using the appropriate programmatic interface commands, instead of the front-panel commands. For example, to set the trigger level to 50%, you could use TRIGger:A SETLevel. To force a trigger, you could use TRIGger FORCe.

**Group** Miscellaneous

Syntax FPAnel:TURN <knob>,[<n>]

**Arguments** <knob> is the name of a rotating control.

A comma (,) separates the control knob argument from the numeric optional rotation value argument. In the absence of the numeric rotation value argument, the default is 1 (clockwise). You do not need a white space between the arguments and the comma.

<n> represents the rotation direction and magnitude of rotation. Negative values represent a counterclockwise knob rotation, and positive values represent a

clockwise rotation. The magnitude of <n> specifies the amount of the turn, where <n> = 1 represents turning the knob one unit, <n> = 2 represents turning the knob two units, <n> = 4 represents turning the knob four units, and so on. The range of units depends on which front panel knob is specified.

Table 2-38: FPAnel:TURN arguments

Argument	Description
GPKNOB1	Multipurpose a knob
GPKNOB2	Multipurpose b knob
HORZPos	Horizontal <b>Position</b> knob
HORZScale	Horizontal <b>Scale</b> knob
PANKNOB1	Outer pan knob
TRIGLevel	Trigger <b>Level</b> knob
VERTPOS <n></n>	Vertical <b>Position</b> knob
VERTSCALE <n></n>	Vertical <b>Scale</b> knob
ZOOM	Inner zoom knob

#### **Examples**

FPANEL: TURN TRIGLEVEL, 10 duplicates turning the front-panel Trigger Level knob clockwise by 10 units.

## GPIBUsb:ID? (Query Only)

Returns the identification string of the connected TEK-USB-488 adaptor module and firmware version. If a TEK-USB-488.2 module is not connected, the system returns "Not detected".

**Group** Miscellaneous

Syntax GPIBUsb:ID?

## **HARDCopy** (No Query Form)

Sends a hard copy of the screen display to the currently active printer using the current palette and layout settings.

**Group** Hard Copy

**Syntax** HARDCopy {START}

HARDCopy?

Related Commands \*WAI, \*CLS

**Arguments** START sends a block of data representing the current screen image to the requested

port. The data sent is in the image format specified by SAVe:IMAGe:FILEFormat, and the compression level is controlled by whatever format has been selected

(BMP and TIFF are uncompressed, while PNG is compressed).

**Examples** HARDCOPY initiates a screen copy to the active printer.

## HARDCopy: INKSaver

Changes hard copy output to print traces and graticule on a white background while retaining waveform color information (except for channel 1, which prints as dark blue because yellow does not show up well and is difficult to see on a white background). This option can significantly reduce print time and quantities of ink required compared with WYSIWYG dark background images.

**Group** Hard Copy

**Syntax** HARDCopy:INKSaver?

**Arguments** ON or  $\langle NR1 \rangle \neq 0$  sets the ink saver mode on.

OFF or  $\langle NR1 \rangle = 0$  sets the ink saver mode off.

**Examples** HARDCOPY: INKSAVER ON will cause subsequent hard copy output to display the

screen on a white background.

## HARDCopy:PREVIEW (No Query Form)

Displays a preview of the current screen contents with the InkSaver palette applied.

**Group** Hard Copy

Syntax HARDCopy:PREVIEW {ON|OFF|<NR1>}

#### **Arguments**

ON or  $\langle NR1 \rangle \neq 0$  turns preview mode on.

OFF or  $\langle NR1 \rangle = 0$  turns preview mode off.

### **HEADer**

Sets or returns the Response Header Enable State that causes the oscilloscope to either include or omit headers on query responses.

**NOTE.** This command does not affect IEEE Std 488.2-1987 Common Commands (those starting with an asterisk); these commands never return headers. This command does affect the Response Header Enable State of both the USBTMC and VXI-11 interfaces. Refer to the Introduction for additional information.

#### Group

Miscellaneous

#### **Syntax**

HEADer {OFF|ON|<NR1>}
HEADer?

#### **Related Commands**

**VERBose** 

#### **Arguments**

OFF sets the Response Header Enable State to false. This causes the oscilloscope to omit headers on query responses, so that only the argument is returned.

ON sets the Response Header Enable State to true. This causes the oscilloscope to include headers on applicable query responses. You can then use the query response as a command.

<NR1> = 0 sets the Response Header Enable State to false; any other value sets this state to true.

#### **Examples**

HEADER OFF specifies that the oscilloscope omits headers on query responses, so that only the argument is returned.

HEADER? might return: HEADER 1 indicating that the oscilloscope is including headers on applicable query responses.

# **HORizontal?** (Query Only)

Returns all settings for the horizontal commands.

#### Group

Horizontal

Syntax HORizontal?

**Examples** HORIZONTAL? might return the following horizontal

settings: HORIZONTAL: DIGITAL: RECORDLENGTH: MAIN 100.0000E+3;:HORIZONTAL: DIGITAL: SAMPLERATE: MAIN

1.0000E+9;:HORIZONTAL:MAIN:UNITS "s";:HORIZONTAL:POSITION 50.0000;SAMPLERATE 1.0000E+9;SCALE 4.0000E-6;RECORDLENGTH

100000; DELAY: MODE 1; TIME 0.0E+0

## **HORizontal:ACQLENGTH? (Query Only)**

Returns the record length.

**Group** Horizontal

**Syntax** HORizontal:ACQLENGTH?

Related Commands HORizontal: RECOrdlength

**Examples** HORIZONTAL:ACQLENGTH? might return HORIZONTAl:ACQLENGTH?

:HORIZONTAL:ACQLENGTH 1.0000E+6 indicating that the record length is

1 million points.

# HORizontal:DELay:MODe

Sets or returns the horizontal delay mode.

**Group** Horizontal

Syntax HORizontal:DELay:MODe {OFF|ON|<NR1>}

HORizontal:DELay:MODe?

**Related Commands** HORizontal:POSition

**Arguments** OFF sets the Horizontal Delay Mode to off. This causes the HORizontal:POSition

command to horizontally position the waveform.

ON sets the Horizontal Delay Mode to on. This causes the HORizontal:DELay:

TIMe command to horizontally position the waveform.

<NR1> = 0 sets the Horizontal Delay Mode to off; any other value sets this mode to on.

**Examples** 

HORIZONTAL: DELAY: MODE OFF sets the Horizontal Delay Mode to off, allowing the HORizontal: POSition command to horizontally position the waveform.

HORIZONTAL: DELAY: MODE? might return HORIZONTAL: DELAY: MODE OFF indicating that the HORizontal: POSition command horizontally positions the waveform.

## HORizontal:DELay:TIMe

Sets or returns the horizontal delay time. The amount of time the acquisition is delayed depends on sample rate and record length.

**Group** Horizontal

Syntax HORizontal:DELay:TIMe <NR3>

HORizontal:DELay:TIMe?

**Arguments** NR3 is the delay in seconds.

**Examples** HORizontal:DELay:TIME 0.3 sets the delay of acquisition data so that the

resulting waveform is centered 300 ms after the trigger occurs.

# **HORizontal:DIGital:RECOrdlength:MAIN? (Query Only)**

Returns the record length of the main digital acquisition.

**Group** Horizontal

**Syntax** HORizontal:DIGital:RECOrdlength:MAIN?

## **HORizontal:DIGital:SAMPLERate:MAIN? (Query Only)**

Returns the sample rate of the main digital acquisition.

**Group** Horizontal

**Syntax** HORizontal:DIGital:SAMPLERate:MAIN?

### **HORizontal:POSition**

Sets or returns the horizontal position. If Horizontal Delay Mode is turned off, this command is equivalent to adjusting the HORIZONTAL POSITION knob on the front panel. When Horizontal Delay Mode is on, this command stores a new horizontal position that is used when Horizontal Delay Mode is turned off.

**Group** Horizontal

Syntax HORizontal: POSition < NR3>

HORizontal: POSition?

**Arguments** <NR3> is the horizontal position expressed as the percentage of the waveform

displayed left of the center of the graticule.

**Examples** HORIZONTAL: POSITION 50 sets the horizontal position to 50%.

HORIZONTAL: POSITION? might return: HORIZONTAL: POSITION 100

indicating that the horizontal position is set to 100%.

## **HORizontal:PREViewstate? (Query Only)**

Returns a boolean value to indicate whether the acquisition system is in the preview state.

**Group** Horizontal

**Syntax** HORizontal:PREViewstate?

**Returns**  $\langle NR1 \rangle = 1$  if the acquisition system is in the preview state.

<NR1> = 0 if the acquisition system is not in the preview state.

## HORizontal:RECOrdlength

Sets the horizontal record length of acquired waveforms. The query form of this command returns the current horizontal record length.

Horizontal Group

HORizontal:RECOrdlength <NR1> Syntax

HORizontal: RECOrdlength?

**Arguments** <NR1> represents the supported values for horizontal record lengths, which are:

100000 or 1000000.

**Examples** HORIZONTAL: RECORDLENGTH 100000 specifies that 100000 data points will

be acquired for each record.

HORIZONTAL: RECORDLENGTH? might return: HORIZONTAL: RECOrdlength 100000 indicating that the horizontal record length is equal to 100000 data points.

### **HORizontal:RESOlution**

Sets or returns the horizontal record length of acquired waveforms. The sample rate is automatically adjusted at the same time to maintain a constant time per division. The query form of this command returns the current horizontal record

length.

Group Horizontal

HORizontal: RESOlution < NR1> Syntax

HORizontal: RESOlution?

**Arguments** <NR1> represents the supported values for horizontal record lengths.

### **HORizontal:SAMPLERate**

Returns the current horizontal sample rate.

Group Horizontal

**Syntax** HORizontal:SAMPLERate?

### **HORizontal:SCAle**

Sets or returns the time base horizontal scale.

**Group** Horizontal

Syntax HORizontal:SCAle <NR3>

HORizontal:SCAle?

**Arguments** <NR3> specifies the range from 2 ns to 100 s, depending on the oscilloscope model.

**Examples** HORIZONTAL: SCALE 2E-6 sets the main scale to 2µs per division.

HORIZONTAL:SCALE? might return: HORIZONTAL:MAIN:SCALE 2.0000E-06

indicating that the main scale is currently set to 2 µs per division.

## **HORizontal:TRIGger:POSition**

Sets the horizontal position when delay mode is OFF. It is similar to

HORizontal:POSition.

**Group** Horizontal

**Syntax** HORizontal:TRIGger:POSition

HORizontal:TRIGger:POSition?

**Examples** HORIZONTAL:TRIGGER:POSITION? might return

HORIZONTAL:TRIGGER:POSITION 50 indicating that the horizontal trigger

position is set to 50%.

## ID? (Query Only)

Returns identifying information about the oscilloscope and related firmware.

**Group** Miscellaneous

Syntax ID?

Related Commands \*IDN?

**Examples** ID? might return TEK/DPO2024, CF: 91.1CT, FV: v1.0000. This indicates the

oscilloscope model number, configured format, and firmware version number.

# \*IDN? (Query Only)

Returns the oscilloscope identification code.

**Group** Miscellaneous

Syntax \*IDN?

Related Commands ID?

**Examples** \*IDN? might return :TEKTRONIX,DPO2024,SN123456789,CF:91.1CT

FV:v1.00000 indicating that the oscilloscope model number, serial number,

configured number, and firmware version number.

## **LANGuage**

Sets or returns the user interface display language. This command only affects the oscilloscope displayed language. Remote commands and their responses are always in English.

**Group** Miscellaneous

Syntax LANGuage

{ENGLish|FRENch|GERMan|ITALian|SPANish|PORTUguese|JAPAnese|

KOREan|RUSSian|SIMPlifiedchinese|TRADitionalchinese}

LANGuage?

**Examples** LANGUAGE? might return: LANGUAGE ENGLISH.

#### **LOCk**

Enables or disables all front-panel buttons and knobs. There is no front panel equivalent.

When the front panel is locked, neither the FPAnel: PRESS nor the FPAnel: TURN commands will work. They will not generate an error event either. You can work around this by using the appropriate programmatic interface commands, instead of the front-panel commands. For example, to set the trigger level to 50%, you could use TRIGger: A SETLevel. To force a trigger, you could use TRIGger FORCe.

**Group** Miscellaneous

**Syntax** LOCk {ALL|NONe}

LOCk?

Related Commands UNLock

**Arguments** ALL disables all front-panel controls.

NONe enables all front-panel controls. This is equivalent to the UNLock ALL

command.

**Examples** LOCK ALL locks the front-panel controls.

LOCK? might return: LOCK NONE indicating that the front-panel controls are

enabled by this command.

### \*LRN? (Query Only)

Returns the commands that list the oscilloscope settings except for configuration information for the calibration values, the WFMInpre? query, and the WFMOutpre? query. This query allows you to record or "learn" the current oscilloscope settings. You can use these commands to return the oscilloscope to the state it was in when you made the \*LRN? query. This command is identical to the SET? Command.

**Group** Miscellaneous

Syntax \*LRN?

Related Commands SET?

**Examples** \*LRN? might return a long response, part of which could be as follows:

:ACQUIRE:STOPAFTER RUNSTOP;STATE 1;MODE SAMPLE;NUMENV INFINITE;NUMAVG 16;SAMPLINGMODE RT;:HEADER 1;:LOCK

NONE;:LANGUAGE ENGLISH;:VERBOSE 1;:ALIAS:STATE

0;:DISPLAY:COLOR:PALETTE NORMAL;:DISPLAY:STYLE:DOTSONLY

0;:DISPLAY:PERSISTENCE 0.0000;CLOCK 1;GRATICULE FULL;INTENSITY:WAVEFORM 30;GRATICULE 75;BACKLIGHT HIGH;:HARDCOPY :INKSAVER OFF;LAYOUT LANDSCAPE;PREVIEW 0;:SAVE:IMAGE:FILEFORMAT BMP;:SAVE:WAVEFORM:FILEFORMAT

INTERNAL;:SAVE:ASSIGN:TYPE SETUP;:TRIGGER:A:MODE AUTO; TYPE EDGE; LE VEL 20.0000E-3; LEVEL: CH1 20.0000E-3;CH2 0.0000;CH3 0.0000;CH4 0.0000;:TRIGGER:A: UPPERTHRESHOLD:CH1 1.4000;CH2 800.0000E-3;CH3 800.0000E-3;CH4 800.0000E-3;:TRIGG ER:A:LOWERTHRESHOLD:CH1 20.0000E-3;CH2 0.0000;CH3 0.0000;CH4 0.0000;:TRIGGER:A:H OLDOFF:TIME 20.0000E-9;:TRIGGER:A:EDGE:SOURCE CH1; COUPLING DC; SLOPE RISE; :TRIGGER: A: LOGIC: CLASS SETHOLD; FUNCTION AND; THRESHOLD: CH1 20.0000E-3; CH2 0.0000; CH3 0.0 000; CH4 0.0000; :TRIGGER: A: LOGIC: INPUT: CH1 X;CH2 X;CH3 X;CH4 X;CLOCK:SOURCE NONE; EDGE RISE;:TRIGGER:A:LOGIC:PATTERN:INPUT:CH1 X;CH2 X;CH3 X;CH4 X;:TRIGGER:A:LOGIC:PATTERN:WHEN TRUE; WHEN: LESSLIMIT 4.0000E-9; LIMIT 4.0000E-9;:TRIGGER:A:SETHOLD:CLOCK:SOURCE CH1;EDGE RISE; THRESHOLD 20.0000E-3; :TRIGGER: A: SETHOLD: DATA: SOURCE CH2; THRESHOLD 0.0000; :TRIGGER: A: SETHOLD: HOLDTIME 4.0000E-9; SETTIME 4.0000E-9; :TRIGGER:A:PULSE:CLASS TRANSITION;:TRIGGER:A:PULSEWIDTH:SOURCE CH1; POLARITY POSITIVE; WHEN LESSTHAN; WIDTH 4.0000E-9;:TRIGGER:A:RUNT:SOURCE CH1; POLARITY POSITIVE; WHEN OCCURS; WIDTH 4.0000E-9;:TRIGGER:A:TRANSITION:SOURCE CH1

### **MARK**

Moves to the next or previous reference mark on the waveform. Returns the current mark position.

**Group** Mark

**Syntax** MARK {NEXT|PREVious}

MARK?

**Arguments** NEXT moves to the next reference mark on the right.

PREVious moves to the next reference mark on the left.

# MARK: CREATE (No Query Form)

Creates a mark on a specified waveform or all waveforms in a column.

**Group** Mark

**Syntax** MARK: CREATE {CH<x>|MATH|B<x>|REF<x>|COLUMN|DIGITal}

Arguments CH<X

CH<x> creates the mark on a channel waveform, where <x> is the channel number.

MATH creates the mark on the math waveform.

B<x> creates the mark on a bus waveform, where <x> is the bus number.

REF<x> creates the mark on a reference waveform, where <x> is the reference waveform number.

COLUMN creates marks on all waveforms in the current zoom pixel column.

DIGItal creates marks on a digital waveform. (An error will result if no digital channel is turned on.)

## MARK:DELEte (No Query Form)

Deletes a mark on a particular waveform, all waveforms in a column, the selected mark, or all marks.

**Group** Mark

Syntax MARK:DELEte {CH<x>|MATH|B<x>|REF<x>|COLUMN|DIGItal}

**Arguments** 

CH<x> deletes the mark on a channel waveform, where <x> is the channel number.

MATH deletes the mark on the math waveform.

B<x> deletes the mark on a bus waveform, where <x> is the bus number.

REF<x> deletes the mark on a reference waveform, where <x> is the reference waveform number.

COLUMN deletes marks on all waveforms in the current zoom pixel column.

DIGItal deletes all marks on all digital channels.

## MARK:FREE? (Query Only)

Returns how many marks are available for use.

**Group** Mark

Syntax MARK: FREE?

## MARK:SELected:END? (Query Only)

Returns the end of the selected mark, 0 to 100% of the waveform.

**Group** Mark

**Syntax** MARK:SELected:END?

## MARK:SELected:FOCUS? (Query Only)

Returns the focus of the selected mark, 0 to 100% of the waveform.

**Group** Mark

Syntax MARK:SELected:FOCUS?

## MARK:SELected:MARKSINCOLumn? (Query Only)

Returns the number of marks in the current zoom pixel column.

**Group** Mark

**Syntax** MARK: SELected: MARKSINCOLumn?

## MARK:SELected:OWNer? (Query Only)

Returns the owner of the selected mark.

**Group** Mark

Syntax MARK:SELected:OWNer?

**Returns** <QString> is the owner of the mark.

**Examples** MARK: SELECTED: OWNER? might return: USER, SEARCH1

## MARK:SELected:SOURCE? (Query Only)

Returns the source waveform for the selected mark.

**Group** Mark

**Syntax** MARK: SELected: SOURCE?

### MARK:SELected:STARt? (Query Only)

Returns the starting point of the selected mark, 0 to 100% of the waveform.

**Group** Mark

Syntax MARK:SELected:STARt?

### MARK:SELected:STATe? (Query Only)

Returns the on or off state of the selected mark. The selected mark is at or near the center of the screen. If you press the front-panel Set/Clear button, this mark will disappear.

**Group** Mark

**Syntax** MARK:SELected:STATe?

# MARK:SELected:ZOOm:POSition? (Query Only)

Returns the position of the selected mark, 0 to 100% of the zoom overview window.

**Group** Mark

Syntax MARK:SELected:ZOOm:POSition?

### MARK:TOTal? (Query Only)

Returns how many marks are currently in use.

**Group** Mark

**Syntax** MARK: TOTal?

### MATH[1]:LABel

Sets or queries the waveform label for the math waveform.

**Group** Math

Syntax MATH[1]:LABel <QString>

MATH[1]:LABel?

**Arguments** <QString> is the quoted string used as the label for the math waveform.

**Examples** MATH: LABEL "Output" sets the label for the math waveform to Output.

MATH: LABEL? might return MATH: LABEL "Sum of channel 1 and channel 2" indicating that the current label for the math waveform.

### MATH[1]? (Query Only)

Returns the definition of the math waveform. The returned data depends on the

setting of the MATH[1]:TYPe command.

**Group** Math

Syntax MATH[1]?

**Related Commands** MATH[1]:TYPe

**Examples** MATH? or MATH1? might return :MATH:TYPE DUAL;DEFINE

"CH1+CH2"; VERTICAL: SCALE 100.0000E-3; POSITION 0.0000; UNITS

"v";:MATH:HORIZONTAL:SCALE 4.0000E-6;POSITION 50.0000;UNITS "s";:MATH:SPECTRAL:MAG DB;WINDOW HANNING;:MATH:LABEL""

### MATH[1]:DEFine

Sets or returns the current math function as a text string.

Dual math is defined if the string is of the form <wfm> <operation> <wfm>, where the <wfm>s are any combination of live channels or reference waveforms, <operation> is any of +, -, or \*, and the MATH[1]:TYPe is DUAL.

FFT math is defined if the string is in the form FFT(<wfm>), where <wfm> is any live channel or reference waveform, and theMATH[1]:TYPe is FFT.

On the front panel, the Dual Wfm Math, and FFT menus contain controls that allow building equivalent math expressions to those described above.

**Group** Math

Syntax MATH[1]:DEFine <QString>

MATH[1]:DEFine?

Related Commands MAT

MATH[1]:TYPe

#### **Arguments**

<QString> quoted string argument is the mathematical expression that defines the waveform.

**Table 2-39: Advanced Math expression elements** 

Expression	Description
CH1-CH4, REF1, REF2	Specifies a waveform data source.
FFT(	Executes a Fast Fourier Transform. The FFT operator must be the first (left-most) operator in an expression. All these operations must end with a right parenthesis.
AMPlitude( , AREa( , BURst( , CARea(	Executes the selected measurement operation on the waveform (active or reference) that follows. All these operations must end with a right parenthesis.
+ , - , *	Executes an addition, subtraction, or multiplication operation on the following expression.
<, >, <=, >=, ==, ≠,   , &&	Executes relational and logical operations.

**Examples** MATH1:DEFINE "CH1+CH2" adds the Ch 1 waveform and Ch 2 waveform,

storing the results in Math 1.

MATH:DEFINE? might return:MATH1:DEFINE "CH2\*REF2" as the expression

that defines Math 1.

### MATH[1]:HORizontal:POSition

Sets or returns the math horizontal display position for FFT or (non-live), live math reference waveforms.

**Group** Math

Syntax MATH[1]:HORizontal:POSition <NR3>

MATH[1]:HORizontal:POSition?

**Arguments** <NR3> is the % of the math waveform that precedes center screen. It can vary

from 0.0 to 100.0.

**Examples** MATH: HORIZONTAL: POSITION 10 sets the horizontal position to 10% pretrigger

# MATH[1]:HORizontal:SCAle

Sets or returns the math horizontal display scale for FFT or (non-live), live math waveforms. The horizontal scale of a dual math waveform with a channel source waveform is set through the HORizontal:SCAle command.

**Group** Math

Syntax MATH[1]:HORizontal:SCAle <NR3>

MATH[1]:HORizontal:SCAle?

**Arguments** <NR3> is the math horizontal scale in seconds.

**Examples** MATH:HORIZONTAL:SCALE? might return MATH:HORIZONTAL:SCALE 2.0E-4

indicating that the math horizontal scale is 200 µ

## MATH[1]:HORizontal:UNIts

Returns the math waveform horizontal measurement unit value.

**Group** Math

**Syntax** MATH[1]:HORizontal:UNIts?

**Examples** MATH:HORIZONTAL:UNITS? might return MATH:HORIZONTAL:UNITS "?"

indicating that the math horizontal unit label for unknown values is the default

question mark unit.

# MATH[1]:SPECTral:GATing:INDICators

Enables or disables the display of indicators that show the portion of the source waveform record used to compute the math FFT waveform.

**Group** Math

Syntax MATH[1]:SPECTral:GATing:INDICators {<NR1>|OFF|ON}

MATH[1]:SPECTral:GATing:INDICators?

**Arguments** OFF turns off the display of indicators.

ON turns on the display of indicators.

<NR1> = 0 turns off the display of indicators. Any other value turns on the display

of indicators.

## MATH[1]:SPECTral:GATing:INDICators:END? (Query Only)

Returns the ending point in the source waveform record used for computing the

**FFT** 

**Group** Math

**Syntax** MATH[1]:SPECTral:GATing:INDICators:END?

**Returns** A value between 0 and 1, which represents the fractional portion of the source

record.

## MATH[1]:SPECTral:GATing:INDICators:STARt? (Query Only)

Returns the starting point in the source waveform record used for computing the FFT math waveform.

**Group** Math

**Syntax** MATH[1]:SPECTral:GATing:INDICators:STARt?

**Returns** A value between 0 and 1, which represents the fractional portion of the source

record.

### MATH[1]:SPECTral:MAG

Sets or returns the units of the Spectral Magnification function in the math string.

**Group** Math

Syntax MATH[1]:SPECTral:MAG {LINEAr|DB}

MATH[1]:SPECTral:MAG?

**Arguments** LINEAR sets the SpectralMag units to linear.

DB sets the SpectralMag units to decibels.

**Examples** MATH1: SPECTRAL: MAG DB sets the SpectralMag units for Math1 to decibels.

MATH1:SPECTRAL:MAG? might return:MATH1:SPECTRAL:MAG DB indicating

that the SpectralMag units for Math1 are set to decibels.

# MATH[1]:SPECTral:NYQUISTFreq? (Query Only)

Returns the Nyquist frequency of the FFT math waveforms.

**Group** Math

**Syntax** MATH[1]:SPECTral:NYQUISTFreq?

### MATH[1]:SPECTral:WINdow

Sets or returns the window function for the spectral analyzer input data for the specified math waveform. A spectral window determines what the filter shape of the spectral analyzer will be in the frequency domain. It can be described by a mathematical function that is multiplied point-by-point times the input data to the spectral analyzer.

**Group** Math

**Syntax** MATH[1]:SPECTral:WINdow

{RECTangular|HAMming|HANning|BLAckmanharris}

MATH[1]:SPECTral:WINdow?

**Arguments** RECTangular window function is equivalent to multiplying all gate data by one.

HAMming window function is based on a cosine series.

HANning window function is based on a cosine series.

BLAckmanharris window function is based on a cosine series.

**Examples** MATH1:SPECTRAL:WINDOW HANNING applies a Hanning window to the spectral

analyzer input data.

MATH1:SPECTRAL:WINDOW? might return :MATH1:SPECTRAL:WINDOW HAMMING indicating that the window function used to multiply the spectral

analyzer input data is the Hamming window.

MATH[1]:TYPe

Sets or returns the math waveform mode type.

**Group** Math

Syntax MATH[1]:TYPe {DUAL|FFT}

MATH[1]:TYPe?

**Arguments** DUAL sets the math waveform mode to dual waveform math.

FFT sets the math waveform mode to FFT math.

**Examples** MATH: TYPE FFT sets the math waveform mode to FFT.

MATH:TYPE FFT;:MATH:DEFINE "FFT( CH1 )" sets the math type to FFT and displays an FFT waveform of the channel 1 waveform, using the current

FFT scale and window settings.

### MATH[1]:VERTical:POSition

Sets or returns the vertical position of the currently selected math type.

**Group** Math

Syntax MATH[1]:VERTical:POSition <NR3>

MATH[1]: VERTical: POSition?

**Related Commands** CH<x>:POSition, REF<x>:VERTical:POSition

**Arguments** <NR3> is the desired position in divisions from the center graticule.

**Examples** MATH1: VERTICAL: POSITION 1.3E+00 positions the Math 1 input signal

1.3 divisions higher than a position of 0.

MATH1: VERTICAL: POSITION? might return: MATH1: VERTICAL: POSITION -1.3000E+00 indicating that the current position of Math 1 is 1.3 divisions

below the center graticule.

### MATH[1]:VERTical:SCAle

Sets or returns the vertical scale of the currently selected math type.

**Group** Math

Syntax MATH[1]:VERTical:SCAle <NR3>

MATH[1]:VERTical:SCAle?

**Related Commands** CH<x>:SCAle, REF<x>:VERTical:SCAle

**Arguments** <NR3> is the scale-per-division in the current math vertical units. The range is

from 1.0E-09 through 5.0.

**Examples** MATH1:VERTICAL:SCALE 100E-03 sets the Math scale to 100 mV per division.

MATH: VERTICAL: SCALE? might return: MATH: VERTICAL: SCALE

1.0000E+00 indicating that the current scale setting of Math is 1 V per division.

### MATH[1]:VERTical:UNIts? (Query Only)

Returns the math waveform vertical measurement unit value.

**Group** Math

**Syntax** MATH[1]:VERTical:UNIts?

**Examples** MATH: VERTICAL: UNITS? might return MATH: VERTICAL: UNITS "V"

indicating that the math vertical unit label is volts.

### **MEASUrement? (Query Only)**

Returns all measurement parameters.

**Group** Measurement

**Syntax** MEASUrement?

**Examples** MEASUREMENT? might return :MEASUREMENT:IMMED:DELAY:DIRECTION

FORWARDS; EDGE1 RISE; EDGE2 RISE; : MEASUREMENT: IMMED: TYPE

PERIOD; UNITS "s"; SOURCE1 CH1; SOURCE2

CH2;:MEASUREMENT:MEAS1:DELAY:DIRECTION FORWARDS;EDGE1

RISE; EDGE2 RISE; :MEASUREMENT: MEAS1: STATE 1; TYPE FREQUENCY; UNITS "Hz"; SOURCE1 CH1; SOURCE2 CH2; COUNT 0; MAXIMUM 0.0000; MEAN 0.0000; MINIMUM 0.0 000; STDDEV

0.0000;:MEASUREMENT:MEAS2:DELAY:DIRECTION FORWARDS;EDGE1

RISE; EDGE2 RISE; :MEASUREMENT: MEAS2: STATE 1; TYPE PERIOD; UNITS

"s"; SOURCE1 CH1; SOURCE2 CH2; COUNT 0; MAXIMUM 0.0000; MEAN 0.0000; MINIMUM 0.0000; STDDEV 0.0000; MEASUREMENT: MEAS3:

DELAY:DIRECTION FORWARDS; EDGE1 RISE; EDGE2

RISE;:MEASUREMENT:MEAS3:STATE 1;TYPE PK2PK;UNITS "V";SOURCE1 CH1;SOURCE2 CH2;COUNT 0;MAXIMUM 0.0000;MEAN 0.0000;MINIMUM 0.0000;STDDEV 0.0000;:MEASUREMENT:MEAS4:DELAY:DIRECTION FORWARDS;EDGE1 RISE;EDGE2 RISE;:MEASUREMENT:MEAS4:STATE 0;TYPE PERIOD;UNITS "s";SOURCE1 CH1;SOURCE2 CH2;COUNT

0;MAXIMUM 0.0000;MEAN 0.0000;MINIMUM 0.0000;STDDEV
0.0000;:MEASUREMENT:METHOD AUTO;REFLEVEL:METHOD
PERCENT;ABSOLUTE:HIGH 0.0000;LOW 0.0000;MID1
0.0000;MID2 0.0000;:MEASUREMENT:REFLEVEL:PERCENT:HIGH
90.0000;LOW 10.0000;MID1 50.0000;MID2
50.0000;:MEASUREMENT:INDICATORS:STATE
OFF;NUMHORZ 0;NUMVERT 0;HORZ1 99.0000E +36;HORZ2
99.0000E+36;HORZ3 99.0000E+36;HORZ4 99.0000E+36;VERT1
99.0000E+36;VERT2 99.0000E+36;VERT3 99.0000E+36;VERT4
99.0000E+36;:MEASUREMENT:STATISTICS:MODE OFF;WEIGHTING
32::MEASUREMENT:GATING SCREEN.

### **MEASUrement:CLEARSNapshot (No Query Form)**

Removes the measurement snapshot display.

**Group** Measurement

Syntax MEASUrement:CLEARSNapshot

Related Commands CLEARMenu

### **MEASUrement: GATing**

Specifies or returns the measurement gating setting.

**Group** Measurement

Syntax MEASUrement:GATing {OFF|SCREen|CURSor}

MEASUrement:GATing?

**Arguments** OFF turns off measurement gating (full record).

SCREEN turns on gating, using the left and right edges of the screen.

CURSor limits measurements to the portion of the waveform between the vertical

bar cursors, even if they are off screen.

**Examples** MEASUREMENT: GATING CURSOR turns on measurement gating using the cursors

as limits.

MEASUREMENT: GATING? might return: MEASUREMENT: GATING CURSOR indicating that measurements are limited to the portion of the waveform between the vertical bar cursors.

### MEASUrement: IMMed? (Query Only)

Returns all immediate measurement setup parameters.

**Group** Measurement

Syntax MEASUrement:IMMed?

**Examples** MEASUREMENT: IMMED? might return

:MEASUREMENT:IMMED:DELAY:DIRECTION FORWARDS;EDGE1 RISE;EDGE2

RISE;:MEASUREMENT:IMMED:TYPE PERIOD;UNITS "s";SOURCE1

CH1; SOURCE2 CH2

# MEASUrement:IMMed:DELay? (Query Only)

Returns information about the immediate delay measurement. This command is equivalent to viewing the delay measurement settings on the measurement readout.

**Group** Measurement

**Syntax** MEASUrement:IMMed:DELay?

**Examples** MEASUREMENT: IMMED: DELAY? might return

:MEASUREMENT:IMMED:DELAY:DIRECTION FORWARDS; EDGE1

RISE; EDGE2 RISE

# MEASUrement:IMMed:DELay:DIRection

Sets or returns the starting point and direction that determines the delay "to" edge when taking an immediate delay measurement.

**NOTE.** Use the MEASUrement:IMMed:SOUrce2 command to specify the delay "to" waveform.

**Group** Measurement

**Syntax** MEASUrement:IMMed:DELay:DIRection {BACKWards|FORWards}

MEASUrement: IMMed: DELay: DIRection?

Related Commands MEASUrement:IMMed:SOUrce2

**Arguments** BACKwards starts the search at the end of the waveform and looks for the last

rising or falling edge in the waveform.

FORWards starts the search at the beginning of the waveform and looks for the

first rising or falling edge in the waveform.

**Examples** MEASUREMENT: IMMED: DELAY: DIRECTION FORWARDS starts searching from the

beginning of the waveform record and looks for the first rising or falling edge.

MEASUREMENT: IMMED: DELAY: DIRECTION? might return

:MEASUREMENT:IMMED:DELAY:DIRECTION BACKWARDS indicating

that searching begins at the end of the waveform record and looks for the last

rising or falling edge.

## MEASUrement:IMMed:DELay:EDGE<x>

Sets or returns the slope of the edge the oscilloscope uses for the delay "from" or

"to" waveform when taking an immediate delay measurement.

**Group** Measurement

Syntax MEASUrement:IMMed:DELay:EDGE<x> {FALL|RISe}

MEASUrement:IMMed:DELay:EDGE<x>?

Related Commands MEASUrement:IMMed:SOUrce1

MEASUrement:IMMed:SOUrce2

**Arguments**  $\langle x \rangle$  specifies which waveform to use, where  $\langle x \rangle = 1$  is the "from" waveform, and

 $\langle x \rangle = 2$  is the "to" waveform.

FALL specifies the falling edge.

RISe specifies the rising edge.

#### **Examples**

MEASUREMENT: IMMED: DELAY: EDGE1 RISE specifies that the "from" waveform rising edge be used for the immediate delay measurement.

MEASUREMENT: IMMED: DELAY: EDGE1? returns either RISE or FALL.

### MEASUrement: IMMed: SOUrce1

Sets or returns the source for all single source immediate measurements and specifies the source to measure "from" when taking an immediate delay measurement or phase measurement.

Digital channels (D<x>) are available as a measurement source for time, edge and pulse measurements such as Period, Frequency, Pos Width, Neg Width, Pos Duty Cycle, Neg Duty Cycle, Pos/Neg Edges and Pos/Neg Pulses, Delay and Phase.

**NOTE.** If you do not specify a numerical suffix, the source is assumed to be SOURCE 1.

**Group** Measurement

Syntax MEASUrement:IMMed:SOUrce1 {CH<x>|MATH<y>|REF<x>}

MEASUrement: IMMed: SOUrce1?

Related Commands MEASUrement:IMMed:SOUrce2

**Arguments** CH<x> is an input channel waveform. The x variable can be expressed as an

integer, where x is the channel number.

MATH<y> is a math waveform. The y variable can be expressed as an integer of 1.

REF<X> is a reference waveform. The x variable can be expressed as an integer,

where x is the reference channel number.

**Examples** MEASUREMENT: IMMED: SOURCE1 MATH1

specifies Math1 as the immediate measurement source.

MEASUREMENT: IMMED: SOURCE1? might return

:MEASUREMENT:IMMED:SOURCE1 CH3 indicating that channel 3 is the

immediate measurement source.

### MEASUrement: IMMed: SOUrce 2

Sets or returns the source to measure "to" for phase or delay immediate measurements.

**NOTE**. Source2 measurements only apply to phase and delay measurement types, which require both a target (Source1) and reference (Source2) source.

**Group** Measurement

Syntax MEASUrement:IMMed:SOUrce2 {CH<x>|MATH<y>|REF<x>}

MEASUrement: IMMed: SOUrce2?

Related Commands MEASUrement:IMMed:SOUrce1

**Arguments** CH<x> is an input channel waveform, where x is the channel number.

MATH<y> is a math waveform. The y variable can be expressed as an integer of 1.

REF<X> is a reference waveform, where x is the reference channel number.

**Examples** MEASUREMENT: IMMED: SOURCE2 REF2 sets the waveform in reference memory

location 2 as the delay "to" source when making delay measurements.

MEASUREMENT: IMMED: SOURCE2? might return

:MEASUREMENT:IMMED:SOURCE2 MATH1 indicating that Math1 is the

immediate measurement source.

### MEASUrement:IMMed:SOUrce<x>

For SOURce1: Sets or returns the source for all single channel measurements. For delay or phase measurements, sets or returns the waveform to measure "from".

For SOUrce2: Sets or returns the waveform to measure "to" when taking a delay measurement or phase measurement.

**Group** Measurement

Syntax MEASUrement:IMMed:SOUrce<x> {CH1|CH2|CH3|CH4|MATH}

MEASUrement:IMMed:SOUrce<x>?

#### **Arguments** CH1-CH4 or MATH is the source waveform.

### MEASUrement: IMMed: TYPe

Sets or returns the immediate measurement type.

**Group** Measurement

**Syntax** MEASUrement:IMMed:TYPe

{AMPlitude|AREa|BURst|CARea|CMEan|CRMs|DELay|FALL|FREQuency|HIGH|LOW|MAXimum|MEAN|MINImum|NDUty|NEDGECount|NOVershoot

|NPULSECount|NWIdth|PEDGECount|PDUty

|PERIOd|PHAse|PK2Pk|POVershoot|PPULSECount|PWIdth|RISe|RMS}

MEASUrement:IMMed:TYPe?

#### **Arguments**

AMPlitude measures the amplitude of the selected waveform. In other words, it measures the high value less the low value measured over the entire waveform or gated region. This measurement is available only on DPO models.

Amplitude = High - Low

AREa measures the voltage over time. The area is over the entire waveform or gated region and is measured in volt-seconds. The area measured above the ground is positive, while the area below ground is negative. This measurement is available only on DPO models.

BURST measures the duration of a burst. The measurement is made over the entire waveform or gated region.

CARea (cycle area) measures the voltage over time. In other words, it measures, in volt-seconds, the area over the first cycle in the waveform or the first cycle in the gated region. The area measured above the common reference point is positive, while the area below the common reference point is negative. This measurement is available on DPO and MSO models.

CMEan (cycle mean) measures the arithmetic mean over the first cycle in the waveform or the first cycle in the gated region. This measurement is available only on DPO and MSO models.

CRMs (cycle rms) measures the true Root Mean Square voltage over the first cycle in the waveform or the first cycle in the gated region. This measurement is available only on DPO and MSO models.

DELay measures the time between the middle reference (default = 50%) amplitude point of the source waveform and the destination waveform.

FALL measures the time taken for the falling edge of the first pulse in the waveform or gated region to fall from a high reference value (default is 90%) to

a low reference value (default is 10%). This measurement is available only on DPO models.

FREQuency measures the first cycle in the waveform or gated region. Frequency is the reciprocal of the period and is measured in hertz (Hz), where 1 Hz = 1 cycle per second.

HIGH measures the High reference (100% level, sometimes called Topline) of a waveform. This measurement is available only on DPO models.

LOW measures the Low reference (0% level, sometimes called Baseline) of a waveform. This measurement is available only on DPO models.

MAXimum finds the maximum amplitude. This value is the most positive peak voltage found. It is measured over the entire waveform or gated region. This measurement is available only on DPO models.

MEAN amplitude measurement finds the arithmetic mean over the entire waveform or gated region. This measurement is available only on DPO models.

MINImum finds the minimum amplitude. This value is typically the most negative peak voltage. It is measured over the entire waveform or gated region. This measurement is available only on DPO models.

NDUty (negative duty cycle) is the ratio of the negative pulse width to the signal period, expressed as a percentage. The duty cycle is measured on the first cycle in the waveform or gated region.

```
Negative Duty Cycle = ((Negative\ Width) / Period) \times 100\%
```

NEDGECount is the count of falling edges.

NOVershoot (negative overshoot) finds the negative overshoot value over the entire waveform or gated region. This measurement is available only on DPO models.

```
Negative\ Overshoot = ((Low - Minimum) / Amplitude) \times 100\%)
```

NPULSECount is the count of negative pulses.

NWIdth (negative width) measurement is the distance (time) between the middle reference (default = 50%) amplitude points of a negative pulse. The measurement is made on the first pulse in the waveform or gated region.

PDUty (positive duty cycle) is the ratio of the positive pulse width to the signal period, expressed as a percentage. It is measured on the first cycle in the waveform or gated region.

```
Positive Duty Cycle = ((Positive\ Width\ /\ Period) \times 100\%
```

PEDGECount is the count of rising edges.

PERIod is the time required to complete the first cycle in a waveform or gated region. Period is the reciprocal of frequency and is measured in seconds.

PHAse measures the phase difference (amount of time a waveform leads or lags the reference waveform) between two waveforms. The measurement is made between the middle reference points of the two waveforms and is expressed in degrees, where 360° represents one waveform cycle.

PK2Pk (peak-to-peak) finds the absolute difference between the maximum and minimum amplitude in the entire waveform or gated region. This measurement is available only on DPO models.

**POVershoot** is the positive overshoot value over the entire waveform or gated region. This measurement is available only on DPO models.

Positive Overshoot =  $((Maximum - High) / Amplitude) \times 100\%$ 

PPULSECount is the count of positive pulses.

PWIdth (positive width) is the distance (time) between the middle reference (default = 50%) amplitude points of a positive pulse. The measurement is made on the first pulse in the waveform or gated region.

RISe timing measurement finds the rise time of the waveform. The rise time is the time it takes for the leading edge of the first pulse encountered to rise from a low reference value (default is 10%) to a high reference value (default is 90%). This measurement is available only on DPO models.

RMS amplitude measurement finds the true Root Mean Square voltage in the entire waveform or gated region. This measurement is available only on DPO models.

#### **Examples**

MEASUREMENT: IMMED: TYPE FREQUENCY defines the immediate measurement to be a frequency measurement.

MEASUREMENT: IMMED: TYPE? might return: MEASUREMENT: IMMED: TYPE RMS indicating that the immediate measurement is the true Root Mean Square voltage.

### MEASUrement: IMMed: UNIts? (Query Only)

Returns the units of the immediate measurement:

VOLTS, VOLTS SQUARED, SEC, HERTZ, PERCENT, DIVS, SAMPLES, OHMS, AMPS, WATTS, MINUTES, DEGREES, UNKNOWN, AMPS SQUARED, HOURS, DAYS, DB, BYTES, INVERSE HERTZ, IRE, V OVER V, V OVER A, VOLTS WATTS, V OVER W, VOLTS DB, V OVER DB, A OVER V, A OVER A, AMPS WATTS, A OVER W, AMPS DB, A OVER DB, WATTS VOLTS, W OVER V, WATTS AMPS, W OVER A, WATTS SQUARED, W OVER W, WATTS DB, W OVER DB, DB VOLTS, DB OVER V, DB AMPS, DB OVER A, DB WATTS, DB OVER W, DB SQUARED, DB OVER DB, VOLTS SEC, AMPS SEC, WATTS SEC, V OVER S, A OVER S, W OVER S

**Group** Measurement

Syntax MEASUrement:IMMed:UNIts?

**Examples** MEASUREMENT: IMMED: UNITS? might return

:MEASUREMENT:IMMED:UNIts "s"

indicating that units for the immediate measurement are in seconds.

### MEASUrement:IMMed:VALue? (Query Only)

Returns the value of the measurement specified by the MEASUrement:IMMed: TYPe command. The measurement is immediately taken on the source(s) specified by a MEASUrement:IMMed:SOUrce1 command.

**NOTE.** A change to HORizontal:MAIn:SCALe or CH<x>:SCALe will not necessarily have taken affect if immediately followed by this command.

**Group** Measurement

**Syntax** MEASUrement:IMMed:VALue?

**Related Commands** MEASUrement:IMMed:TYPe, MEASUrement:IMMed:SOUrce1, \*ESR?,

**ALLEv?** 

**Examples** MEASUREMENT:IMMED:VALUE? might return:MEASUREMENT:IMMED:VALUE

9.9000E+37. If the measurement has an error or warning associated with it, then an item is added to the error queue. The error can be checked for with the

\*ESR? and ALLEV? commands.

### **MEASUrement:INDICators? (Query Only)**

Returns all measurement indicator parameters.

**Group** Measurement

Syntax MEASUrement:INDICators?

**Examples** MEASUREMENT: INDICATORS? might return

MEASUREMENT:INDICATORS:STATE MEAS1;NUMHORZ 0;NUMVERT 4;HORZ1 7.5E0;HORZ2 -3.400000095367E0;HORZ3 0.0E0;HORZ4 0.0E0;VERT1 -6.351123E-6;VERT2 -3.179753E-6;VERT3 -6.40943E-6;VERT4

-6.403E-6

### MEASUrement:INDICators:HORZ<x>? (Query Only)

Returns the position of the specified horizontal measurement indicator  $\langle x \rangle$ , where  $\langle x \rangle$  can be 1, 2, 3, or 4.

**Group** Measurement

Syntax MEASUrement:INDICators:HORZ<x>?

**Examples** MEASUREMENT:INDICATORS:HORZ1? might return

MEASUREMENT: INDICATORS: HORZ1 -2.0E-3 indicating that horizontal

indicator1 has a value of -2 mV.

### MEASUrement:INDICators:NUMHORZ? (Query Only)

Returns the number of horizontal measurement indicators currently being displayed.

**Group** Measurement

**Syntax** MEASUrement:INDICators:NUMHORZ?

**Examples** MEASUREMENT: INDICATORS: NUMHORZ? might return

MEASUREMENT: INDICATORS: NUMHORZ 2 indicating that there are currently 2 horizontal lines drawn on the graticule. The indicators show where the measurement specified by MEASUrement: INDICators: STATE is being

performed.

### MEASUrement:INDICators:NUMVERT? (Query Only)

Returns the number of vertical measurement indicators currently being displayed.

**Group** Measurement

Syntax MEASUrement:INDICators:NUMVERT?

**Examples** MEASUREMENT: INDICATORS: NUMVERT? might return

MEASUREMENT: INDICATORS: NUMVERT 2 indicating that there are currently 2 vertical lines drawn on the graticule. The indicators show where the measurement

specified by MEASUrement:INDICators:STATE is being performed.

### MEASUrement:INDICators:STATE

Sets or returns the state of visible measurement indicators.

**Group** Measurement

Syntax MEASUrement:INDICators:STATE {OFF|MEAS<x>}

MEASUrement: INDICators: STATE?

**Arguments** OFF turns the visible measurement indicators off.

MEAS<x> displays the visible measurement indicators for measurement <x>,

where  $\langle x \rangle$  can be 1, 2, 3, or 4.

**NOTE.** There must be an active measurement before you can activate an indicator

for a specified measurement.

**Examples** MEASUREMENT:INDICATORS:STATE MEAS2 turns on the display of visible

measurement indicators for measurement 2.

MEASUREMENT: INDICATORS: STATE? might return

MEASUREMENT: INDICATORS: STATE OFF indicating that no measurement

indicators are active.

# MEASUrement:INDICators:VERT<x>? (Query Only)

Returns the value of the specified vertical measurement indicator  $\langle x \rangle$  from the trigger point, where  $\langle x \rangle$  can be 1, 2, 3, or 4. A negative value means that the indicator is positioned earlier in the waveform record than the trigger point.

**Group** Measurement

Syntax MEASUrement:INDICators:VERT<x>?

**Examples** MEASUREMENT:INDICATORS:VERT2? might return

MEASUREMENT: INDICATORS: VERT2 -3.724507E-6 indicating that the second measurement indicator is positioned 3.72 μs before the trigger point.

### MEASUrement:MEAS<x>? (Query Only)

Returns all measurement parameters for the specified active measurement <x>.

**Group** Measurement

Syntax MEASUrement:MEAS<x>?

## MEASUrement:MEAS<x>:COUNt? (Query Only)

Returns the number of values accumulated for this measurement since the last statistical reset. Values may be ignored if they generated an error. Measurements are specified by x, which ranges from 1 through 4.

**Group** Measurement

**Syntax** MEASUrement:MEAS<x>:COUNt?

**Examples** MEASUREMENT: MEAS3: COUNT? might return: MEASUREMENT: MEAS3: COUNT

3247.

## MEASUrement:MEAS<x>:DELay? (Query Only)

Returns the delay measurement parameters for the measurement specified by <x>, which ranges from 1 through 4.

**Group** Measurement

**Syntax** MEASUrement:MEAS<x>:DELay?

**Examples** MEASUREMENT: MEAS1? might return

:MEASUREMENT:MEAS1:DELAY:DIRECTION FORWARDS;EDGE1 RISE;EDGE2

RISE.

## MEASUrement:MEAS<x>:DELay:DIRection

Sets or returns the starting point and direction that determines the delay "to" edge when taking a delay measurement. Use the MEASUrement:MEAS<x>:SOURCE2 command to specify the waveform.

**Group** Measurement

**Syntax** MEASUrement:MEAS<x>:DELay:DIRection {BACKWards|FORWards}

MEASUrement:MEAS<x>:DELay:DIRection?

Related Commands MEASUrement:MEAS<x>:SOURCE2

**Arguments** BACKWards means the search starts at the end of the waveform and

looks for the last rising or falling edge in the waveform. Use the MEASUrement:MEAS<x>:DELay:EDGE<x> command to specify the slope

of the edge.

FORwards means the search starts at the beginning of the waveform and looks for the first rising or falling edge in the waveform. Use the MEASUrement:MEAS<x>:DELay:EDGE<x> command to specify the slope

of the edge.

**Examples** MEASUREMENT: MEAS3: DELAY: DIRECTION BACKWARDS starts searching from

the end of the waveform record.

MEASUREMENT: MEAS3: DELAY: DIRECTION? might return

:MEASUREMENT:MEAS3:DELAY:DIRECTION BACKWARDS indicating

that the current search direction is backwards.

### MEASUrement:MEAS<x>:DELay:EDGE<x>

Sets or returns the slope of the edge used for the delay "from" or "to" waveform when taking an immediate delay measurement. The waveform is specified by

MEASUrement:MEAS<x>:SOURCE[1].

**Group** Measurement

Syntax MEASUrement:MEAS<x>:DELay:EDGE<x> {FALL|RISe}

MEASUrement:MEAS<x>:DELay:EDGE<x>?

**Arguments**  $\langle x \rangle$  specifies which waveform to use, where  $\langle x \rangle = 1$  is the "from" waveform, and

 $\langle x \rangle = 2$  is the "to" waveform.

FALL specifies the falling edge.

RISe specifies the rising edge.

**Examples** MEASUREMENT: MEAS1: DELAY: EDGE1 RISE specifies that the "from" waveform

rising edge be used for the immediate delay measurement.

MEASUREMENT: MEAS1: DELAY: EDGE1? returns either RISE or FALL.

## MEASUrement:MEAS<x>:MAXimum? (Query Only)

Returns the maximum value found for this measurement since the last statistical reset. Measurements are specified by x, which ranges from 1 through 4.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:MAXimum?

**Examples** MEASUREMENT: MEAS3: MAXIMUM? might return

:MEASUREMENT:MEAS3:MAXIMUM 4.18E-9.

### MEASUrement:MEAS<x>:MEAN? (Query Only)

Returns the mean value accumulated for this measurement since the last statistical reset. Measurements are specified by x, which ranges from 1 through 4.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:MEAN?

**Examples** MEASUREMENT: MEAS1: MEAN? might return: MEASUREMENT: MEAS1: MEAN

514.71E-09.

### MEASUrement:MEAS<x>:MINImum? (Query Only)

Returns the minimum value for this measurement since the last statistical reset. Measurements are specified by  $\langle x \rangle$ , which ranges from 1 through 4.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:MINImum?

**Examples** MEASUREMENT: MEAS1: MINIMUM? might return

:MEASUREMENT:MEAS1:MINIMUM 1.75E-09.

# MEASUrement:MEAS<x>:SOURCE[1]

Sets or returns the source for all single source measurements and specifies the source to measure "from" when taking a delay measurement or phase measurement. Measurements are specified by <x>, which ranges from 1 through 4.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:SOURCE[1] {CH<x>|MATH<y>|REF<x>}

MEASUrement:MEAS<x>:SOURCE[1]?

**Arguments** CH<x> is an input channel waveform, where x is the channel number.

MATH<y> is a math waveform, where y is 1.

REF<x> is a reference waveform, where x is the reference channel number.

**Examples** MEASUREMENT: MEAS2: SOURCE1 MATH1 specifies Math 1 as the measurement

2 source.

MEASUREMENT: MEAS1: SOURCE1? might return

:MEASUREMENT:MEAS1:SOURCE[1] MATH1 indicating that Math1 is the

measurement 2 source.

### MEASUrement:MEAS<x>:SOURCE2

Sets or returns the reference source to measure "to" when taking a delay measurement or phase measurement. Measurements are specified by <x>, which ranges from 1 through 4.

**NOTE.** Source2 measurements only apply to phase and delay measurement types, which require both a target (Source1) and reference (Source2) source.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:SOURCE2 {CH<x>|MATH<y>|REF<x>}

MEASUrement:MEAS<x>:SOURCE2?

**Related Commands** MEASUrement:MEAS<x>:TYPe

**Arguments** CH<x> is an input channel waveform, where x is the channel number.

MATH<y> is the math waveform, which is always 1.

REF<x> is a reference waveform, where x is the reference channel number.

**Examples** MEASUREMENT: MEAS4: SOURCE2 CH1 specifies CH1 as the delay "to" source

when making delay measurement.

MEASUREMENT: MEAS2: SOURCE2? might return

:MEASUREMENT:MEAS2:SOURCE2 MATH1 indicating that Math 1 is the

measurement 2 source.

### MEASUrement:MEAS<x>:SOUrce<x>

For SOURce1: Sets or returns the source for all single channel measurements. For delay or phase measurements, sets or returns the waveform to measure "from".

For SOUrce2: Sets or returns the waveform to measure "to" when taking a delay

measurement or phase measurement.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:SOUrce<x> {CH<x>|MATH|}

MEASUrement:MEAS<x>:SOUrce<x>?

**Arguments** CH<x> is an input channel waveform, where x is the channel number.

MATH is the math waveform.

REF<x> is a reference waveform, where x is the reference channel number.

### MEASUrement:MEAS<x>:STATE

Sets or returns whether the specified measurement slot is computed and displayed. The measurement slot is specified by  $\langle x \rangle$ , which ranges from 1 through 4.

For a measurement to display, you must have selected a source waveform and defined the measurement you want to take and display. You select the measurement using the MEASUrement:MEAS<x>:SOURCE[1] command. You define the measurement type using the MEASUrement:MEAS<x>:TYPe command.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:STATE {OFF|ON|<NR1>}

MEASUrement:MEAS<x>:STATE?

**Related Commands** MEASUrement:MEAS<x>:SOURCE[1], MEASUrement:MEAS<x>:TYPe

**Arguments** OFF disables calculation and display of the specified measurement slot.

ON enables calculation and display of the specified measurement slot.

<NR1> = 0 disables calculation and display of the specified measurement slot; any other value enables calculation and display of the specified measurement slot.

**Examples** MEASUREMENT: MEAS2: STATE ON computes and displays the measurement

defined as measurement 2.

MEASUREMENT: MEAS1: STATE? might return: MEASUREMENT: MEAS1: STATE 0 indicating that measurement defined for measurement slot 1 is disabled.

### MEASUrement:MEAS<x>:STDdev? (Query Only)

Returns the standard deviation of values accumulated for this measurement since the last statistical reset. Measurements are specified by <x>, the measurement slots, from 1 through 4.

**Group** Measurement

**Syntax** MEASUrement:MEAS<x>:STDdev?

**Examples** MEASUREMENT: MEAS1: STDDEV? might return: MEASUREMENT: MEAS1: STDDEV

21.0E-12.

### MEASUrement:MEAS<x>:TYPe

Sets or returns the measurement type defined for the specified measurement slot. The measurement slot is specified by <x>, which ranges from 1 through 4.

**Group** Measurement

**Syntax** MEASUrement:MEAS<x>:TYPe

{AMPlitude|AREa|BURSt|CARea|CMEan|CRMs|DELay|FALL|FREQuency | HIGH|LOW|MAXimum|MEAN|MINImum|NDUty|NEDGECount|NOVershoot | NPULSECount|NWIdth|PDUty|PEDGECount|PERIOd|PHASe|PK2Pk

| POVershoot | PPULSECount | PWIdth | RISe | RMS }

MEASUrement:MEAS<x>:TYPe?

#### **Arguments**

AMPlitude measures the amplitude of the selected waveform. In other words, it measures the high value less the low value measured over the entire waveform or gated region. This measurement is available only on DPO models.

Amplitude = High - Low

AREa measures the voltage over time. The area is over the entire waveform or gated region and is measured in volt-seconds. The area measured above the ground is positive, while the area below ground is negative. This measurement is available only on DPO models.

BURST measures the duration of a burst. The measurement is made over the entire waveform or gated region.

CARea (cycle area) measures the voltage over time. In other words, it measures, in volt-seconds, the area over the first cycle in the waveform or the first cycle in the gated region. The area measured above the common reference point is positive, while the area below the common reference point is negative. This measurement is available only on DPO models.

CMEan (cycle mean) measures the arithmetic mean over the first cycle in the waveform or the first cycle in the gated region. This measurement is available only on DPO models.

CRMs (cycle rms) measures the true Root Mean Square voltage over the first cycle in the waveform or the first cycle in the gated region. This measurement is available only on DPO models.

DELay measures the time between the middle reference (default = 50%) amplitude point of the source waveform and the destination waveform. This measurement is available only on DPO models.

FALL measures the time taken for the falling edge of the first pulse in the waveform or gated region to fall from a high reference value (default is 90%) to

a low reference value (default is 10%). This measurement is available only on DPO models.

FREQuency measures the first cycle in the waveform or gated region. Frequency is the reciprocal of the period and is measured in hertz (Hz), where 1 Hz = 1 cycle per second.

HIGH measures the High reference (100% level, sometimes called Topline) of a waveform. This measurement is available only on DPO models.

LOW measures the Low reference (0% level, sometimes called Baseline) of a waveform. This measurement is available only on DPO models.

MAXimum finds the maximum amplitude. This value is the most positive peak voltage found. It is measured over the entire waveform or gated region. This measurement is available only on DPO models.

MEAN amplitude measurement finds the arithmetic mean over the entire waveform or gated region. This measurement is available only on DPO models.

MINImum finds the minimum amplitude. This value is typically the most negative peak voltage. It is measured over the entire waveform or gated region. This measurement is available only on DPO models.

NDUty (negative duty cycle) is the ratio of the negative pulse width to the signal period, expressed as a percentage. The duty cycle is measured on the first cycle in the waveform or gated region.

```
Negative Duty Cycle = ((Negative\ Width) / Period) \times 100\%
```

NEDGECount is the count of negative edges.

NOVershoot (negative overshoot) finds the negative overshoot value over the entire waveform or gated region. This measurement is available only on DPO models.

```
Negative\ Overshoot = ((Low - Minimum) / Amplitude) \times 100\%)
```

NPULSECount is the count of negative pulses.

NWIdth (negative width) measurement is the distance (time) between the middle reference (default = 50%) amplitude points of a negative pulse. The measurement is made on the first pulse in the waveform or gated region.

PDUty (positive duty cycle) is the ratio of the positive pulse width to the signal period, expressed as a percentage. It is measured on the first cycle in the waveform or gated region.

```
Positive Duty Cycle = ((Positive\ Width) / Period) \times 100\%
```

PEDGECount is the count of positive edges.

PERIod is the time required to complete the first cycle in a waveform or gated region. Period is the reciprocal of frequency and is measured in seconds.

PHAse measures the phase difference (amount of time a waveform leads or lags the reference waveform) between two waveforms. The measurement is made between the middle reference points of the two waveforms and is expressed in degrees, where 360° represents one waveform cycle.

PK2Pk (peak-to-peak) finds the absolute difference between the maximum and minimum amplitude in the entire waveform or gated region. This measurement is available only on DPO models.

**POVershoot** is the positive overshoot value over the entire waveform or gated region. This measurement is available only on DPO models.

Positive Overshoot =  $((Maximum - High) / Amplitude) \times 100\%$ 

PPULSECount is the count of positive pulses.

PWIdth (positive width) is the distance (time) between the middle reference (default = 50%) amplitude points of a positive pulse. The measurement is made on the first pulse in the waveform or gated region.

RISe timing measurement finds the rise time of the waveform. The rise time is the time it takes for the leading edge of the first pulse encountered to rise from a low reference value (default is 10%) to a high reference value (default is 90%). This measurement is available only on DPO models.

RMS amplitude measurement finds the true Root Mean Square voltage in the entire waveform or gated region. This measurement is available only on DPO models.

#### **Examples**

MEASUREMENT: MEAS2: TYPE FREQUENCY defines measurement 2 as a measurement of the frequency of a waveform.

MEASUREMENT: MEAS1: TYPE? might return: MEASUREMENT: MEAS1: TYPE RMS indicating that measurement 1 is defined to measure the RMS value of a waveform.

## MEASUrement:MEAS<x>:UNIts? (Query Only)

Returns the units associated with the specified measurement. The measurement slots are specified by  $\langle x \rangle$ , which ranges from 1 through 4.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:UNIts?

**Related Commands** MEASUrement:MEAS<x>:TYPe

#### **Examples**

MEASUREMENT: MEAS1: UNITS? might return: MEASUREMENT: MEAS1: UNITS % indicating units for measurement 1 are set to percent.

# MEASUrement:MEAS<x>:VALue? (Query Only)

Returns a calculate value for the measurement specified by <x>, which ranges from 1 through 4.

**NOTE.** This is the same value as displayed on-screen. If measurement statistics are enabled, a new value is calculated with every waveform. In addition, this value is updated approximately every 1/3 second. If you are acquiring a long acquisition record, the oscilloscope may take longer to update.

**Group** Measurement

Syntax MEASUrement:MEAS<x>:VALue?

**Related Commands** MEASUrement:MEAS<x>:UNIts?, \*ESR?, ALLEv?

**Examples** MEASUREMENT: MEAS1: VALUE? might return: MEASUREMENT: MEAS1: VALUE

2.8740E-06. If the measurement has an error or warning associated with it, then an item is added to the error queue. The error can be checked for with the

\*ESR? and ALLEV? commands.

### **MEASUrement: METHod**

Sets or returns the method used to calculate the 0% and 100% reference level.

**Group** Measurement

Syntax MEASUrement:METHod {Auto|HIStogram|MINMax}

MEASUrement: METHod?

Related Commands MEASUrement:REFLevel:PERCent:HIGH, MEASUrement:REFLevel:PERCent:

LOW, MEASUrement:REFLevel:PERCent:MID, MEASUrement:REFLevel:

PERCent:MID2

#### **Arguments**

Auto selects the best method for each data set.

HIStogram sets the high and low waveform levels statistically using a histogram algorithm.

MINMax uses the highest and lowest values of the waveform record. This selection is best for examining waveforms with no large, flat portions of a common value, such as sine waves and triangle waves.

#### **Examples**

MEASUREMENT: METHOD? might return: MEASUREMENT: METHOD MINMAX indicating that the reference levels are set to MIN and MAX.

### MEASUrement:REFLevel? (Query Only)

Returns the current reference level parameters.

Group

Measurement

**Syntax** 

MEASUrement: REFLevel?

#### **Examples**

MEASUREMENT: REFLEVEL? might return these reference

level settings :MEASUREMENT:REFLEVEL:METHOD

PERCENT; ABSOLUTE: HIGH 0.0000; LOW 0.0000; MID1 0.0000; MID2 0.0000; MEASUREMENT: REFLEVEL: PERCENT: HIGH 90.0000; LOW

10.0000; MID1 50.0000 ; MID2 50.0000

### MEASUrement:REFLevel:ABSolute:HIGH

Sets or returns the high reference level, and is the upper reference level when MEASUrement:REFLevel:METHod is set to Absolute. This command affects the results of rise and fall measurements

**NOTE.** this command affects the associated reference level parameter for all MEASurements: IMMed and the four periodic measurements.

Group

Measurement

**Syntax** 

MEASUrement:REFLevel:ABSolute:HIGH <NR3>
MEASUrement:REFLevel:ABSolute:HIGH?

Related Commands MEASUrement:REFLevel:METHod, MEASUrement:IMMed:TYPe,

MEASUrement:MEAS<x>:TYPe

**Arguments** <NR3> is the high reference level, in volts. The default is 0.0 V.

**Examples** MEASUREMENT: REFLEVEL: ABSOLUTE: HIGH 1.71 sets the high reference level

to 1.71 V.

MEASUREMENT: REFLEVEL: ABSOLUTE: HIGH? might return

:MEASUREMENT:REFLEVEL:ABSOLUTE:HIGH 1.7100E+00 indicating that the

absolute high reference level is set to 1.71 V.

### MEASUrement:REFLevel:ABSolute:LOW

Sets or returns the low reference level, and is the lower reference level when MEASUrement:REFLevel:METHod is set to Absolute.

**NOTE.** this command affects the associated reference level parameter for all MEASurements: IMMed and the four periodic measurements.

**Group** Measurement

Syntax MEASUrement:REFLevel:ABSolute:LOW <NR3>

MEASUrement: REFLevel: ABSolute: LOW?

**Related Commands** MEASUrement:REFLevel:METHod, MEASUrement:IMMed:TYPe,

MEASUrement:MEAS<x>:TYPe

**Arguments** <NR3> is the low reference level, in volts. The default is 0.0 V.

**Examples** MEASUREMENT: REFLEVEL: ABSOLUTE: LOW 0.0 sets the low reference level

to 0.0 V.

MEASUREMENT: REFLEVEL: ABSOLUTE: LOW? might return

:MEASUREMENT:REFLEVEL:ABSOLUTE:LOW 0.0000E+00 indicating

that the absolute low reference level is set to 0.0 V.

# MEASUrement:REFLevel:ABSolute:MID[1]

Sets or returns the mid reference level, and is the 50% reference level when MEASUrement:REFLevel:METHod is set to Absolute. This command affects the results of period, frequency, delay, and all cyclic measurements.

**NOTE.** this command affects the associated reference level parameter for all MEASurements: IMMed and the four periodic measurements.

**Group** Measurement

Syntax MEASUrement:REFLevel:ABSolute:MID[1] <NR3>

MEASUrement:REFLevel:ABSolute:MID[1]?

Related Commands MEASUrement:REFLevel:METHod

**Arguments** <NR3> is the mid reference level, in volts. The default is 0.0 V.

**Examples** MEASUREMENT: REFLEVEL: ABSOLUTE: MID 1 .71 sets the mid reference level

to 0.71 V.

MEASUREMENT: REFLEVEL: ABSOLUTE: MID? might return

:MEASUREMENT:REFLEVEL:ABSOLUTE:MID 0.7100E+00 indicating

that the absolute mid1 reference level is set to 0.71 V.

### MEASUrement:REFLevel:ABSolute:MID2

Sets or returns the mid reference level for the "to" waveform when taking a delay measurement, and is the 50% reference level when MEASUrement:REFLevel:METHod is set to Absolute. This command affects the results of delay measurements.

**NOTE.** this command affects the associated reference level parameter for all MEASurements:IMMed and the four periodic measurements.

**Group** Measurement

Syntax MEASUrement:REFLevel:ABSolute:MID2 <NR3>

MEASUrement:REFLevel:ABSolute:MID2?

Related Commands MEASUrement:REFLevel:METHod

**Arguments** <NR3> is the mid reference level, in volts. The default is 0.0 V.

**Examples** MEASUREMENT: REFLEVEL: ABSOLUTE: MID2 0.5 sets the mid reference level for

the delay waveform to 0.5 V.

MEASUREMENT: REFLEVEL: ABSOLUTE: MID2? might return

:MEASUREMENT:REFLEVEL:ABSOLUTE:MID2 0.5000E+00 indicating that the

absolute mid2 reference level is set to 0.5 V.

## MEASUrement:REFLevel:ABSolute:MID<x>

Sets or returns the mid reference level for channel  $\langle x \rangle$ , where x is the measurement channel.

**Group** Measurement

Syntax MEASUrement:REFLevel:ABSolute:MID<x> <NR3>

MEASUrement:REFLevel:ABSolute:MID<x>?

**Arguments** <NR3> is the mid reference level in volts.

## MEASUrement:REFLevel:METHod

Specifies or returns the reference level units used for measurement calculations.

**NOTE.** this command affects the associated reference level parameter for all MEASurements: IMMed and the eight periodic measurements. To change the parameter for individual measurements, use the MEASUrement: MEAS<x>:REFLevel commands.

**Group** Measurement

Syntax MEASUrement:REFLevel:METHod {ABSolute|PERCent}

MEASUrement:REFLevel:METHod?

**Arguments** ABSolute specifies that the reference levels are set explicitly using the

MEASUrement:REFLevel:ABSolute commands. This method is useful when

precise values are required (for example, when designing to published interface specifications, such as RS-232-C).

PERCent specifies that the reference levels are calculated as a percent relative to HIGH and LOW. The percentages are defined using the MEASUrement:REFLevel:PERCent commands.

### **Examples**

MEASUREMENT: REFLEVEL: METHOD ABSOLUTE specifies that explicit user-defined values are used for the reference levels.

MEASUREMENT: REFLEVEL: METHOD? might return

:MEASUREMENT: REFLEVEL: METHOD PERCENT indicating that the reference level units used are calculated as a percent relative to HIGH and LOW.

## MEASUrement:REFLevel:PERCent:HIGH

Sets or returns the percent (where 100% is equal to HIGH) used to calculate the high reference level when MEASUrement:REFLevel:METHod is set to Percent. This command affects the results of rise and fall measurements.

**NOTE.** This command affects the associated reference level parameter for all MEASurements: IMMed and the four periodic measurements.

**Group** Measurement

Syntax MEASUrement:REFLevel:PERCent:HIGH <NR3>

MEASUrement:REFLevel:PERCent:HIGH?

**Related Commands** MEASUrement:REFLevel:METHod, MEASUrement:IMMed:TYPe,

MEASUrement:MEAS<x>:TYPe

**Arguments** <NR3> is the high reference level, ranging from 0 to 100%. The default high

reference level is 90%.

**Examples** MEASUREMENT: REFLEVEL: PERCENT: HIGH 95 sets the high reference level

to 95% of HIGH.

MEASUREMENT: REFLEVEL: PERCENT: HIGH? might return

:MEASUREMENT:REFLEVEL:PERCENT:HIGH 90 indicating that the

percentage high reference level is set to 90% of HIGH.

## MEASUrement:REFLevel:PERCent:LOW

Sets or returns the percent (where 100% is equal to HIGH) used to calculate the low reference level when MEASUrement:REFLevel:METHod is set to Percent. This command affects the results of rise and fall measurements.

**NOTE.** this command affects the associated reference level parameter for all MEASurements: IMMed and the four periodic measurements.

**Group** Measurement

Syntax MEASUrement:REFLevel:PERCent:LOW <NR3>

MEASUrement:REFLevel:PERCent:LOW?

Related Commands MEASUrement:REFLevel:METHod, MEASUrement:IMMed:TYPe,

MEASUrement:MEAS<x>:TYPe

**Arguments** <NR3> is the low reference level, ranging from 0 to 100%. The default low

reference level is 10%.

**Examples** MEASUREMENT: REFLEVEL: PERCENT: LOW 15 sets the high reference level to

15% of HIGH.

MEASUREMENT: REFLEVEL: PERCENT: LOW? might return

:MEASUREMENT:REFLEVEL:PERCENT:LOW 10 indicating that the

percentage high reference level is set to 10% of HIGH.

## MEASUrement:REFLevel:PERCent:MID[1]

Sets or returns the percent (where 100% is equal to HIGH) that is used to calculate the mid reference level when MEASUrement:REFLevel:METHod is set to Percent. This command affects the results of period, frequency, delay, and all cyclic measurements.

**NOTE**. this command affects the associated reference level parameter for all MEASurements: IMMed and the four periodic measurements.

**Group** Measurement

Syntax MEASUrement:REFLevel:PERCent:MID[1] <NR3>

MEASUrement:REFLevel:PERCent:MID[1]?

Related Commands MEASUrement: REFLevel: METHod

**Arguments** <NR3> is the mid reference level, ranging from 0 to 100%. The default mid

reference level is 50%.

**Examples** MEASUREMENT: REFLEVEL: PERCENT: MID 1 60 sets the mid reference level

to 60% of HIGH.

MEASUREMENT: REFLEVEL: PERCENT: MID? might return

:MEASUREMENT:REFLEVEL:PERCENT:MID 65 indicating that the

percentage mid reference level is set to 65% of HIGH.

## MEASUrement:REFLevel:PERCent:MID2

Sets or returns the percent (where 100% is equal to HIGH) that is used to calculate the mid reference level for the second waveform specified when MEASUrement:REFLevel:METHod is set to Percent. This command affects the results of delay measurements.

**NOTE.** this command affects the associated reference level parameter for all MEASurements:IMMed and the four periodic measurements.

**Group** Measurement

Syntax MEASUrement:REFLevel:PERCent:MID2 <NR3>

MEASUrement:REFLevel:PERCent:MID2?

**Related Commands** MEASUrement:REFLevel:METHod

**Arguments** <NR3> is the mid reference level, ranging from 0 to 100%. The default mid

reference level is 50%.

**Examples** MEASUREMENT: REFLEVEL: PERCENT: MID2 40 sets the mid2 reference level

to 40% of HIGH.

MEASUREMENT: REFLEVEL: PERCENT: MID2? might return

:MEASUREMENT:REFLEVEL:PERCENT:MID2 45 indicating that the

percentage mid2 reference level is set to 45% of HIGH.

## MEASUrement:REFLevel:PERCent:MID<x>

Sets or returns the mid reference level for channel  $\langle x \rangle$ , where x is the measurement channel.

**Group** Measurement

Syntax MEASUrement:REFLevel:PERCent:MID<x> <NR3>

MEASUrement:REFLevel:PERCent:MID<x>?

**Arguments** <NR3> is the mid reference level in percent.

# **MEASUrement:SNAPShot (No Query Form)**

Displays the measurement snapshot list on the oscilloscope screen. The list contains the immediate values for all available measurements of the active signal.

**Group** Measurement

**Syntax** MEASUrement:SNAPShot

# **MESSage**

This command sets or queries message parameters.

**Group** Miscellaneous

Syntax MESSage MESSage?

**Examples** MESSAGE? might return MESSAGE: SHOW "TP401"; BOX

271,82,292,114; STATE 0 indicating that the message parameters.

# MESSage:BOX

Sets or returns the size and position of the message window. This command does not display the message unless MESSage:STATE is on.

X1 and Y1 are the screen coordinates of the top left corner of the message box. X2 and Y2 are the screen coordinates of the bottom right corner of the message box. All four coordinates are returned by the query.

Changing the text in the message box, using the MESSAGE:SHOW command, automatically resizes the message box. If you want a custom message box size, send the MESSAGE:BOX command after changing the text using the MESSAGE:SHOW command.

Message box settings and data are saved and restored in saved setups.

**Group** Display

**Syntax** MESSage:BOX <X1>,<Y1>[,<X2>,<Y2>]

MESSage:BOX?

Related Commands MESSage:STATE, MESSage:SHOW, MESSage:CLEAR

**Arguments** <X1> and <X2> = 0 to 1023, and are pixel positions along the horizontal axis.

<X1> defines the left and <X2> defines the right side of the window.

<Y1> and <Y2> = 0 to 767, and are pixel positions along the vertical axis. <Y1> defines the top and <Y2> defines the bottom of the window. The reserved height of all characters is 16 pixels so the window must be at least that high to fully display characters. <X2> and <Y2> are optional because the MESSAGE: SHOW command automatically sizes the box to fit the message. All four values are returned in a query.

# MESSage:CLEAR (No Query Form)

Removes the message text from the message window.

**Group** Display

Syntax MESSage:CLEAR

**Related Commands** MESSage:BOX, MESSage:SHOW, MESSage:STATE

**Examples** MESSage:CLEAR

removes the message from the message window.

# MESSage:SHOW

Clears the contents of the message window and displays the new message in the window. Changing the string length causes the message box to automatically resize to fit the text. The box may be resized using the MESSage:BOX command.

**Group** Display

Syntax MESSage:SHOW <QString>

MESSage: SHOW?

Related Commands MESSage:BOX, MESSage:CLEAR, MESSage:STATE

Arguments <QString> is the message and can include any of the characters shown in the Character Set, Appendix A. The maximum length of the message is 1000 characters; the instrument ignores longer strings.

The message box size is set to fit the message. You can also set the message area height and width using the MESSage:BOX command. The length of the message that fits in the message area depends on the contents of the message because the width of characters varies.

If the message exceeds the limits of the message box, either horizontally or vertically, the portion of the message that exceeds the limits will not be displayed. The message string itself is not altered. The entire message can be returned as a query response regardless of what is displayed in the message box.

The message is left-justified, and is displayed on a single line starting with the top most line in the window. A new line character can be embedded in the string to position the message on multiple lines. You can also use white space and tab characters to position the message within a line. Text which does not fit within the message box is truncated. Defining a message box text string erases any previously displayed text within the message box.

You can send a tab by transmitting a tab character (\t or \x09) followed characters representing the most significant eight bits followed by significant eight bits of a 16-bit number. The number specifies the position relative to the left margin of the message area. For example, to tab send TAB (\t or \x09), NUL (decimal 0), and CR (decimal 13).

For example, using hexadecimal escape sequences, MESSAGE:SHOW '\x09\x01\x17Hello' when sent as a command would cause the 'Hello' to be displayed starting at pixel position 279 relative to the left margin set by the MESSAGE:BOX command. If you want to display characters starting at position 279, then 279 = 0x0117; split the hexadecimal number into two characters 0x01 and 0x17 and send x09x01x17.

Special characters which control decoration are two character sequences where the first character is an escape (0x1b) and the second character is as described below.

Bit 7	0		
Bit 6	If set, inverse video is toggled from current state and the following text is displayed in the new inverse state until the state is toggled again. Remaining bits are ignored		
Bit 5	If set, the color index in the four LSB's (bits 0 through 3) is applied to the foreground or background color depending on the fg/bg bit (bit 4).		
Bit 4	If set, color change is applied to the background, otherwise applies to the foreground.		
Bit 0 – 3	Specifies the color index (0 through 15) to change color as specified below:		
	Index 0	Black (background)	
	Index 1	Yellow (Ch 1)	
	Index 2	Cyan (Ch 2)	
	Index 3	Magenta (Ch 3)	
	Index 4	Green (Ch 4)	
	Index 5	Red (math)	
	Index 6	White (reference)	
	Index 7	Orange	
	Index 8	Gray (Graticule)	
	Index 9	White (text)	
	Index 10	Tek blue	
	Index 11	Bright blue	
	Index 12	Undefined	
	Index 13	Blue	
	Index 14	Undefined	
	Index 15	Dark blue	
Bit 4	If set, the foreground color is set to the default foreground color.		
Bit 3	If set, the background color is set to the default background color.		
Bit 2	Undefined		
Bit 1	Undefined		
Bit 0	Undefined		

The ESC (escape) character followed by the @ character turns inverse video on or off and can be embedded in the message string. Example: "abcESC@defESC@ghi" specifies the string "abcdefghi" where the "def" portion is displayed in inverse video.

Example: "abcESC#defESC)ESC@ghi" specifies the string "abcdefghi" where the "def" portion appears in the channel 3 color (magenta) and the "ghi" portion appears in the normal text color except it's in inverse video.

An alternate way to enter characters is octal escape sequences. This consists of a backslash followed by numerals in the standard C language printf fashion.

Another way to enter characters is \xnn where the nn is the hexadecimal value of the character to display.

An advantage of these methods is that any controller program can be used. Another advantage is it's easy to access characters with the high bit set, that is, those characters with a decimal value greater than 127.

An alternate way to enter certain characters is with a backslash followed by a single character (following "standard" Unix) as described in the table below.

n	Newline (carriage return and line feed)
1	Backslash (\\ is required to get a backslash character)
t	Horizontal tab; the next 2 characters specify the pixel column to tab to as explained earlier

If a backslash is followed by an undefined special character, the backslash is ignored and the character following it is accepted as is.

**NOTE.** The use of any escape codes other than those described above may produce unpredictable results.

## **Examples**

MESSage:SHOW "Hello World"

displays "Hello world" in the upper left corner of the box (you can define the box size with the MESSAGE BOX command).

MESSage:SHOW "←@Hello World←@ ... hello"

displays "Hello world ... hello" in the upper left corner of the box and the word "world" is displayed in inverse video. In this example,  $\leftarrow$  stands for the escape character. The escape character may appear differently for you depending on your controller program.

# MESSage:STATE

Controls the display of the message window on the screen.

**Group** Display

Syntax MESSage:STATE {OFF|ON|<NR1>}

MESSage: STATE?

Related Commands MESSage:BOX

#### MESSage:SHOW, MESSage:CLEAR

#### Arguments OFF

OFF or  $\langle NR1 \rangle = 0$  removes the message window from the screen.

ON or  $\langle NR1 \rangle \neq 0$  displays the message window and its contents on the screen.

# **NEWpass (No Query Form)**

This command changes the password that enables access to password protected data. The PASSWord command must be successfully executed before using this command or an execution error will be generated.

Group

Miscellaneous

**Syntax** 

NEWpass <QString>

**Related Commands** 

\*PUD

**PASSWord** 

**Arguments** 

<QString> is the new password, which can contain up to 16 characters.

**Examples** 

NEWPASS "mypassword" creates a new password (mypassword) for accessing your protected data.

\*OPC

Generates the operation complete message in the Standard Event Status Register (SESR) when all pending commands that generate an OPC message are complete. The \*OPC? query places the ASCII character "1" into the output queue when all such OPC commands are complete. The \*OPC? response is not available to read until all pending operations finish. (See page 3-1, *Status and Events*.)

The \*OPC command allows you to synchronize the operation of the oscilloscope with your application program. (See page 3-7, *Synchronization Methods*.)

Table 2-40: Commands that Generate an OPC Message

Operation	Command
Single sequence acquisition	ACQuire:STATE {ON NR 1}
	AUXin:PRObe:DEGAUss EXECute
	CH <x>:PRObe:DEGAUss EXECute</x>
	DIAg:STATE EXECute
	RECAll:SETUp <file path=""></file>
	RECAll:WAVEform <file path="">,REF<x></x></file>
	SAVe:IMAGe <file path=""></file>
	SAVe:SETUp <file path=""></file>
	SAVe:WAVEform <wfm>, {REF<x>}</x></wfm>
	TEKSecure
Hard copy operation	HARDCopy START
Calibration step	CALibrate:FACtory {STARt PREVious CONTinue}

**Group** Status and Error

Syntax \*OPC \*OPC?

Related Commands BUSY?, \*WAI

### **Examples**

\*OPC generates the operation complete message in the SESR at the completion of all pending OPC operations.

\*OPC? might return 1 to indicate that all pending OPC operations are finished.

## PASSWord(No Query Form)

Enables the \*PUD and NEWpass set commands. Sending PASSWord without any arguments disables these same commands. Once the password is successfully entered, the \*PUD and NEWpass commands are enabled until the oscilloscope is powered off, or until the FACtory command or the PASSWord command with no arguments is issued.

To change the password, you must first enter the valid password with the PASSWord command and then change to your new password with the NEWpass command. Remember that the password is case sensitive.

**Group** Miscellaneous

Syntax PASSWord <QString>

Related Commands NEWpass, \*PUD

**Arguments** <QString> is the password and can include up to 10 characters. The factory

default password is "XYZZY" and is always valid.

**Examples** PASSWORD "XYZZY" enables the \*PUD and NEWpass set commands.

PASSWORD disables the \*PUD and NEWpass set commands. You can still use the

query version of \*PUD.

# **PICTBridge:DATEPrint**

Enables or disables printing the date on the print output.

**Group** PictBridge

Syntax PICTBridge:DATEPrint {DEFLT|OFF|ON}

**Arguments** DEFLT is the default setting of the printer.

ON enables the date print on the print output.

OFF disables the date print on the print output.

**Examples** PICTBRIDGE:DATEPRINT? might return PICTBRIDGE:DATEPRINT DEFLT

indicating that the default setting of the printer.

PICTBRIDGE: DATEPRINT ON enables the date print on the print output.

# PICTBridge:DEFault (No Query Form)

Sets the arguments for all PictBridge commands to their default values. The

default values are the same as printer default settings.

**Group** PictBridge

Syntax PICTBridge:DEFault

**Examples** PICTBRIDGE: DEFAULT sets all the PictBridge commands to their default values.

PICTBridge:IDPrint

Enables or disables printing the oscilloscope model and serial number on the

print output.

**Group** PictBridge

Syntax PICTBridge:IDPrint {DEFLT|OFF|ON}

PICTBridge:IDPrint?

**Related Commands** 

**Arguments** OFF disables the oscilloscope model and serial number print on the print output.

ON enables the oscilloscope model and serial number print on the print output.

Default is provided for compatibility with TDS instruments that support

pictbridge.

**Examples** PICTBRIDGE:IDPRINT? might return PICTBRIDGE:IDPRINT 0 indicating that

the ID print is disabled on the print output.

PICTBRIDGE: IDPRINT ON enables the printing of oscilloscope model and serial

number on the print output.

PICTBridge: IMAGESize

Sets or returns the image print size.

Group PictBridge

Syntax PICTBridge:IMAGESize {DEFLT|IN2P5BY3P25|L|IN4BY6|L2|

IN8BY10|L4|E|CARD|HAGAKIPC|CM6BY8|CM7BY10|CM9BY13|
CM10BY15|CM13BY18|CM15BY21|CM18BY24| A4|LETTER}

**Arguments** DEFLT for a default image print size.

IN2P5BY3P25 for a 2 5\*3 25 image print size.

L for a 3 5\*5 image print size.

IN4BY6 for a 4\*6 image print size.

L2 for a 5\*7 image print size.

IN8BY10 for a 8\*10 image print size.

L4 for a 254 MM\*178 MM image print size.

E for a 110 MM\*74 MM image print size.

CARD for a 89 MM\*55MM image print size.

HAGAKIPC for a 100 MM\*148 MM image print size.

CM6BY8 for a 6 CM\*8 CM image print size.

CM7BY10 for a 7 CM\*10 CM image print size.

CM9BY13 for a 9 CM\*13 CM image print size.

CM10BY15 for a 10 CM\*15 CM image print size.

CM13BY18 or a 13 CM\*18 CM image print size.

CM15BY21 for a 15 CM\*21 CM image print size.

CM18BY24 for a 18 CM\*24 CM image print size.

A4 for a A4 image print size.

LETTER for a Letter image print size.

#### **Examples**

PICTBRIDGE: IMAGESIZE? might return PICTBRIDGE: IMAGESIZE DEFLT

indicating that the default image print size.

PICTBRIDGE: IMAGESIZE CARD sets the image print size to 89 MM\* 55 MM.

# PICTBridge:PAPERSize

Sets the output print paper size.

Group

PictBridge

**Syntax** 

PICTBridge: PAPERSize

{DEFLT|L|L2|HAGAKIPCARD|MM54BY86|MM100BY150

|IN4BY6|IN8BY10|LETTER|IN11BY17|A0|A1|A2|A3|A4|A5|A6|A7|A8|A9|

B0|B1|B2|B3|

B4|B5|B6|B7|B8|B9|ROLL89MM|ROLL127MM|ROLL100MM|ROLL210MM}

### **Arguments**

DEFLT for a default paper size.

L for a paper size L

L2 for a paper size 2L.

HAGAKIPCARD for a paper size Hagaki.

MM54BY86 for a card paper size.

MM100BY150 for paper size of 100\*150 MM.

IN4BY6 for a paper size of 4\*6.

IN8BY10 for a paper size of 8\*10.

LETTER for a letter paper size.

IN11BY17 for a paper size of 11\*17.

A0 for a A0 paper size.

A1 for a A1 paper size.

A2 for a A2 paper size.

A3 for a A3 paper size.

A4 for a A4 paper size.

A5 for a A5 paper size.

A6 for a A6 paper size.

A7 for a A7 paper size.

A8 for a A8 paper size.

A9 for a A9 paper size.

B0 for a B0 paper size.

B1 for a B1 paper size.

B2 for a B2 paper size.

B3 for a B3 paper size.

B4 for a B4 paper size.

B5 for a B5 paper size.

B6 for a B6 paper size.

B7 for a B7 paper size.

B8 for a B8 paper size.

B9 for a B9 paper size.

ROLL89MM for a 89 MM Roll paper size.

ROLL127MM for a 127 MM Roll paper size.

ROLL100MM for a 100 MM Roll paper size.

ROLL210MM for a 210 MM Roll paper size.

**Examples** PICTBRIDGE: PAPERSIZEL sets the paper size to L.

PICTBRIDGE: PAPERSIZE? might return PICTBRIDGE: PAPERSIZE DEFLT

indicating that the paper size is set to Default.

# PICTBridge:PAPERType

Sets or returns the paper type.

Group PictBridge

**Syntax** PICTBridge:PAPERType {DEFLT|PLAIN|PHOTO|FASTPHOTO}

**Arguments** DEFLT for a default print paper type.

PLAIN for a plain print paper type.

PHOTO for a photo print paper type.

FASTPHOTO for a fastphoto print paper type.

**Examples** PICTBRIDGE: PAPERTYPE? might return PICTBRIDGE: PAPERTYPE DEFLT

indicating that the default paper type.

PICTBRIDGE: PAPERTYPE PLAIN sets the paper type to Plain.

# PICTBridge:PRINTQual

Sets or returns the output print quality.

**Group** PictBridge

Syntax PICTBridge:PRINTQual {DEFLT|NRMAL|FINE|DRAFT}

**Arguments** DEFLT for the default quality print.

NRMAL for a normal quality print.

FINE for a fine quality print.

DRAFT for a draft quality print.

### **Examples**

PICTBRIDGE: PRINTQUAL? might return PICTBRIDGE: PRINTQUAL DEFLT

indicating that the default quality print.

PICTBRIDGE: PRINTQUAL FINE sets the print quality to Fine.

## \*PSC

Sets or returns the power-on status flag that controls the automatic power-on handling of the DESER, SRER, and ESER registers. When \*PSC is true, the DESER register is set to 255 and the SRER and ESER registers are set to 0 at power-on. When \*PSC is false, the current values in the DESER, SRER, and ESER registers are preserved in nonvolatile memory when power is shut off and are restored at power-on.

**Group** Status and Error

Syntax \*PSC {OFF|ON|NR1>}

\*PSC?

#### **Related Commands**

DESE, \*ESE, FACtory, \*RST, \*SRE

### **Arguments**

OFF sets the power-on status clear flag to false.

ON sets the power-on status clear flag to true.

<NR1> = 0 sets the power-on status clear flag to false. This disables the power-on clear allowing the oscilloscope to possibly assert SRQ after power-on; any other value sets the power-on status clear flag to true, enabling the power-on status clear preventing any SRQ assertion after power on.

## **Examples**

\*PSC 0 sets the power-on status clear flag to false.

\*PSC? might return 1 to indicate that the power-on status clear flag is set to true.

## \*PUD

Sets or returns a string of Protected User Data. This data is protected by the PASSWord command. You can modify it only by first entering the correct password. This password is not necessary to query the data.

**Group** Status and Error

Syntax \*PUD {<Block>|<QString>}

\*PUD?

Related Commands PASSWord

**Arguments** <Block> is a block containing up to 300 ASCII characters.

<QString> is a string containing up to 300 ASCII characters.

**Examples** \*PUD #229This oscilloscope belongs to me stores the string "This

oscilloscope belongs to me" in the user protected data area.

\*PUD? might return #221PROPERTY OF COMPANY X

# \*RCL (No Query Form)

This command restores the state of the oscilloscope from a copy of the settings stored in memory (The settings are stored using the \*SAV command).

**Group** Save and Recall

Syntax \*RCL <NR1>

Related Commands FACtory, \*LRN?, RECAll:SETUp, \*RST, \*SAV, SAVe:SETUp

**Arguments** <NR1> is a value in the range from 1 to 10, which specifies a saved setup storage

location.

**Examples** \*RCL 3 restores the oscilloscope from a copy of the settings stored in memory

location 3.

# RECAII:SETUp (No Query Form)

Restores the state of the oscilloscope from a copy of the settings stored in memory.

The settings are stored using the \*SAV command.

**Group** Save and Recall

Syntax RECAll:SETUp {FACtory|<NR1>|<file path>}

Related Commands FACtory, \*RCL, \*RST, \*SAV, SAVe:SETUp, FILESystem:CWD

**Arguments** FACtory restores the factory setup.

<NR1> is a value in the range from 1 to 10, which specifies a saved setup storage location.

<file path> specifies a location for an oscilloscope setup file. <file path> is
a quoted string that defines the file name and path. Input the file path using the
form <drive>:/<dir>/<filename>.<extension> and one or <dir>s are
optional. If you do not specify them, the oscilloscope will read the file from the
default directory (see FILESystem:CWD). <filename> stands for a filename; the
use of wildcard characters in filenames is not supported. Filename extensions are
not required, but highly recommended.

**Examples** RECALL: SETUP FACTORY recalls (and makes current) the oscilloscope setup to its factory defaults

to its factory defaults.

RECALL: SETUP 2 recalls the oscilloscope setup from setup storage location 2.

RECALL: SETUP "TEK00000. SET" recalls the setup from the file TEK00000.SET in the default directory for setups (E:/tekScope/setups).

# RECAII:WAVEform (No Query Form)

This command (no query form) recalls a stored waveform to a reference location.

**Group** Save and Recall

Syntax RECAll:WAVEform <file path>,REF<x>

Related Commands SAVe: WAVEform, FILESystem: CWD, FILESystem

**Arguments** REF<x> specifies a location in internal reference memory. Reference memory

location values range from 1 through 4.

<file path> specifies a location for an oscilloscope setup file. <file path> is
a quoted string that defines the file name and path. Input the file path using the
form <drive>:/<dir>/<filename>.<extension> and one or <dir>s are
optional. If you do not specify them, the oscilloscope will read the file from the
default directory (see FILESystem:CWD). <filename> stands for a filename; the

use of wildcard characters in filenames is not supported. Filename extensions are not required, but highly recommended.

#### **Examples**

RECALL: WAVEFORM "tek00000.isf", REF1 recalls the waveform stored in the file named tek00000.isf from the current directory for waveforms to the reference location 1.

# REF<x>? (Query Only)

Returns reference waveform data for the channel specified by  $\langle x \rangle$ , where x is the reference channel number.

**Group** Vertical

Syntax REF<x>?

# REF<x>:DATE? (Query Only)

Returns the date that reference waveform data for channel  $\langle x \rangle$  was copied into the internal reference memory, where x is the reference channel number.

**Group** Vertical

**Syntax** REF<x>:DATE?

# REF<x>:HORizontal:DELay:TIMe

Sets or returns the horizontal delay time for reference waveform  $\langle x \rangle$ , where x is the reference channel number. The delay time is expressed in seconds and is limited to  $\pm 5$  times the reference horizontal scale.

**Group** Vertical

Syntax REF<x>:HORizontal:DELay:TIMe <NR3>

REF<x>:HORizontal:DELay:TIMe?

**Arguments** <NR3> is the delay time in seconds.

**Examples** REF2:HORIZONTAL:DELAY:TIME 4.0E-6 sets the horizontal delay time for

the REF2 waveform to 4 µs.

### REF<x>:HORizontal:SCAle

Sets or returns the horizontal scale for reference waveform <x>, where x is the reference channel number.

**Group** Vertical

Syntax REF<x>:HORizontal:SCAle <NR3>

REF<x>:HORizontal:SCAle?

**Arguments** <NR3> is the horizontal scale in seconds.

**Examples** REF1:HORIZONTAL:SCALE? might return REF1:HORIZONTAL:SCALE 4.0E-4.

### REF<x>:LABel

Sets or returns the reference waveform label for the channel specified by  $\langle x \rangle$ , where x is the reference channel number.

**Group** Vertical

Syntax REF<x>:LABel <Qstring>

REF<x>:LABel?

**Arguments** <Qstring> is an alpha-numeric string of text, enclosed in quotes, that contains

the label text for the reference channel <x> waveform. The text string is limited

to 30 characters.

**Examples** REF2:LABEL? might return:REF2:LABEL "Clk Wfm 2".

## REF<x>:POSition

Sets or returns the vertical position for channel <x>, where x is the reference channel number.

**Group** Vertical

Syntax REF<x>:POSition <NR3>

REF<x>: POSition?

**Arguments** <NR3> is the vertical position in volts.

REF<x>:SCAle

Sets or returns the vertical scale for the channel specified by  $\langle x \rangle$ , where x is

the reference channel number.

**Group** Save and Recall

Syntax REF<x>:SCAle <NR3>

REF<x>:SCAle?

**Arguments** NR3 is the vertical scale in volts

REF<x>:TIMe? (Query Only)

Returns the time that reference waveform data was copied into the internal reference memory for reference channel <x>, where x is the reference channel

number.

**Group** Vertical

**Syntax** REF<x>:TIMe?

**Examples** REF2:TIME? might return "16:54:05".

## REF<x>:VERTical:POSition

Sets or returns the vertical position of the reference waveform specified by  $\langle x \rangle$ , where x is the reference channel number.

Increasing the position value of a waveform causes the waveform to move up, and decreasing the position value causes the waveform to move down. Position adjusts only the display position of a waveform. The position value determines the

vertical graticule coordinate at which signal values are displayed. For example, if the position for Reference 3 is set to 2.0, the signal represented by that reference will be displayed at 2.0 divisions above the center of the screen.

**Group** Vertical

Syntax REF<x>:VERTical:POSition <NR3>

REF<x>:VERTical:POSition?

**Related Commands** CH<x>:POSition, MATH[1]:VERTical:POSition

**Arguments** <NR3> is the desired position, in divisions from the center horizontal graticule.

The range is from -5.0 to 5.0 divisions.

**Examples** REF2:VERTICAL:POSITION 1.3E+00 positions the Reference 2 input signal

1.3 divisions above the center horizontal graticule.

REF1: VERTICAL: POSITION? might return: REF1: VERTICAL: POSITION -1.3000E+00 indicating that the current position of Reference 1 is 1.3 divisions

below the center horizontal graticule.

### REF<x>:VERTical:SCAle

Sets or returns the vertical scale for the reference waveform specified by  $\langle x \rangle$ , where x is the reference channel number.

Each waveform has a vertical scale parameter. For a signal with constant amplitude, increasing the Scale causes the waveform to be displayed smaller. Decreasing the scale causes the waveform to be displayed larger.

Scale affects all waveforms, but affects reference and math waveforms differently from channel waveforms:

- For reference and math waveforms, this setting controls the display only, graphically scaling these waveforms and having no affect on the acquisition hardware.
- For channel waveforms, this setting controls the vertical size of the acquisition window as well as the display scale. The range and resolution of scale values depends on the probe attached and any other external factors you have specified.

**Group** Vertical

Syntax REF<x>:VERTical:SCAle <NR3>

REF<x>:VERTical:SCAle?

**Related Commands** CH<x>:SCAle, MATH[1]:VERTical:SCAle

**Arguments** <NR3> is the gain in user units-per-division.

**Examples** REF2:VERTICAL:SCALE 100E-03 sets the Reference 2 scale to 100 mV per

division.

REF2:VERTICAL:SCALE? might return :REF2:VERTICAL:SCALE

1.0000e+00 indicating that the current vertical scale setting for Reference 2 is

1 V per division.

## **REM (No Query Form)**

Embeds a comment within programs as a means of internally documenting the

programs. The oscilloscope ignores these embedded comment lines.

**Group** Miscellaneous

Syntax REM <QString>

**Arguments** <QString> is a string that can contain a maximum of 80 characters.

**Examples** REM "This is a comment" is a comment string that the oscilloscope will

ignore.

# \*RST (No Query Form)

Resets the oscilloscope to the factory default settings. The \*RST command does not alter the following:

- Calibration data that affect device specifications
- The Output Queue
- The Service Request Enable Register setting
- The Power-on status clear flag setting
- Alias definitions
- Stored settings
- The \*PUD? Response
- Any of the values associated with the DATA command.
- Oscilloscope password

**Group** Status and Error

Syntax \*RST

Related Commands FACtory, RECAll:SETUp, SAVe:SETUp, \*PSC, \*RCL, \*SAV

**Arguments** None

**Examples** \*RST resets the oscilloscope settings to factory defaults.

# \*SAV (No Query Form)

Stores the state of the oscilloscope to a specified memory location. You can use the \*RCL command to restore the oscilloscope to this saved state at a later time.

**Group** Save and Recall

Syntax \*SAV <NR1>

Related Commands \*RCL, RECAll:SETUp, SAVe:SETUp

**Arguments** 

<NR1> specifies a location in which to save the state of the oscilloscope. Location values range from 1 through 10. Using an out-of-range location value causes an execution error. Any settings that have been stored previously at this location will be overwritten.

**Examples** 

\*SAV 2 saves the current oscilloscope state in memory location 2.

## SAVe: ASSIgn: TYPe

Sets or returns the assignment of the data to be saved when the front-panel Save button is pressed.

**Group** Save and Recall

Syntax SAVe:ASSIgn:TYPe {IMAGe|WAVEform|SETUp}

SAVe:ASSIgn:TYPe?

**Arguments** IMAGe assigns the Save button to save screen images.

WAVEform assigns the Save button to save waveforms.

SETUP assigns the Save button to save setups.

# **SAVe:EVENTtable:BUS<x> (No Query Form)**

Saves the data from bus<x> to a specified file and location; where x is the bus number

**Group** Save and Recall

Syntax SAVe:EVENTtable:BUS<x> <file path>

**Arguments** <file path> is a quoted string that defines the file name and path location

where the event table will be stored.

**NOTE.** <filename> stands for a filename of up to 125 characters, followed by a period (".") and the three-character extension. Waveform files should have a .csv extension for comma-separated spreadsheet format files.

# SAVe:IMAGe (No Query Form)

Saves a capture of the screen image into the specified file. Supported image formats are PNG, Windows Bitmap, and TIFF. If an extension for a supported file type is added to the file name, then the corresponding format will be used. If no supported extension is added to the file, the format to use will be determined by the value obtained from the :SAVe:IMAGe:FILEFormat? query.

**Group** Save and Recall

Syntax SAVe:IMAGe <file path>

**Related Commands** SAVe:ASSIgn:TYPe

**Arguments** <file path> is a filename, including path, where the image will be saved.

If you do not specify a directory, the oscilloscope will store the file in the current working directory. File name extensions are not required but are highly

recommended. The images will be saved in E:/.

### SAVe:IMAGe:FILEFormat

Sets or returns the file format to use for saving screen images when the file type cannot be determined from the given file name or when screen images are captured by using the front panel.

**Group** Save and Recall

Syntax SAVe:IMAGe:FILEFormat {PNG|BMP|TIFf}

SAVe: IMAGe: FILEFormat?

Related Commands SAVe:IMAGe

**Arguments** PNG saves the file in Portable Network Graphics format.

BMP saves the file in Microsoft Windows bitmap format.

TIFf saves the file in Tagged Image File Format.

### SAVe:IMAGe:LAYout

Sets or returns the layout to use for saved screen images.

**Group** Save and Recall

Syntax SAVe:IMAGe:LAYout {LANdscape|PORTRait}

SAVe: IMAGe: LAYout?

**Arguments** LANdscape specifies that screen images are saved in landscape format.

PORTRait specifies that screen images are saved in portrait format.

# SAVe:SETUp (No Query Form)

Stores the state of the oscilloscope to a specified memory location. You can later

use the \*RCL command to restore the oscilloscope to this saved state.

**Group** Save and Recall

Syntax SAVe:SETUp {<file path>|<NR1>}

Related Commands \*RCL, RECAll:SETUp, \*SAV

Arguments

<file path> is the target location for storing the setup file. <file path> is a quoted string that defines the file name and path. Input the file path using the form <driv>:<dir>/<filename>. <extension> and one or <dir>s are optional. If you do not specify them, the oscilloscope will store the file in the current working directory. <filename> stands for a filename. (Use of wildcard characters in filenames is not supported.) Filename extensions are not required but are highly recommended. For setups, use the extension ".SET".

<NR1> specifies a location for saving the current front-panel setup. The front-panel setup value ranges from 1 to 10. Using an out-of-range value causes an execution error. Any settings that have been stored previously at this location will be overwritten.

**Examples** SAVE: SETUP 5 saves the current oscilloscope setup in memory location 5.

SAVE: SETUP "TEK00000. SET" saves the current oscilloscope setup in the file

TEK00000.SET in the current working directory.

# SAVe:WAVEform (No Query Form)

This command saves a specified waveform or all displayed waveforms (excluding serial bus waveforms). Only individual analog waveforms (CH<x>, MATH and REF<x>) can be saved to reference memory locations.

You can save all displayed waveforms, excluding serial bus waveforms, to a single CSV file when the SAVE: WAVEFORM: FILEFORMAT is set to SPREADSHEET.

You can save all displayed waveforms, excluding serial bus waveforms to consecutive ISF (internal save format) files when the SAVE: WAVEFORM: FILEFORMAT is set to INTERNAL.

**NOTE.** For MSO models, reduced resolution waveform data is not available for the digital channels.

### **Group** Save and Recall

#### Related Commands

RECAll: WAVEform, SAVe: WAVEform: FILEFormat

### **Arguments**

<wfm>, <REF<x>> saves the specified waveform to the specified reference
memory location. <wfm> can be any live analog channel (where <x> is the
channel number), the MATH1 waveform, or another reference waveform (such
as REF1).

<wfm>, <QString> saves the specified waveform to the file specified in the
quoted string argument. Any live channel (such as CH1), the MATH1 waveform,
any reference waveform can be saved to a file.

ALL, <QString> saves all displayed waveforms, excluding serial bus waveforms, to a single CSV file specified by the quoted string argument when the SAVE:WAVEFORM:FILEFORMAT is set to SPREADSHEET, or saves all displayed waveforms, excluding serial bus waveforms to individual ISF (internal save format) files with a file name prefix specified by the argument with an underscore (\_) and the waveform ID (such as CH1, REF1, MATH) appended to the file name(s).

#### **Examples**

SAVE: WAVEFORM CH1, REF1 saves the CH1 waveform in reference memory location 1.

:SAVE:WAVEFORM:FILEFORMAT SPREADSHEET; :SAVE:WAVEFORM ALL, "E:/test\_folder/test1\_all.csv" saves all displayed waveforms (excluding serial bus waveforms) to E:/test\_folder/test1\_all.csv.

:SAVe:WAVEform:FILEFormat INTERNal; :SAVe:WAVEform ALL, "E:/test\_folder/test1" saves all displayed waveforms (excluding serial bus waveforms) to individual files named E:/test\_folder/test1\_<wfm>.isf (for example test1\_CH1.isf).

### SAVe:WAVEform:FILEFormat

Specifies or returns the file format for saved waveforms. Waveform header and timing information is included in the resulting file of non-internal formats. The oscilloscope saves DPO waveforms as a 500 x 200 matrix, with the first row corresponding to the most recently acquired data. The values specified by DATa:STARt and DATa:STOP determine the range of waveform data to output. In the event that DATa:STOP value is greater than the current record length, the current record length determines the last output value.

**Group** Save and Recall

Syntax SAVe:WAVEform:FILEFormat {INTERNal|SPREADSheet}

SAVe: WAVEform: FILEFormat?

Related Commands CURVe, DATa, DATa:STARt, DATa:STOP, SAVe:WAVEform,

WFMInpre:NR Pt, WFMOutpre:NR Pt?

**Arguments** INTERNal specifies that waveforms are saved in an internal format, using a .isf

filename extension. These files can be recalled as reference waveforms. When this argument is specified, the settings specified via the DATa:STARt and DATa:STOP

commands have no meaning as the entire waveform is saved.

SPREADSheet specifies that waveform data is saved in a format that contains comma delimited values. These waveform data files are named using the .csv

filename extension. Saving waveforms in CSV format enables spreadsheet

programs to import the data.

**Examples** SAVE: WAVEFORM: FILEFORMAT INTERNAL specifies that the internal file format

is the format used for saving waveforms.

SAVE: WAVEFORM: FILEFORMAT? might return: SAVE: WAVEFORM: FILEFORMAT

INTERNAL indicating that waveforms are saved using the internal format.

# SAVe:WAVEform:GATIng

Specifies whether save waveform operations should save the entire waveform (NONe) or a specified portion of the waveform.

**Group** Save and Recall

Syntax SAVe:WAVEform:GATIng {NONe|CURSors|SCREEN}

SAVe: WAVEform: GATIng?

**Arguments** CURSors turns on cursors and the gates are the waveform record points at the

cursor positions.

NONe saves the entire waveform.

SCREEN, if zoom is on, the gates are the start and end waveform record points of the zoom (upper) graticule, otherwise the gates are the start and end waveform

record points of the main graticule.

**Examples** SAVE: WAVEFORM: GATING CURSors specifies that, when the waveform gating

is set to cursors, save waveform operations should save the waveform points between the cursors. If cursors are turned off, waveform gating automatically

reverts to NONE.

### SAVe:WAVEform:SPREADSheet:RESOlution

Specifies whether to save the full (LRL) or reduced (thumb) resolution waveform

to a CSV file.

**Group** Waveform Enhanced

Syntax SAVe:WAVEform:SPREADSheet:RESOlution {FULL|REDUced}

SAVe: WAVEform: SPREADSheet: RESOlution?

**Arguments** FULL specifies that full resolution waveform is saved to a CSV file.

REDUced specifies that reduced resolution waveform is saved to a CSV file.

**Examples** SAVE: WAVEFORM: SPREADSHEET: RESOLUTION? might return

SAVE: WAVEFORM: SPREADSHEET: RESOLUTION FULL indicating that full

resolution waveform is saved to a CSV file.

SAVE: WAVEFORM: SPREADSHEET: RESOLUTIONREDUCED sets the reduced resolution waveform to be saved to a CSV file.

# **SEARCH?** (Query Only)

Returns all search-related settings.

Search Group Syntax SEARCH? **Examples** SEARCH? might return: :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:CONDITION SS; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:CONDITION SS; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:DATA:MOSI:VALUE "XXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:DATA:MOSI:VALUE "XXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:DATA:MISO:VALUE "XXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:DATA:MISO:VALUE "XXXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:DATA:SIZE1; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:DATA:SIZE 1; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:CONDITION TXSTART; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:CONDITION TXSTART; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:RX:DATA:SIZE 1; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:RX:DATA:SIZE 1; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C: RX:DATA:VALUE "XXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:RX:DATA:VALUE "XXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:TX:DATA:SIZE 1; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:TX:DATA:SIZE 1; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:TX:DATA:VALUE "XXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:TX:DATA:VALUE "XXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:CONDITION START; :SEARCH:SEARCH1:T RIGGER:A:BUS:B2:I2C:CONDITION START; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:DATA:VALUE "XXXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:DATA:VALUE "XXXXXXXXX"; :SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:DATA:SIZE 1;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:DATA:SIZE 1;

```
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:ADDRESS:MODE ADDR7;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:ADDRESS:MODE ADDR7;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:ADDRESS:TYPE USER;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:ADDRESS:TYPE USER;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:ADDRESS:VALUE
"XXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:ADDRESS:VALUE
"XXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:CONDITION SOF;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:CONDITION SOF;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:FRAMETYPE DATA;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:FRAMETYPE DATA;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:DATA:VALUE "XXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:DATA:VALUE "XXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A: BUS:B1:CAN:DATA:QUALIFIER EQUAL;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:DATA:QUALIF IER EQUAL;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:IDENTIFIER:MODE
STANDARD;
:SEARCH: SEARCH1:TRIGGER:A:BUS:B2:CAN:IDENTIFIER:MODE
STANDARD:
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:IDENTIFIER:VALUE
"XXXXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:IDENTIFIER:VALUE
"XXXXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:CONDITION SYNCFIELD;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:CONDITION SYNCFIELD;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:VALUE"XXXXXXXXX";
:SEARCH:SEARCH1:TRI GGER:A:BUS:B2:LIN:DATA:VALUE "XXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:HIVALUE
"XXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:DATA:HIVALUE
"XXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:QUALIFIER EQUAL;
:SEARCH:SEARCH1:TRIG GER:A:BUS:B2:LIN:DATA:QUALIFIER EQUAL;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:IDENTIFIER:VALUE
"XXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:IDENTIFIER:VALUE
"XXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:ERRTYPE SYNC;
```

```
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:ERRTYPE SYNC;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:PARALLEL:VALUE
"xxxxxxxxxxxxxxx";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:PARALLEL:VALUE
:SEARCH:SEARCH1:TRIGGER:A:BUS:SOURCE
B1;:SEARCH:SEARCH1:TRIGGER:A:TYPE EDGE;
LEVEL 0.0E+0; LEVEL: CH1 0.0E+0; CH20.0E+0; CH30.0E+0; CH4
0.0E+0;MATH 0.0E+0;
REF1 0.0E+0 ;REF2
0.0E+0;:SEARCH:SEARCH1:TRIGGER:A:UPPERTHRESHOLD:CH1 1.4000;
CH2 1.4000; CH3 1.4000; CH4 1.4000; MATH 492.0000E-3; REF1
492.0000E-3; REF2 492.0000E-3;
:SEARCH:SEARCH1:TRIGGER:A:LOWERTHRESHOLD:CH1 0.0E+0;CH2
0.0E+0; CH30.0E+0;
CH4 0.0E+0; MATH 0.0E+0; REF1 0.0E+0; REF2 0.0E+0;
:SEARCH:SEARCH1:TRIGGER:A:EDGE:SOURCE CH1;SLOPE RISE;
:SEARCH:SEARCH1:TRIGGER:A:LOGIC:FUNCTION AND;
THRESHOLD:CH1 0.0E+0;CH2 0.0E+0; CH3 0.0E+0;CH4 0.0E+0;MATH
0.0E+0; REF1 0.0E+0; REF20.0E+0;
:SEARCH:SEARCH1:TRIGGE R:A:LOGIC:INPUT:CH1 X;CH2 X;CH3 X;CH4
X; MATH X; REF1 X; REF2 X;
REF3 X;REF4 X;CLOCK:SOURCE NONE;EDGE RISE;
:SEARCH:SEARCH1:TRIGGER:A:LOGIC:INPUT:D0 X;D1 X;D2 X;
D3 X ;D4 X;D5 X;D6 X;D7 X;D8 X;D9 X;D10 X;D11 X;D12 X;D13
X;D14 X;D15 X;
:SEARCH: SEARCH1:TRIGGER:A:LOGIC:PATTERN:INPUT:CH1 X;CH2
X:CH3 X:
CH4 X;MATH X;REF1 X;REF2 X;RE F3 X;REF4 X;D0 X;D1 X;D2 X;D3
X;D4X;
D5 X;D6 X;D7 X ;D8 X;D9X;D10 X;D11 X;D12 X; D13 X;D14 X;D15
:SEARCH:SEARCH1:TRIGGER:A:LOGIC:PATTERN:WHEN
TRUE; WHEN: LESSLIMIT 2.0000E-9; MORELIMIT 2.0000E-9;
:SEARCH:SEARCH1:TRIGGER:A:PULSEWIDTH:POLARITY POSITIVE;WHEN
LESSTHAN; WIDTH 8.0000E-9;
:SEARCH:SEARCH1:TRIGGER:A:RUNT:POLARITY POSITIVE;WHEN
OCCURS; WIDTH 8.0000E-9;
:SEARCH:SEARCH1:TRIGGER:A:TRANSITION:POLARITY POSITIVE; WHEN
SLOWER; DELTATIME 8.0000E-9;
:SEARCH:SEARCH1:TRIGGER:A:SETHOLD:CLOCK:SOURCE CH1;EDGE
RISE; THRESHOLD 0.0E+0;
:SEARCH:SEARCH1:TRIGGER:A:SETHOLD:DATA:SOURCE NONE;THRESHOLD
9.9100E+37;
:SEARCH:SEARCH1:TRIGGER:A:SETHOLD:HOLDTIME 2.000
0E-9; SETTIME 2.0000E-9;
```

THRESHOLD:CH1 0.0E+0;CH2 0.0E+0;CH3 0.0E+0;CH4 0.0E+0; MATH

0.0E+0; REF1 0.0E+0; REF2 0.0E+0;

:SEARCH:SEARCH1:STATE 0

# SEARCH:SEARCH<x>:COPy (No Query Form)

Copies the search criteria to the trigger, or the trigger criteria to a search. <x> is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:COPy {SEARCHtotrigger|TRIGgertosearch}

**Arguments** SEARCHtotrigger copies the search criteria to the trigger

TRIGgertosearch copies the trigger criteria to the search

### SEARCH:SEARCH<x>:STATE

Sets the search state to on or off. <x> is the search number, which is always 1. The query form returns the search state.

**Group** Search

Syntax SEARCH:SEARCH<x>:STATE {<NR1>|OFF|ON}

SEARCH: SEARCH<x>: STATE?

**Arguments** OFF or  $\langle NR1 \rangle = 0$  sets the search state to off.

ON or  $\langle NR1 \rangle \neq 0$  sets the search state to on.

## SEARCH:SEARCH<x>:TOTAL? (Query Only)

Returns the total number of matches for the search. The total number of matches may be more than the number of marks placed. <x> is the search number, which is always 1.

**Group** Search

**Syntax** SEARCH: SEARCH<X>: TOTAL?

**Returns** <NR1> is the total number of matches.

## SEARCH:SEARCH<x>:TRIGger:A:BUS? (Query Only)

Queries the SEARCH:SEARCH<x>:TRIGger:A:BUS? settings.

**Group** Bus

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS?

SEARCH:SEARCH<x>:TRIGger:A:BUS??

```
Examples SEARCH: SEARCH1: TRIGGER: A: BUS? might return
```

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:CONDITION SS; :SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:CONDITION SS;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:DATA:MOSI:VALUE

"XXXXXXXX";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:DATA:MOSI:VALUE

"xxxxxxxx";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:DATA:MISO:VALUE

"XXXXXXXX";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:DATA:MISO:VALUE

"xxxxxxxx";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:SPI:DATA:SIZE 1;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:SPI:DATA:SIZE 1;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:CONDITION TXSTART;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:CONDITION TXSTART;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:RX:DATA:SIZE 1;

:SEARCH:SEARCH1 :TRIGGER:A:BUS:B2:RS232C:RX:DATA:SIZE 1;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:RX:DATA:VALUE

"XXXXXXXX";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:RX:DATA:VALUE

"XXXXXXXX";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:TX:DATA:SIZE 1;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:TX:DATA:SIZE 1;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:RS232C:TX:DATA:VALUE

"xxxxxxxx";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:RS232C:TX:DATA:VALUE "

XXXXXXXXX";

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:CONDITION START;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:CONDITION START;

:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:DATA:VALUE "XXXXXXXXX";

```
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:DATA:VALUE "XXXXXXXXX";
:SEARCH1:TRIGGER:A:BUS:B1:I2C:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C: DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:ADDRESS:MODE ADDR7;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:ADDRESS:MODE ADDR 7;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:ADDRESS:TYPE USER;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:ADDRESS:TYPE USER;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:I2C:ADDRESS:VALUE
"XXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:I2C:ADDRESS:VALUE
"XXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:CONDITION SOF;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:CONDITION SOF;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:FRAMETYPE DATA;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:FRAMETYPE DATA;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:DATA:VALUE "XXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:DATA:VALUE "XXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2: CAN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:DATA:DIRECTION NOCARE;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:DATA:QUALIFIER EQUAL;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:DATA:QUALIFIER EQUAL;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:IDENTIFIER:MODE
STANDARD:
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:IDENTIFIER:MODE
STANDARD;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:CAN:IDENTIFIER:VALUE
"XXXXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:CAN:IDENTIFIER:VALUE
"XXXXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:CONDITION SYNCFIELD;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:CONDITION SYNCFIELD;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:DATA:SIZE 1;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:VALUE "XXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:DATA:VALUE "XXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:HIVALUE
"XXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:DATA:HIVALUE "XXXXXXXX
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:QUALIFIER EQUAL;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:DATA:QUALIFIER EQUAL;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:IDENTIFIER:VALUE
"XXXXXX";
```

:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:IDENTIFIER:VALUE
"XXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:ERRTYPE SYNC;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:LIN:ERRTYPE SYNC;
:SEARCH:SEARCH1:TRIGGER:A:BUS:B1:PARALLEL:VALUE
"XXXXXXXXXXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:B2:PARALLEL:VALUE
"XXXXXXXXXXXXXXXXXXXX";
:SEARCH:SEARCH1:TRIGGER:A:BUS:SOURCE B1

# SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:CONDition

Sets or returns the search condition for a CAN trigger search. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:CONDition

{SOF|FRAMEtype|IDentifier|DATA|IDANDDATA|EOF|ACKMISS|ERROR}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:CONDition?

**Arguments** SOF specifies a search based on the start of frame.

FRAMEtype specifies a search based on the frame type.

IDentifier specifies a search based on the frame identifier.

DATA specifies a search based on the frame data.

IDANDDATA specifies a search based on the frame identifier and data.

EOF specifies a search base on the end of frame.

ACKMISS specifies a search based on the missing ACK field.

ERROR specifies a search based on a bit stuffing error.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:DIRection

Sets or returns the CAN search to be valid for Read, Write, or Either condition if the criteria is IDentifier. SEARCH<x> is the search number and B<x> is the bus number. This only applies if the search condition is IDentifier.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:DIRection

{READ|WRITE|NOCARE}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:DIRection?

**Related Commands** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:CONDition

**Arguments** READ specifies the read condition.

WRITE specifies the write condition.

NOCARE specifies either a read or write condition.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:QUALifier

Sets or returns the CAN data qualifier for a search. SEARCH<x> is the search number and B<x> is the bus number. This only applies if the trigger condition is IDANDDATA or DATA.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:QUALifier

{LESSThan|MOREThan|UNEQual|LESSEQual|MOREEQual|EQual} SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:QUALifier?

Related Commands SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue

**Arguments** LESSThan searches for bus data less than the value specified by

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue.

MOREThan searches for bus data more than the value specified by SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue.

UNEQual searches for bus data not equal to the value specified by SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue.

LESSEQual searches for bus data less than or equal to the value specified by SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue.

MOREEQual searches for bus data more than or equal to the value specified by SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue.

**EQual** searches for bus data equal to the value specified by SEARCH: SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:SIZe

Sets or returns the length of the data string in bytes to be used for a CAN search if the search condition is DATA or IDANDDATA. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:SIZe <NR1>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:SIZe?

**Arguments** <NR1> is the data string length in bytes.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue

Sets or returns the binary data string to be used for a CAN search if the search condition is ID or IDANDDATA. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue <bin>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:VALue?

**Related Commands** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:DATa:QUALifier

**Arguments** <br/> <br/> <br/> <br/> is the data in binary format.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:FRAMEtype

Sets or returns the CAN Frame Type to be used if the trigger search condition is Frame Type. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:FRAMEtype

{DATA|REMote|ERRor|OVERLoad}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN:FRAMEtype?

**Arguments** DATA specifies a data frame.

REMote specifies a remote frame.

ERROr specifies an error frame.

OVERLoad specifies an overload frame.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:MODe

Sets or returns the CAN addressing mode for a trigger search to a standard or extended format. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN{:IDentifier|:

ADDRess}:MODe {STandard|EXTended}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN{:IDentifier|:

ADDRess}:MODe?

**Arguments** STandard specifies an 11-bit identifier field.

EXTended specifies a 29-bit identifier field.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:VALue

Sets or returns the binary address string to be used for a CAN trigger search if the search condition is ID or IDANDDATA. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN{:IDentifier|:

ADDRess}:VALue <bin>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:CAN{:IDentifier|:

ADDRess \ : VALue?

**Arguments** <br/> <br/> <br/> is the address in binary format.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:MODe

Sets or returns the I2C address mode to 7 or 10-bit. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:MODe

{ADDR7|ADDR10}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:MODe?

**Arguments** ADDR7 specifies 7-bit addresses.

ADDR10 specifies 10-bit addresses.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:TYPe

Sets or returns the I2C address type. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:TYPe

{GENeralcall|STARtbyte|HSmode|EEPROM|USER}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:TYPe?

**Arguments** GENeral call specifies the GENeral call address type.

STARtbyte specifies the STARtbyte address type.

HSmode specifies the HSmode address type

EEPROM specifies the EEPROM address type.

USER specifies a user address.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:VALue

Sets or returns the binary address string to be used for an I2C trigger search if the search condition is ADDR or ADDRANDDATA. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:VALue <bin>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:ADDRess:VALue?

**Arguments** <br/> <br/> <br/> <br/> is the address in binary format.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:CONDition

Sets or returns the search condition for an I2C trigger search. SEARCH<x> is the

search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:CONDition

{STARt|STOP|REPEATStart|ACKMISS|ADDRess|DATA|ADDRANDDATA}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:CONDition?

**Arguments** STARt specifies a search based on a start condition.

STOP specifies a search based on a stop condition.

REPEATstart specifies a search based on a repeat of start condition.

ACKMISS specifies a search based on a missing acknowledgement condition.

ADDRess specifies a search based on an address.

DATA specifies a search based on a data condition.

ADDRANDDATA specifies a search based on an address and data condition.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:DIRection

Sets or returns the I2C search condition to be valid on a Read, Write, or Either condition. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:DIRection

{READ|WRITE|NOCARE}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:DIRection?

**Arguments** READ specifies a read condition.

WRITE specifies a write condition.

NOCARE specifies either a read or write condition.

#### SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:SIZe

Sets or returns the length of the data string in bytes to be used for an I2C trigger search if the search condition is DATA or ADDRANDDATA. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:SIZe <NR1>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:SIZe?

**Arguments** <NR1> is the data string length in bytes.

#### SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:VALue

Sets or returns the binary data string to be used for an I2C trigger search if the search condition is DATA or ADDRANDDATA. SEARCH<X> is the search

number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:VALue <bin>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C:DATa:VALue?

**Arguments** <br/> <br/> <br/> <br/> is the data in binary format.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:CONDition

Sets or returns the search condition for a LIN search.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:CONDition

{SYNCField|IDentifier|DATA|IDANDDATA|WAKEup|SLEEP|ERROR}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:CONDition?

**Arguments** SYNCField specifies to search on the sync field.

IDentifier specifies to search on the identifier.

DATA specifies to search on the data.

IDANDDATA specifies to search on the identifier and the data.

WAKEup specifies to search on wake up.

SLEEP specifies to search on sleep.

ERROR specifies to search on errors.

**Examples** 

SEARCH: SEARCH1: TRIGGER: A: BUS: B1: LIN: CONDITION? might return SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:CONDITION SYNCFIELD

indicating a search on the sync field.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:HIVALue

Sets or returns the binary data string to be used for LIN searches if the search condition is ID or IDANDDATA.

**Conditions** This command requires a DPO2AUTO application module.

Bus Group

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:HIVALue **Syntax** 

<QString>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:HIVALue?

<QString> is a quoted string of 1s, 0s, or Xs representing the binary data string Arguments

to be used for LIN searches if the search condition is ID or IDANDDATA.

**Examples** SEARCH: SEARCH1: TRIGGER: A: BUS: B1: LIN: DATA: HIVALUE? might return

SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:HIVALUE "XXXXXXXXX"

indicating that the high value is don't care.

#### SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:QUALifier

Sets or returns the LIN data qualifier. This only applies if the trigger condition is

IDANDDATA or DATA

Conditions This command requires a DPO2AUTO application module.

Bus Group

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:QUALifier

{LESSThan|MOREThan|EQUal|UNEQual| LESSEQual|MOREEQual|INrange|OUTrange}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:QUALifier?

**Arguments** LESSThan sets the LIN data qualifier to less than.

MOREThan sets the LIN data qualifier to greater than.

EQUal sets the LIN data qualifier to equal.

UNEQual sets the LIN data qualifier to not equal.

LESSEQual sets the LIN data qualifier to less than or equal.

MOREEQual sets the LIN data qualifier to more than or equal.

INrange sets the LIN data qualifier to in range.

OUTrange sets the LIN data qualifier to out of range.

**Examples** SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:QUALIFIER LESSThan

sets the data qualifier to lessthan.

SEARCH: SEARCH1: TRIGGER: A: BUS: B1: LIN: DATA: QUALIFIER? might return

SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:QUALIFIER EQUAL

indicating that the data qualifier is equal.

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:SIZe

Sets or returns the length of the data string in bytes to be used for LIN Search, if

search condition is DATA or IDANDDATA.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:SIZe <NR1>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:SIZe?

**Arguments** <NR1> is the length of the data in bytes.

**Examples** SEARCH: TRIGGER: A:BUS: B1:LIN: DATA: SIZE 8 sets the LIN data

size is 8 bytes.

SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:SIZE? might return SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:SIZE 1 indicating that the LIN data size is 1 byte.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:VALue

Sets or returns the binary data string used for a LIN search if the search condition is ID or IDANDDATA.

**Conditions** This command requires a DPO2AUTO application module.

Group Bus

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:VALue <QString>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:DATa:VALue?

**Arguments** <QString> is the binary data string for the search.

**Examples** SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:VALUE? might return

SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:DATA:VALUE "XXXXXXXXX"

indicating that the data value is don't care.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:ERRTYPE

Sets or returns the error type used for a LIN Search.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:ERRTYPE

{SYNC|PARity|CHecksum}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:ERRTYPE?

**Arguments** SYNC specifies a sync error type.

PARity specifies a parity error type.

CHecksum specifies a checksum error type.

SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:ERRTYPE? might return **Examples** 

SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:ERRTYPE SYNC indicating a

SYNC error type.

#### SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:IDentifier:VALue

Sets or returns the binary address string used for LIN search if search condition is ID or IDANDDATA.

**Conditions** This command requires a DPO2AUTO application module.

Bus Group

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:IDentifier:VALue

<QString>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN:IDentifier:VALue?

**Arguments** <QString> is a quoted string specifying the binary address string to be used for

LIN search if search condition is ID or IDANDDATA.

**Examples** SEARCH: SEARCH1: TRIGGER: A: BUS: B1: LIN: IDENTIFIER: VALUE? might

return SEARCH:SEARCH1:TRIGGER:A:BUS:B1:LIN:IDENTIFIER:VALUE

"XXXXXX" indicating that the binary address is undefined.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:PARallel:VALue

Sets or returns the binary data string to be used for a parallel trigger search. SEARCH<x> is the search number and B<x> is the bus number.

Search

Group

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:PARallel:VALue <QString> Syntax 1

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:PARallel:VALue?

<QString> is the binary data string. **Arguments** 

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:CONDition

Sets or returns the condition for a RS232 trigger search. SEARCH<x> is the search

number and B<x> is the bus number.

**Conditions** This command requires a DPO2COMP application module.

Group Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:CONDition

{RXSTArt|RXDATA|RXENDPacket|RXPARity|TXSTArt|

TXDATA | TXENDPacket | TXPARity }

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:CONDition?

RXSTArt specifies a search based on the RX Start Bit. Arguments

RXDATA specifies a search based on RX Data.

**RXENDPacket** specifies a search based on the RX End of Packet condition.

RXPARIty specifies a search based on the RX parity.

TXSTArt specifies a search base on the TX Start Bit.

TXDATA specifies a search based on TX Data.

TXENDPacket specifies a search based on the TX End of Packet condition.

TXPARIty specifies a search based on the TX parity.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:RX:DATa:SIZe

Sets or returns the length of the data string for a RS232 trigger search if the trigger condition is RX. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2COMP application module.

Group Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:RX:DATa:SIZe

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:RX:DATa:SIZe?

**Arguments** <NR1> is the length of the data string in Bytes.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:RX:DATa:VALue

Sets or returns the binary data string for a RS232 trigger search if the condition involves RX. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2COMP application module.

Search Group

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:RX:DATa:VALue Syntax

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:RX:DATa:VALue?

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:TX:DATa:SIZe

Sets or returns the length of the data string to be used for a RS232 trigger search if the Trigger condition is TX. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2COMP application module.

Group Search

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:TX:DATa:SIZe **Syntax** 

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:TX:DATa:SIZe?

<NR1> is the length of the data string in Bytes. **Arguments** 

#### SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:TX:DATa:VALue

Sets or returns the binary data string to be used for a RS232 trigger search if the condition involves TX. SEARCH<x> is the search number and B<x> is the

bus number.

**Conditions** This command requires a DPO2COMP application module.

Search Group

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:TX:DATa:VALue SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:RS232C:TX:DATa:VALue?

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:CONDition

Sets or returns the search condition for a SPI trigger search. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:CONDition

{SS|MISO|MOSI|MISOMOSI}

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:CONDition?

**Arguments** SS specifies a search based on the Slave Selection condition.

MISO specifies a search based on the Master-In Slave-Out condition.

MOSI specifies a search based on the Master-Out Slave-In condition.

MISOMOSI specifies a search based on the Master-In Slave-Out and Master-Out

Slave-In conditions.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa{:MISO|:IN}:VALue

Sets or returns the binary data string for an SPI trigger search if the search condition is MISO or MISOMOSI. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa{:MISO|:IN}:

VALue <bin>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa{:MISO|:IN}:

VALue?

**Arguments** <br/> <br/> <br/> <br/> is the data string in binary format.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa{:MOSI|:OUT}:VALue

Sets or returns the binary data string for an SPI trigger search if search the condition is MOSI, or MISOMOSI. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa{:MOSI|:OUT}:

VALue <bin>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa{:MOSI|:OUT}:

VALue?

**Arguments** <br/> <br/> <br/> <br/> is the data in binary format.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa:SIZe

Sets or returns the length of the data string for an SPI trigger search if the search condition is MISO, MOSI, or MISOMOSI. SEARCH<x> is the search number and B<x> is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa:SIZe <NR1>

SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI:DATa:SIZe?

**Arguments** <NR1> is the data string length in bytes.

## SEARCH:SEARCH<x>:TRIGger:A:BUS:SOUrce

Sets or returns a bus serial search. <x> is the search number.

**Conditions** This command requires a DPO2AUTO or DPO2EMBD application module.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:BUS:SOUrce {B1|B2}

SEARCH:SEARCH<x>:TRIGger:A:BUS:SOUrce?

**Arguments** B1 specifies the Bus 1 source.

B2 specifies the Bus 2 source.

#### SEARCH:SEARCH<x>:TRIGger:A:EDGE:SLOpe

Sets or returns the slope for an edge trigger search to determine where to place a

mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:EDGE:SLOpe {RISe|FALL}

SEARCH:SEARCH<x>:TRIGger:A:EDGE:SLOpe?

**Arguments** RISe specifies a rising edge.

FALL specifies a falling edge.

## SEARCH:SEARCH<x>:TRIGger:A:EDGE:SOUrce

Sets or returns the source waveform for an edge trigger search to determine where

to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:EDGE:SOUrce

{CH1|CH2|CH3|CH4|MATH}

SEARCH:SEARCH<x>:TRIGger:A:EDGE:SOUrce?

**Arguments** CH<x> specifies one input channel as the edge source, where <x> is the channel

number.

MATH specifies the math waveform as the search source.

## SEARCH:SEARCH<x>:TRIGger:A:LEVel

Sets or returns the level for an edge trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LEVel {<NR3>|TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LEVel?

**Arguments** <NR3> specifies the trigger level, in volts.

TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V

## SEARCH:SEARCH<x>:TRIGger:A:LEVel:CH<x>

Sets or returns the level for an edge trigger search to determine where to place a mark. SEARCH<x> is the search number and CH<x> is the channel number. Each channel can have an independent level.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LEVel:CH<x> {<NR3>|TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LEVel:CH<x>?

**Arguments** <NR3> specifies the trigger level in volts.

TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V

# SEARCH:SEARCH<x>:TRIGger:A:LEVel:MATH[1]

Sets or returns the math waveform level for an edge trigger search to determine where to place a mark. <x> is the search number. The value of MATH is 1 for all oscilloscopes.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LEVel:MATH {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LEVel:MATH?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V

#### SEARCH:SEARCH<x>:TRIGger:A:LEVel:REF<x>

Sets or returns the specified reference waveform level for an edge trigger search to determine where to place a mark. SEARCH<x> is the search number and REF<x> is the reference channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LEVel:REF<x> {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LEVel:REF<x>?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:FUNCtion

Sets or returns the logic operator for a logic trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:FUNCtion {AND|NANd}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:FUNCtion?

**Arguments** AND places a mark if all conditions are true.

NANd places a mark if any of the conditions is false.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CH<x>

Sets or returns the Boolean logic criteria for a logic trigger search to determine where to place a mark. SEARCH<x> is the search number and CH<x> is the channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CH<x> {HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CH<x>?

**Arguments** HIGH specifies the logic high.

LOW specifies the logic low.

X specifies a "don't care" state.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CLOCk:EDGE

Sets or returns whether the clock edge is a rising or falling for a logic search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CLOCk:EDGE

{FALL|RISe|EITher}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CLOCk:EDGE?

**Arguments** RISe specifies a rising edge.

FALL specifies a falling edge.

EITher specifies either a falling or rising edge.

#### SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CLOCk:SOUrce

Sets or returns the clock source definition for a logic trigger search. <x> is the search number. If a clock source is defined, then the logic search is determined by the state of the other inputs at the clock transition. If no clock source is defined, then the logic search is determined only by the state of the inputs.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CLOCk:SOUrce

{CH<x>|MATH|REF|D<x>|NONe}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:CLOCk:SOUrce?

**Arguments** 

CH<x> specifies a channel input as the clock source, where  $\langle x \rangle = 1, 2, 3, \text{ or } 4.$ 

MATH specifies the math waveform as the clock source.

REF specifies the reference waveform as the clock source.

D<x> specifies the digital waveform as the clock source, where <x>=0-15

NONe specifies no clock source.

# SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:D<x>

Sets or returns the waveform logic criteria for a trigger search. SEARCH<x> is the search number and D<x> is the digital channel number.

Group

Search

**Syntax** 

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:D<x> {HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:D<x>?

**Arguments** 

HIGH specifies a high logic level.

LOW specifies a low logic level.

X specifies a "don't care" condition.

# SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:MATH

Sets or returns the Boolean logic criteria for a logic trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

Group

Search

Syntax

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:MATH {HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:MATH?

**Arguments** 

HIGH specifies a high logic level.

LOW specifies a low logic level.

X specifies a "don't care" condition.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:REF<x>

Sets or returns the Boolean logic criteria for a logic trigger search to determine where to place a mark. SEARCH<x> is the search number and REF<x> is the reference channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:REF<x> {HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut:REF<x>?

**Arguments** HIGH specifies a high logic level.

LOW specifies a low logic level.

X specifies a "don't care" condition.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:CH<x>

Sets or returns the logic criteria for a logic pattern trigger search to determine where to place a mark. SEARCH<x> is the search number and CH<x> is the channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:CH<x>

{HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:CH<x>?

**Arguments** HIGH specifies a high logic level.

LOW specifies a low logic level.

X specifies a "don't care" condition.

#### SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:D<x>

Sets or returns the logic criteria for a logic pattern search to determine where to place a mark. SEARCH<x> is the search number and D<x> is the digital channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:D<x>

{HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:D<x>?

**Arguments** HIGH specifies a high logic level.

LOW specifies a low logic level.

X specifies a "don't care" condition.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:MATH

Sets or returns the Boolean logic criteria for a logic pattern trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:MATH

{HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:MATH?

**Arguments** HIGH specifies a high logic level.

LOW specifies a low logic level.

X specifies a "don't care" condition.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:REF<x>

Sets or returns the Boolean logic criteria for a pattern trigger search to determine where to place a mark. SEARCH<x> is the search number and REF<x> is the

reference channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:REF<x>

{HIGH|LOW|X}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:INPut:REF<x>?

**Arguments** HIGH specifies a high logic level.

LOW specifies a low logic level.

X specifies a "don't care" condition.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn

Sets or returns the condition for generating a logic pattern trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn

{TRUe|FALSe|LESSThan|MOREThan|Than|EQUal|UNEQual} SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn?

**Arguments** TRUe places a mark when the pattern becomes true.

FALSe places a mark when the pattern becomes false.

LESSThan places a mark if the specific pattern is true less than the time set by the SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit command.

MOREThan places a mark if the specific pattern is true more than the time set by the SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit command.

EQUal places a mark if the specific pattern is true longer than the time set by the SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit command, but less than the specified time set by the SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:MORELimit command.

UNEQual places a mark if the specific pattern is true less than the time set by the SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit command, or longer than the specified time set by the SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:MORELimit command.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit

Sets or returns the maximum time that the selected pattern may be true and still generate an A logic pattern search to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit

<NR3>

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit?

**Arguments** <NR3> specifies the maximum amount of time to hold the pattern true.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:MORELimit

Sets or returns the minimum time that the selected pattern may be true and still generate an A logic pattern search to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:MORELimit

<NR3>

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:MORELimit?

**Arguments** <NR3> specifies the minimum amount of time to hold the pattern true.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:CH<x>

Sets or returns the channel threshold level for a logic trigger search to determine where to place a mark. SEARCH<x> is the search number and CH<x> is the channel number

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:CH<x>

{<NR3>|TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:CH<x>?

**Arguments** <NR3> specifies the trigger level, in volts.

TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:MATH

Sets or returns the math waveform threshold level for a logic trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:MATH {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:MATH?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

## SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:REF<x>

Sets or returns the reference waveform threshold level for a logic trigger search to determine where to place a mark. SEARCH<x> is the search number and REF<x> is the reference channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:REF<x> {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LOGIc:THReshold:REF<x>?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

## SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:CH<x>

Sets or returns the channel waveform lower threshold to determine where to place a mark. This setting is applied to all channel searches that use a lower threshold. SEARCH<x> is the search number and CH<x> is the channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:CH<x> {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:CH<x>?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

#### SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:MATH

Sets or returns the math waveform lower threshold to determine where to place a mark. This setting is applied to all math searches that use a lower threshold. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:MATH {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:MATH?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

#### SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:REF<x>

Sets or returns the reference waveform lower threshold to determine where to place a mark. This setting is applied to all reference searches that use a lower threshold.

SEARCH<x> is the search number and REF<x> is the reference channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:REF<x> {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:REF<x>?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

## SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:POLarity

Sets or returns the polarity for a pulse trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:POLarity

{NEGative|POSitive}

SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:POLarity?

**Arguments** POSITIVE places a mark only when the polarity of the pulse is positive.

**NEGative** places a mark only when the polarity of the pulse is negative.

## SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:SOUrce

Sets or returns the source waveform for a pulse trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:SOUrce

{CH1|CH2|CH3|CH4|MATH|REF}

SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:SOUrce?

**Arguments** CH<x> specifies one input channel as the edge source, where <x> = 1, 2, 3 or 4.

MATH specifies the math waveform as the search source.

REF specifies the reference waveform as the search source.

### SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WHEn

Sets or returns the condition for generating a pulse width search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WHEn

{LESSthan|MOREthan|EQual|UNEQual}

SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WHEn?

**Arguments** LESSThan places a mark if the pulse width is less than the time set by the SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WIDth command.

MOREthan places a mark if the pulse width is more than the time set by the

SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WIDth command.

EQUal places a mark if the pulse width is equal to the time set by the SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WIDth command within a tolerance of ±5%.

UNEQual places a mark if the pulse width is unequal to the time the time set by the SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WIDth command within a tolerance of  $\pm$ 5%.

## SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WIDth

Sets or returns the pulse width setting for a pulse width trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WIDth <NR3>

SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth:WIDth?

**Arguments** <NR3> is the pulse width.

## SEARCH:SEARCH<x>:TRIGger:A:RUNT:POLarity

Sets or returns the polarity setting for a runt trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:RUNT:POLarity

{EITher|NEGative|POSitive}

SEARCH:SEARCH<x>:TRIGger:A:RUNT:POLarity?

**Arguments** POSitive places a mark when the rising edge crosses the low threshold and

the falling edge re-crosses the low threshold without either edge ever crossing

the high threshold.

NEGative places a mark when the falling edge crosses the high threshold and the rising edge re-crosses the high threshold without either edge ever crossing

the low threshold.

EITher places a mark on a runt of either polarity.

## SEARCH:SEARCH<x>:TRIGger:A:RUNT:SOUrce

Sets or returns the source setting for a runt trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:RUNT:SOUrce

{CH1|CH2|CH3|CH4|MATH|REF}

SEARCH:SEARCH<x>:TRIGger:A:RUNT:SOUrce?

**Arguments** CH1-CH4 specifies an input channel as the edge source.

MATH specifies the math waveform as the search source.

REF specifies the reference waveform as the search source.

## SEARCH:SEARCH<x>:TRIGger:A:RUNT:WHEn

Sets or returns the condition setting for a runt trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:RUNT:WHEn

{LESSthan|MOREthan|EQual|UNEQual|OCCURS} SEARCH:SEARCH<x>:TRIGger:A:RUNT:WHEn?

**Arguments** OCCURS argument specifies a trigger event if a runt of any detectable width occurs.

LESSthan argument sets the oscilloscope to trigger if the a runt pulse is detected with width less than the time set by the SEARCH:SEARCH<x>:TRIGger:A:

RUNT:WIDth command.

MOREthan argument sets the oscilloscope to trigger if the a runt pulse is detected with width more than the time set by the SEARCH:SEARCH<x>:TRIGger:A: RUNT:WIDth command.

EQUal argument sets the oscilloscope to trigger when the pattern is true for a time period equal to the time period specified in SEARCH:SEARCH<x>:TRIGger:A:RUNT:WIDth within a  $\pm$ 5% tolerance.

NOTEQual argument sets the oscilloscope to trigger when the pattern is true for a time period greater than or less than (but not equal) the time period specified in SEARCH:SEARCH<x>:TRIGger:A:RUNT:WIDth within a ±5% tolerance.

## SEARCH:SEARCH<x>:TRIGger:A:RUNT:WIDth

Sets or returns the width setting for a runt trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:RUNT:WIDth <NR3>

SEARCH:SEARCH<x>:TRIGger:A:RUNT:WIDth?

**Arguments** <NR3> specifies the minimum width, in seconds.

#### SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:EDGE

Sets or returns the clock slope setting for a setup/hold trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

Search Group

SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:EDGE {FALL|RISe} **Syntax** 

SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:EDGE?

FALL specifies polarity as the clock falling edge. **Arguments** 

RISe specifies polarity as the clock rising edge.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:SOUrce

Sets or returns the clock source setting for an setup/hold trigger search to

determine where to place a mark. <x> is the search number.

Group Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:SOUrce

{CH1|CH2|CH3|CH4|MATH|REF}

SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:SOurce?

**Related Commands** SEARCH:SEARCH<x>:TRIGger:A:SETHold:DATa:SOUrce

> CH1-CH4 specifies an input channel as the edge source. **Arguments**

> > MATH specifies the math waveform as the search source.

REF specifies the reference waveform as the search source.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:THReshold

Sets or returns the clock threshold setting for an setup/hold trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:THReshold

{<NR3>|TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:THReshold?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

<NR3> is the clock level, in volts.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:DATa:SOUrce

Sets or returns the data source setting for an setup/hold trigger search to determine where to place a mark. <x> is the search number. You cannot specify the same source for both clock and data.

**Group** Search

**Syntax** DPO Models:

SEARCH:SEARCH<x>:TRIGger:A:SETHold:DATa:SOurce

{CH1|CH2|CH3|CH4|MATH|REF|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

SEARCH:SEARCH<x>:TRIGger:A:SETHold:DATa:SOurce?

**Related Commands** SEARCH:SEARCH<x>:TRIGger:A:SETHold:CLOCk:SOUrce

**Arguments** DPO Models:

CH1-CH4 specifies an input channel as the search source.

MATH specifies the math waveform as the search source.

REF specifies the reference waveform as the search source.

D0-D15 specifies the digital waveform as the search source.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:DATa:THReshold

Sets or returns the data threshold setting for an setup/hold trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:SETHold:DATa:THReshold

{<NR3>|TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:SETHold:DATa:THReshold?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

<NR3> is the clock level, in volts.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:HOLDTime

Sets or returns the hold time setting for an setup/hold trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:SETHold:HOLDTime <NR3>

SEARCH:SEARCH<x>:TRIGger:A:SETHold:HOLDTime?

**Arguments** <NR3> specifies the hold time setting in seconds. Positive values for hold time

occur after the clock edge. Negative values occur before the clock edge.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:SETTime

Sets or returns the setup time setting for an setup/hold trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:SETHold:SETTime <NR3>

SEARCH:SEARCH<x>:TRIGger:A:SETHold:SETTime?

**Arguments** <NR3> specifies the setup time for setup and hold violation triggering.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold:CH<x>

Sets or returns the trigger search setup and hold lower threshold to determine where to place a mark. Search<x> is the search number, which is always 1.

CH<x> is the channel number.

**Conditions** MSO oscilloscopes only.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold:CH<x> <NR3>

SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold:CH<x>?

**Arguments** <NR3> is the lower threshold in volts.

## SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold{:MATH|:MATH1}

Sets or returns the trigger search setup and hold lower threshold to determine where to place a mark. Where  $\langle x \rangle$  is the search number, which is always 1.

**Conditions** MSO oscilloscopes only.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold{:MATH|:MATH1}

<NR3>

SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold{:MATH|:MATH1}?

**Arguments** <NR3> is the lower threshold in volts.

# SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold:REF<x>

Sets or returns the trigger search setup and hold lower threshold to determine where to place a mark. Search<x> is the search number, which is always 1. REF<x> is the reference waveform number.

**Conditions** MSO oscilloscopes only.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold:REF<x> <NR3>

SEARCH:SEARCH<x>:TRIGger:A:SETHold:THReshold:REF<x>?

**Arguments** <NR3> is the lower threshold in volts.

# SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:DELTatime

Sets or returns the transition time setting for an transition trigger search to determine where to place a mark.<x> is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:DELTatime

<NR3>

SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:DELTatime?

**Arguments** <NR3> specifies the transition time, in seconds.

### SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:POLarity

Sets or returns the polarity setting for an transition trigger search to determine where to place a mark. <x> is the search number.

**Group** Search

**Syntax** SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:POLarity

{EITher|NEGative|POSitive}

SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:POLarity?

**Arguments** POSitive specifies that a pulse edge must traverse from the lower (most

negative) to higher (most positive) level for transition triggering to occur.

NEGative specifies that a pulse edge must traverse from the upper (most positive)

to lower (most negative) level for transition triggering to occur.

EITher specifies either positive or negative polarity.

# SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:SOUrce

Sets or returns the source setting for an transition trigger search to determine where to place a mark. <x> is the search number.

Group Search

Syntax SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:SOurce

{CH1|CH2|CH3|CH4|MATH}

SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:SOurce?

**Arguments** CH1-CH4 specifies one input channel as the edge source.

MATH specifies the math waveform as the search source.

# SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:WHEn

Sets or returns the condition setting for an transition trigger search to determine where to place a mark.  $\langle x \rangle$  is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:WHEn

{SLOWer|FASTer|EQual|UNEQual}

SEARCH:SEARCH<x>:TRIGger:A{:TRANsition|:RISEFall}:WHEn?

**Arguments** FASTer sets the trigger to occur when the transitioning signal is faster than the set

volts/second rate.

SLOWer sets the trigger to occur when the transitioning signal is slower than

the set volts/second rate.

EQual sets the trigger to occur when the transitioning signal is equal to the set

volts/second rate within a  $\pm 5\%$  tolerance.

UNEQual sets the trigger to occur when the transitioning signal is not equal to

the set volts/second rate  $\pm 5\%$ .

# SEARCH:SEARCH<x>:TRIGger:A:TYPe

Sets or returns the trigger type setting for a search to determine where to place a mark. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:TYPe

{EDGe|SETHold|PULSEWidth|RUNt|TRAnsition|LOGIc|BUS (with the

appropriate application module installed)}

SEARCH:SEARCH<x>:TRIGger:A:TYPe?

#### **Arguments**

RUNt triggers when a pulse crosses the first preset voltage threshold but does not cross the second preset threshold before recrossing the first. The thresholds are set with the SEARCH:SEARCH<x>:TRIGger:A:LOWerthreshold:CH<x> and SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:CH<x> commands.

PULSEWIdth triggers when a pulse is found that has the specified polarity and is either inside or outside the limits as specified by SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit and SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern:WHEn:MORELimit. The polarity is selected using the SEARCH:SEARCH<x>:TRIGger:A:RUNT: POLarity command.

TRAnsition triggers when a pulse crosses both thresholds in the same direction as the specified polarity and the transition time between the two threshold crossings is greater or less than the specified time delta.

# SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:CH<x>

Sets or returns the channel waveform upper threshold to determine where to place a mark. This setting is applied to all channel searches that uses an upper threshold.SEARCH<x> is the search number and CH<x> is the channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:CH<x> {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:CH<x>?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

# SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:MATH

Sets or returns the math waveform upper threshold to determine where to place a mark. This setting is applied to all math waveform searches that uses an upper threshold. <x> is the search number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:MATH {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:MATH?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

# SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:REF<x>

Sets or returns the reference waveform upper threshold to determine where to place a mark. This setting is applied to all reference waveform searches that uses an upper threshold. SEARCH<x> is the search number and REF<x> is the reference channel number.

**Group** Search

Syntax SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:REF<x> {TTL|ECL}

SEARCH:SEARCH<x>:TRIGger:A:UPPerthreshold:REF<x>?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

**SELect** 

Sets or returns the selected waveform display (controlled by the front-panel)

on or off.

**Group** Vertical

**Syntax** SELect {ON|OFF}

**Arguments** ON turns the selected waveform display on.

OFF turns the selected waveform display off.

#### **Examples** SELECT? might return the following

:SELECT:BUS1 0;BUS2 0;CH1 1;CH2 0;CH3 0;CH4 0;MATH 0;REF1 0;REF2 0;D0 0;D1 0;D2 0;D3 0;D4 0;D5 0;D6 0;D7 0;D8 0;D9 0;D10 0;D11 0;D12 0;D13 0;D14 0;D15 0,CONTROL CH1

### SELect:BUS<x>

This command turns on and off the display of the waveform for  $\langle x \rangle$ , where x is the bus number. The query returns whether the channel is on or off but does not indicate whether it is the selected waveform.

**Group** Vertical

Syntax SELect:BUS<x> {<NR1>|OFF|ON}

SELect:BUS<x>?

### SELect:CH<x>

Turns the display of the channel  $\langle x \rangle$  waveform on or off, where  $\langle x \rangle$  is the channel number. This command also resets the acquisition. The query returns whether the channel is on or off but does not indicate whether it is the selected waveform.

**Group** Vertical

Syntax SELect:CH<x> {ON|OFF|<NR1>}

SELect:CH<x>?

**Arguments** ON turns on the display of the specified waveform. This waveform also becomes

the selected waveform.

OFF turns off the display of the specified waveform.

<NR1> = 0 turns off the display of the specified waveform; any other value turns

on the display of the specified waveform.

**Examples** SELECT: CH2 ON turns the channel 2 waveform display on, and selects channel 2.

SELECT: CH1? might return: SELECT: CH1 1 indicating that channel 1 is being

displayed.

### **SELect:CONTROL**

Sets or returns the waveform that is the recipient of future channel-related commands, for example, the cursor commands. The command form also performs the equivalent of a SELect:CH<x> ON command, as well as the Math, Reference, and Bus variations of that command.

**Group** Vertical

Syntax SELect:CONTROl {CH<x>|MATH|BUS<x>}

SELect:CONTROl?

**Arguments** CH<x> specifies a channel waveform as the waveform affected by the front-panel

controls. <x> is the channel number.

MATH specifies the math waveform as the waveform that is affected by the

front-panel controls.

BUS<x> specifies a bus waveform as the waveform affected by the front-panel

controls. <x> specifies the bus number.

**Returns** NONE if all the channels are turned off. NONE is ignored on input.

**Examples** SELECT: CONTROL CH2 resets acquisition displays on channel 2, and causes the

selected waveform to be the implied object of waveform commands.

SELECT: CONTROL? might return: SELECT: CONTROL MATH indicating that math

is the implied object of waveform commands.

SELect:D<x>

Turns on the display of the digital channel <x> and resets the acquisition. <x> is the channel number. The query returns whether the channel is on or off but does

not indicate whether it is the selected waveform.

**Group** Vertical

Syntax SELect:D<x> {<NR1>|OFF|ON}

SELect:D<x>?

**Arguments** ON turns on the display of the specified waveform. This waveform also becomes

the selected waveform.

OFF turns off the display of the specified waveform.

<NR1> = 0 turns off the display of the specified waveform; any other value turns on the display of the specified waveform.

#### **Examples**

SELECT: D2 ON turns the digital channel 2 waveform display on, and selects digital channel 2.

SELECT:D2? might return:SELECT:D2 1 indicating that digital channel 2 is being displayed.

# SELect:MATH[1]

Turns on and off the display of the math waveform. The query returns whether the math waveform is on or off but does not indicate whether it is the selected waveform

### **Group** Vertical

Syntax SELect:MATH[1] {ON|OFF|<NR1>}

SELect:MATH[1]?

#### **Arguments**

ON turns on the display of the specified waveform. This waveform also becomes the selected waveform.

OFF turns off the display of the specified waveform.

<NR1> = 0 turns off the display of the specified waveform; any other value turns on the display of the specified waveform.

#### **Examples**

SELECT: MATH ON turns the math waveform display on, and selects it.

SELECT: MATH? might return: SELECT: MATH 1 indicating that the math waveform is being displayed.

### SELect:REF<x>

Turns on and off the display of the reference waveform <x>. The <x> variable represents the reference channel number. The query returns whether the channel is on or off.

#### **Group** Vertical

Syntax SELect:REF<x> {ON|OFF|<NR1>}

SELect:REF<x>?

**Arguments** ON turns on the display of the specified waveform. This waveform also becomes

the selected waveform.

OFF turns off the display of the specified waveform.

<NR1> = 0 turns off the display of the specified waveform; any other value turns

on the display of the specified waveform.

**Examples** SELECT: REF2 ON turns the channel 2 waveform display on, and selects reference

waveform 2.

SELECT: REF2? might return: SELECT: REF2 1 indicating that reference

waveform 2 is being displayed.

# SET? (Query Only)

Returns the commands that list the oscilloscope settings except for configuration information for the calibration values, the WFMInpre? query, and the WFMOutpre? query. This query allows you to record or "learn" the current oscilloscope settings. You can use these commands to return the oscilloscope to the state it was in when you made the SET? query. The SET? query always returns command headers, regardless of the setting of the HEADer command. This is because the returned commands are intended to be sent back to the oscilloscope as a command string. The VERBose command can still be used to specify whether the returned headers should be abbreviated or full-length.

This command is identical to the \*LRN? command.

**Group** Miscellaneous

Syntax SET?

Related Commands HEADer, \*LRN?, VERBose

**Examples** SET? returns a long response, part of which could be as follows: :SET

:ACQUIRE:STOPAFTER RUNSTOP;STATE 1;MODE SAMPLE;NUMENV INFINITE;NUMAVG 16;SAMPLINGMODE RT;:HEADER 1;:LOCK NONE;:LANGUAGE ENGLISH;:VERBOSE 1;:ALIAS:STATE 0;:DISPLAY:COLOR:PALETTE NORMAL;:DISPLAY:PERSISTENCE 0.0000;CLOCK 1;GRATICULE FULL;INTENSITY:WAVEFORM

30;GRATICULE 75;BACKLIGHT HIGH;:HARDCOPY:INKSAVER

OFF; LAYOUT LANDSCAPE; PREVIEW 0; :SAVE: IMAGE: FILEFORMAT BMP;:SAVE:WAVEFORM:FILEFORMAT INTERNAL;:SAVE:ASSIGN:TYPE SETUP;:TRIGGER:A:MODE AUTO;TYPE EDGE;LEVEL 20.0000E-3; LEVEL: CH1 20.0000E-3; CH2 0.0000; CH3 0.0000; CH4 0.0000; TRIGGER: A: UPPERTHRESHOLD: CH1 1.4000; CH2 800.0000E-3; CH3 800.0000E-3; CH4 800.0000E-3;: TRIGGER: A: LOWERTHRESHOLD: CH1 20.0000E-3; CH2 0.0000; CH3 0.0000; CH4 0.0000; TRIGGER: A: HOLDOFF: TIME 20.0000E-9;:TRIGGER:A:EDGE:SOURCE CH1;COUPLING DC;SLOPE RISE;:TRIGGER:A:LOGIC:CLASS SETHOLD;FUNCTION AND; THRESHOLD: CH1 20.0000E-3; CH2 0.0000; CH3 0.0000; CH4 0.0000; :TRIGGER: A: LOGIC: INPUT: CH1 X;CH2 X;CH3 X;CH4 X;CLOCK:SOURCE NONE;EDGE RISE;:TRIGGER:A:LOGIC:PATTERN:INPUT:CH1 X;CH2 X;CH3 X;CH4 X;:TRIGGER:A :LOGIC:PATTERN:WHEN TRUE; WHEN: LESSLIMIT 4.0000E-9; LIMIT 4.0000E-9; TRIGGER: A :SETHOLD:CLOCK:SOURCE CH1;EDGE RISE;THRESHOLD 20.0000E-3;:TRIGGER:A:SETHOLD:DATA:SOURCE CH2;

# SETUP<x>:DATE? (Query Only)

Returns the date when the oscilloscope setup was saved for the specified channel  $\langle x \rangle$ .

**Group** Save and Recall

**Syntax** SETUP<x>:DATE?

**Examples** SETUP4:DATE? might return SETUP4:DATE: 04-18-06 which is the setup

date for channel 4.

#### SETUP<x>:LABEL

Sets or returns the setup label for the specified channel  $\langle x \rangle$ .

**Group** Save and Recall

Syntax SETUP<x>:LABEL <Qstring>

**Arguments** <Qstring> is an alpha-numeric string of characters, enclosed in quotes, that

defines the label text for SETUP<x>. The length of the string is limited to 30

characters.

**Examples** SETUP: LABEL? might return SETUP1: LABEL: TEST 2 which is the label setup

for channel 1.

# SETUP<x>:TIME? (Query Only)

Returns the time when the oscilloscope setup was saved for the specified channel

<x>.

**Group** Save and Recall

**Syntax** SETUP<x>:TIME?

**Examples** SETUP2:TIME? might return "SETUP2:TIME: 15:24:07 which is the setup

time for channel 2.

\*SRE

The \*SRE (Service Request Enable) command sets or returns the bits in the

Service Request Enable Register. For information, refer to Registers.

**Group** Status and Error

Syntax \*SRE <NR1> \*SRE?

Related Commands \*CLS, DESE, \*ESE, \*ESR?, EVENT?, EVMsg?, FACtory, \*STB?

**Arguments** <NR1> is a value in the range from 0 through 255. The binary bits of the SRER

are set according to this value. Using an out-of-range value causes an execution error. The power-on default for SRER is 0 if \*PSC is 1. If \*PSC is 0, the SRER maintains the praying power avallable through the current power evalue.

**Examples** \*SRE 48 sets the bits in the SRER to binary 00110000.

\*SRE? might return 32, showing that the bits in the SRER have the binary value of 00100000.

# \*STB? (Query Only)

\*STB? (Read Status Byte) returns the contents of the Status Byte Register (SBR) using the Master Summary Status (MSS) bit. For information, refer to Registers.

**Group** Status and Error

Syntax \*STB?

Related Commands \*CLS, DESE, \*ESE, \*ESR?, EVENT?, EVMsg?, FACtory, \*SRE

Returns <NR1>

**Examples** \*STB? might return 96, showing that the SBR contains the binary value 01100000.

# **TEKSecure (No Query Form)**

This command initializes both waveform and setup memories, overwriting any previously stored data. These are the WFMInpre?, WFMOutpre?, DATa, DATa:RESOlution and DATa:COMPosition command values after the TEKSecure operation.

:WFMOUTPRE:BYT\_NR 1 :WFMOUTPRE:BIT\_NR 8 :WFMOUTPRE:ENCDG BIN
:WFMOUTPRE:BN\_FMT RI :WFMOUTPRE:BYT\_OR MSB :WFMOUTPRE:WFID
"Ch1, DC coupling, 100.0mV/div, 4.000us/div, 10000 points,
Sample mode" :WFMOUTPRE:NR\_PT 10000 :WFMOUTPRE:PT\_FMT
Y :WFMOUTPRE:XUNIT "s" :WFMOUTPRE:XINCR 4.0000E-9
:WFMOUTPRE:XZERO -20.0000E-6 :WFMOUTPRE:PT\_OFF 0
:WFMOUTPRE:YUNIT "V" :WFMOUTPRE:YMULT 4.0000E-3
:WFMOUTPRE:YOFF 0.0000 :WFMOUTPRE:YZERO 0.0000
:WFMINPRE:BYT\_NR 1 :WFMINPRE:BIT\_NR 8 :WFMINPRE:ENCDG BIN
:WFMINPRE:BN\_FMT RI :WFMINPRE:BYT\_OR MSB :WFMINPRE:NR\_PT
10000 :WFMINPRE:PT\_FMT Y :WFMINPRE:XUNIT "s" :WFMINPRE:XINCR
4.0000E-9 :WFMINPRE:XZERO 0.0000 :WFMINPRE:PT\_OFF 0
:WFMINPRE:YUNIT "V" :WFMINPRE:YMULT 4.0000E-3 :WFMINPRE:YOFF
0.0000 :WFMINPRE:YZERO 0.0000 DATA:DESTINATION REF1
DATA:ENCDG RIBINARY DATA:SOURCE CH1 DATA:START 1 DATA:STOP

10000 DATA:WIDTH 1 :DATA:RESOLUTION FULL :DATA:COMPOSITION COMPOSITE\_YT

**NOTE.** The TEKSecure command can take up to five minutes to complete. The oscilloscope is inoperable during this period.

**Group** Miscellaneous

Syntax TEKSecure

### **Examples** TEKSECURE initializes both waveform and setup memories.

This is a program example of how to generate an SRQ when TEKSECURE completes:

```
# Bit 0 of the DESE (Device Event Status Enable Register)
# enables OPC to be reported to the SESR (Standard Event
# Status Register)
DESE 255
# Bit 0 of the ESER (Event Status Enable Register)
# enables OPC to be summarized in the ESB (Event Status #
Bit) of the SBR (Status Byte Register)
*ESE 255
# Bit 5 of the SRE (Service Request Enable Register)
enables
# the generation of SRQ when the ESB bit of the SBR
becomes # TRUE
*SRE 32
TEKSECURE;*OPC
```

When the TEKSECURE operation has completed, the OPC bit of the SESR will be TRUE and SRQ will have been generated.

#### TIME

Sets or returns the time that the oscilloscope displays.

**Group** Miscellaneous

Syntax TIME <QString>
 TIME?

Related Commands DATE

**Arguments** <QString> is a time in the form "hh:mm:ss" where hh refers to a two-digit hour

number, mm refers to a two-digit minute number from 00 to 59, and ss refers to a

two-digit second number from 00 to 59.

**Examples** TIME "14:00:00" sets the time to exactly 2:00 p.m.

TIME? might return: TIME "14:05:17" indicating that the current time is set

to 2:05 p.m. and 17 seconds.

# **TOTaluptime? (Query Only)**

This command returns the total number of hours that the oscilloscope has been powered on since the nonvolatile memory was last programmed (usually since the initial manufacturing process).

**Group** Miscellaneous

Syntax TOTaluptime?

# \*TRG (No Query Form)

Performs a group execute trigger on commands defined by \*DDT.

**Group** Miscellaneous

Syntax \*TRG

Related Commands \*DDT

**Examples** \*TRG immediately executes all commands that have been defined by \*DDT.

# TRIGger (No Query Form)

Forces a trigger event to occur.

**Group** Trigger

Syntax TRIGger FORCe

TRIGger?

**Arguments** FORCe creates a trigger event. If TRIGger:STATE is set to READy, the acquisition

will complete. Otherwise, this command will be ignored.

**Examples** TRIGGER FORCE forces a trigger event to occur.

# TRIGger:A

Sets the A trigger level automatically to 50% of the range of the minimum and maximum values of the trigger input signal. The query returns current A trigger parameters. The trigger level is the voltage threshold through which the trigger source signal must pass to generate a trigger event. This command works for the following cases: Edge Trigger (when source is Not Line), Logic Trigger (when Clock Source is not Off or Logic Pattern is Don't Care), and Pulse Width Trigger.

**Group** Trigger

Syntax TRIGger: A SETLevel

TRIGger:A?

**Related Commands** TRIGger:A:EDGE?, TRIGger:A:LOGIc?, TRIGger:A:PULse?

**Arguments** SETLevel sets the A trigger level to 50% of the range of the minimum and

maximum values of the trigger input signal.

**Examples** TRIGGER: A SETLEVEL sets the A trigger level to 50% of the range of the

minimum and maximum values of the trigger input signal.

TRIGGER:A? might return a long response with A trigger parameters, some of which could be as follows: :TRIGGER:A:MODE AUTO;TYPE EDGE;LEVEL 20.0000E-3;LEVEL:CH1 20.0000E-3;CH2 0.0000; CH3 0.0000;CH4 0.0000;:TRIGGER:A:UPPERTHRESHOLD:CH1

1.4000; CH2 800.0000E-3; CH3 8 00.0000E-3; CH4

800.0000E-3;:TRIGGER:A:LOWERTHRESHOLD:CH1 20.0000E-3;CH2

0.0000; CH3 0.0000; CH4 0.0000; :TRIGGER: A: HOLDOFF: TIME

20.0000E-9;:TRIGGER:A:EDGE:SOURCE CH1;COUPLING

DC;SLOPE RISE;:TRIGGER:A:LOGIC:CLASS SETHOLD;FUNCTION

AND; THRESHOLD: CH1 20.0000E-3; CH2 0.0000; CH3 0.0000; CH4 0.0000; TRIGGER: A: LOGIC: INPUT: CH1 X; CH2 X; CH3 X; CH4 X; CLOCK: SOURCE NONE; EDGE

RISE;:TRIGGER:A:LOGIC:PATTERN:INPUT:CH1 X; CH2 X;CH3 X;CH4 X;:TRIGGER:A:LOGIC:PATTERN:WHEN TRUE; WHEN: LESSLIMIT 4.0000E-9; MO RELIMIT 4.0000E-9;:TRIGGER:A:SETHOLD:CLOCK:SOURCE CH1;EDGE RISE; THRESHOLD 20.000 0E-3; :TRIGGER: A: SETHOLD: DATA: SOURCE CH2; THRESHOLD 0.0000; :TRIGGER: A: SETHOLD: HOLD TIME 4.0000E-9;SETTIME 4.0000E-9;:TRIGGER:A:PULSE:CLASS TRANSITION;:TRIGGER:A:PULSEWIDTH:SOURCE CH1; POLARITY POSITIVE; WHEN LESSTHAN; WIDTH 4.0000E-9;:TRIGGER:A:RUNT:SOURCE CH1;POLARITY POSITIVE;WHEN OCCURS; WIDTH 4.0000E-9; :TRIGGER: A: TRANSITION: SOURCE CH1; POLARITY POSITIVE; WHEN SLOWER; DELTATIME 4.0000E-9;:TRIGGER:A:VIDEO :POLARITY POSITIVE;SOURCE CH1; STANDARD NTSC; SYNC ALLLINES; HOLDOFF: FIELD 0.0000;: TRIGGER: A: VIDEO: CUSTOM: FORMAT PROGRESSIVE; SCAN RATE15K;:TRIGGER:A:VIDEO:LINE 1;H DTV:FORMAT HD1080I60;:TRIGGER:A:BUS:SOURCE B1;B1:I2C:CONDITION START; DATA: VALUE "XXXXXXXXX"; SIZE 1; START 0.0000; DIRECTION NOCARE;:TRIGGER:A:BUS:B1:I2C:ADDRESS:MODE ADDR7; TYPE USER; VALUE "XXXXXXX";:TRIGGER:A:BUS:B1:SPI:CONDITION MOSI;DATA:OUT :VALUE "XXXXXXXX";:TRIGGER:A:BUS:B1:SPI:DATA:IN:VALUE "XXXXXXXX";:TRIGGER:A:BUS: B1:SPI:DATA:SIZE 1;START 0.0000;:

### TRIGger: A: BUS

Sets or returns the trigger type: I2C, CAN, SPI, and RS232. There are up to two serial buses, B1, B2, depending on your instrument model. Each can be independently set to one of the serial trigger types. The serial parameters related to the trigger are broken into two sections: Trigger:A:SERIAL xxx, consisting of parameters the user will change frequently, and BUS:B1:xxx, consisting of parameters the user will specify once (bus definition).

**Conditions** Requires a DPO2AUTO, DPO2EMBD, or DPO2COMP application module.

**Group** Trigger

Syntax TRIGger:A:BUS {I2C|SPI|CAN|RS232}

TRIGger:A:BUS?

**Arguments** 12C specifies the Inter-IC bus.

SPI specifies the Serial Peripheral Interface bus.

CAN specifies the Controller Area Network bus.

# TRIGger:A:BUS:B<x>:CAN:CONDition

Sets or returns the CAN trigger condition for bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** Requires a DPO2AUTO application module.

**Group** Trigger

**Syntax** TRIGger:A:BUS:B<x>:CAN:CONDition

{SOF|FRAMEtype|IDentifier|DATA|IDANDDATA|EOF|ACKMISS}

TRIGger:A:BUS:B<x>:CAN:CONDition?

**Arguments** SOF enables triggering on the start of frame.

FRAMEtype enables triggering on the type of frame.

IDentifier enables triggering on a matching identifier.

DATA enables triggering on matching data.

IDANDDATA enables triggering on a matching identifier and matching data.

EOF enables triggering on the end of frame.

ACKMISS enables triggering on a missing acknowledge.

**Examples** TRIGGER:A:BUS:B1:CAN:CONDITION? might return:TRIGGER:A:BUS:B1:

CAN: CONDITION EOF indicating an end of file condition.

TRIGGER: A: BUS: B1: CAN: CONDITION DATA enables triggering on matching

CAN data.

# TRIGger:A:BUS:B<x>:CAN:DATa:DIRection

Sets or returns the CAN trigger data direction to be valid on a Read, Write, or Either condition for bus <x>, where x is the bus number. This applies only,

if the trigger condition is ID.

**Conditions** Requires a DPO2AUTO application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:CAN:DATa:DIRection {READ|WRITE|NOCARE}

TRIGger:A:BUS:B<x>:CAN:DATa:DIRection?

**Arguments** READ sets the CAN data direction to READ.

WRITE sets the CAN data direction to WRITE.

NOCARE sets the CAN data direction to either.

**Examples** TRIGGER: A: BUS: B1: CAN: DATA: DIRECTION WRITE sets the CAN data

direction to Write.

### TRIGger:A:BUS:B<x>:CAN:DATa:QUALifier

Sets or returns the CAN data qualifier for bus <x>, where x is the bus number. This applies only, if the trigger condition is IDANDDATA or DATA.

**Conditions** Requires a DPO2AUTO application module.

**Group** Trigger

**Syntax** TRIGger:A:BUS:B<x>:CAN:DATa:QUALifier

{LESSThan|MOREThan|EQUal|UNEQual|LESSEQual|MOREEQual}

TRIGger:A:BUS:B<x>:CAN:DATa:QUALifier?

**Arguments** LESSThan sets the oscilloscope to trigger when the data is less than the qualifier

value.

MOREThan sets the oscilloscope to trigger when the data is more than the qualifier

value.

EQUal sets the oscilloscope to trigger when the data is equal to the qualifier value.

UNEQual sets the oscilloscope to trigger when the data is not equal to the qualifier

value.

LESSEQual sets the oscilloscope to trigger when the data is less than or equal

to the qualifier value.

MOREEQual sets the oscilloscope to trigger when the data is more than or equal

to the qualifier value.

**Examples** TRIGGER:A:BUS:B1:CAN:DATA:QUALIFIER LESSTHAN sets the oscilloscope

to trigger when the data is less than the qualifier value.

TRIGGER:A:BUS:B1:CAN:DATA:QUALIFIER? might return :TRIGGER:A:BUS:B1:CAN:DATA:QUALIFIER THAN, indicating that the oscilloscope is set to trigger when the data is than the qualifier value.

# TRIGger:A:BUS:B<x>:CAN:DATa:SIZe

Sets or returns the length of the data string in bytes for a CAN trigger if the condition is DATA or IDANDDATA. Applies to bus <x>, where x is the bus number

**Conditions** This command requires a DPO2AUTO application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:CAN:DATa:SIZe <NR1>

TRIGger:A:BUS:B<x>:CAN:DATa:SIZe?

**Arguments** <NR1> is the length of the data string in bytes.

# TRIGger:A:BUS:B<x>:CAN:DATa:VALue

Sets or returns the binary data string to be used for a CAN trigger if the trigger condition is ID or IDANDDATA. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:CAN:DATa:VALue <QString>

TRIGger:A:BUS:B<x>:CAN:DATa:VALue?

**Arguments** <QString> is the CAN data value in binary format. The only allowed characters

in the QString are 0, 1, and X.

**Examples** TRIGGER:A:BUS:B1:CAN:DATA:VALUE 1011 sets the CAN data value to 1011.

# TRIGger:A:BUS:B<x>:CAN:FRAMEtype

Sets or returns the frame type for a CAN FRAMEType trigger. Applies to bus <x>, where x is the bus number.

**Conditions** 

This command requires a DPO2AUTO application module. This command is only valid when the TRIGger:A:BUS:B<x>:CAN:CONDition is FRAMETYPE.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:CAN:FRAMEtype

{DATA|REMote|ERROr|OVERLoad}
TRIGger:A:BUS:B<x>:CAN:FRAMEtype?

TREASE TREE STEAM TO THE COPPE

**Arguments** DATA specifies a data frame type.

REMote specifies a remote frame type.

ERRor specifies an error frame type.

OVERLold specifies an overload frame type.

Examples

TRIGGER: A: BUS: B1: CAN: FRAMETYPE DATA sets the CAN trigger frame type to DATA

# TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:MODe

Sets or returns the CAN addressing mode for bus  $\langle x \rangle$ , where x is the bus number. Use this command to do the following:

Trigger on ID

Trigger in IDANDDATA

**Conditions** This command requires a DPO2AUTO application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:MODe

{STandard|EXTended}

TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:MODe?

**Arguments** STandard specifies the standard addressing mode.

EXTended specifies the extended addressing mode.

# TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:VALue

Sets or returns the binary address string used for a CAN trigger if the trigger condition is ID or IDANDDATA. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:VALue <QString>

TRIGger:A:BUS:B<x>:CAN{:IDentifier|:ADDRess}:VALue?

**Arguments** <QString> is up to 29 bits specifying the binary CAN identifier value. The only

allowed characters in the QString are 0, 1, and X.

**Examples** TRIGGER:A:BUS:B1:CAN:IDENTIFIER:VALUE 1011 sets the CAN trigger

identifier value to 1011.

# TRIGger:A:BUS:B<x>:I2C:ADDRess:MODe

Sets or returns the I<sup>2</sup>C address mode to 7 or 10-bit. Applies to bus  $\langle x \rangle$ , where x is the bus grapher

is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:I2C:ADDRess:MODe {ADDR7|ADDR10}

TRIGger:A:BUS:B<x>:I2C:ADDRess:MODe?

**Arguments** ADDR7 specifies the 7-bit I<sup>2</sup>C address mode.

ADDR10 specifies the 10-bit I<sup>2</sup>C address mode.

**Examples** TRIGGER:A:BUS:B1:I2C:ADDRESS:MODE ADDR10 sets the I2C address mode

to 10-bit.

## TRIGger:A:BUS:B<x>:I2C:ADDRess:TYPe

Sets or returns the I<sup>2</sup>C address type. The only supported address type is USER.

Applies to bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:I2C:ADDRess:TYPe

{GENeralcall|STARtbyte|HSmode|EEPROM|USER}

TRIGger:A:BUS:B<x>:I2C:ADDRess:TYPe?

**Arguments** GENeral call specifies a general call address.

STARtbyte specifies a start byte address.

HSmode specifies a high-speed mode address.

**EEPROM** specifies an EEPROM address.

USER specifies a user address.

## TRIGger:A:BUS:B<x>:I2C:ADDRess:VALue

Sets or returns the binary address string used for the I<sup>2</sup>C trigger if the trigger condition is ADDRESS or ADDRANDDATA. Applies to bus <x>, where x is the

bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:I2C:ADDRess:VALue <QString>

TRIGger:A:BUS:B<x>:I2C:ADDRess:VALue?

**Arguments** <QString> is up to 7 or 10-bits depending on the address mode that specifies the

address. The only allowed characters in the QString are 0, 1, and X.

**Examples** TRIGGER:A:BUS:B1:I2C:ADDRESS:VALUE 1011 sets the I<sup>2</sup>C address value

to XXX1011.

## TRIGger:A:BUS:B<x>:I2C:CONDition

Sets or returns the trigger condition for an I<sup>2</sup>C trigger. Applies to bus <x>, where

x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

**Syntax** TRIGger:A:BUS:B<x>:I2C:CONDition

{START|STOP|REPEATStart|ACKMISS|ADDRess|DATA|ADDRANDDATA}

TRIGger:A:BUS:B<x>:I2C:CONDition?

**Arguments** STARt specifies a search based on start condition.

STOP specifies a search based on stop condition.

REPEATStart specifies a search based on repeat of start condition.

ACKMISS specifies a search based on missing acknowledgement condition.

ADDRess specifies a search based on address.

DATA specifies a search based on data.

ADDRANDDATA specifies a search based on address and data.

**Examples** TRIGGER:A:BUS:B1:I2C:CONDITION START specifies start as the I<sup>2</sup>C trigger

condition.

### TRIGger:A:BUS:B<x>:I2C:DATa:DIRection

Sets or returns the I<sup>2</sup>C trigger type to be valid on a Read, Write, or Either condition. Read or write is indicated by the R/W bit in the I<sup>2</sup>C protocol. Applies

to bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:I2C:DATa:DIRection {READ|WRITE|NOCARE}

TRIGger:A:BUS:B<x>:I2C:DATa:DIRection?

**Arguments** READ specifies read as the data direction.

WRITE specifies write as the data direction.

NOCARE specifies either as the data direction.

**Examples** TRIGGER: A: BUS: B1: I2C: DATA: DIRECTION WRITE specifies write as the

I<sup>2</sup>C data direction.

## TRIGger:A:BUS:B<x>:I2C:DATa:SIZe

Sets or returns the length of the data string in bytes to be used for an I2C trigger if the trigger condition is DATA or ADDRANDDATA. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:I2C:DATa:SIZe <NR1>

TRIGger:A:BUS:B<x>:I2C:DATa:SIZe?

**Arguments** <NR1> is the length of the data string in bytes.

# TRIGger:A:BUS:B<x>:I2C:DATa:VALue

Sets or returns the binary data string used for I2C triggering if the trigger condition is DATA or ADDRANDDATA. Applies to bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:I2C:DATa:VALue <QString>

TRIGger:A:BUS:B<x>:I2C:DATa:VALue?

#### **Arguments**

<QString> is the binary data string, where the number of bits is 8 times the number of bytes specified. The only allowed characters in the string are 0, 1, and X.

### TRIGger:A:BUS:B<x>:LIN:CONDition

Sets or returns the trigger condition for LIN.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

**Syntax** TRIGger:A:BUS:B<x>:LIN:CONDition

{SYNCField|IDentifier|DATA|IDANDDATA|WAKEup|SLEEP|ERROR}

TRIGger:A:BUS:B<x>:LIN:CONDition?

**Arguments** SYNCField sets the LIN trigger condition to sync field.

IDentifier sets the LIN trigger condition to identifier.

DATA sets the LIN trigger condition to data.

IDANDDATA sets the LIN trigger condition to ID and data.

WAKEup sets the LIN trigger condition to wake up.

SLEEP sets the LIN trigger condition to sleep.

ERROR sets the LIN trigger condition to error.

**Examples** TRIGGER: A:BUS: B1: LIN: CONDITION ERROR sets the LIN trigger condition

to error.

TRIGGER: A: BUS: B1: LIN: CONDITION? might return

TRIGGER: A: BUS: B1: LIN: CONDITION SYNCFIELD indicating that the LIN

trigger condition is sync field.

# TRIGger:A:BUS:B<x>:LIN:DATa:HIVALue

Sets or returns the binary data string to be used for LIN trigger if trigger condition

is ID or IDANDDATA.

**Conditions** This command requires a DPO2AUTO application module.

Group Bus

Syntax TRIGger:A:BUS:B<x>:LIN:DATa:HIVALue <QString>

TRIGger:A:BUS:B<x>:LIN:DATa:HIVALue?

**Arguments** <QString> is a quoted string that is the binary data string used for LIN trigger if

the trigger condition is ID or IDANDDATA.

**Examples** TRIGGER: A: BUS: B1: LIN: DATA: HIVALUE "11001010" sets the high value

to 11001010.

TRIGGER: A: BUS: B1: LIN: DATA: HIVALUE? might return

TRIGGER: A: BUS: B1: LIN: DATA: HIVALUE "XXXXXXXX" indicating

that the high value is don't care.

# TRIGger:A:BUS:B<x>:LIN:DATa:QUALifier

Sets or returns the LIN data qualifier. This only applies if the trigger condition is

IDANDDATA or DATA.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

**Syntax** TRIGger:A:BUS:B<x>:LIN:DATa:QUALifier

{LESSThan|MOREThan|EQUal|UNEQual|LESSEQual|MOREEQual|INrange|OUTrang

TRIGger:A:BUS:B<x>:LIN:DATa:QUALifier?

**Arguments** LESSThan sets the LIN data qualifier to less than.

MOREThan sets the LIN data qualifier to greater than.

EQUal sets the LIN data qualifier to equal.

UNEQual sets the LIN data qualifier to not equal.

LESSEQual sets the LIN data qualifier to less than or equal.

MOREEQual sets the LIN data qualifier to greater than or equal.

INrange sets the LIN data qualifier to in range.

OUTrange sets the LIN data qualifier to out of range.

**Examples** TRIGGER:A:BUS:B1:LIN:DATA:QUALIFIER OUTRANGE sets the data qualifier

to out of range.

TRIGGER: A: BUS: B1: LIN: DATA: QUALIFIER? might return

TRIGGER: A:BUS: B1:LIN: DATA: QUALIFIER EQUAL indicating that the data

qualifier is set to equal.

# TRIGger:A:BUS:B<x>:LIN:DATa:SIZe

Sets or returns the length of the data string in bytes to be used for LIN trigger.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax TRIGger:A:BUS:B<x>:LIN:DATa:SIZe <NR1>

TRIGger:A:BUS:B<x>:LIN:DATa:SIZe?

**Arguments** <NR1> is the size of the data string in bytes.

**Examples** TRIGGER:A:BUS:B1:LIN:DATA:SIZE 8 sets the data size to 8 bytes.

TRIGGER: A: BUS: B1: LIN: DATA: SIZE? might return

TRIGGER: A: BUS: B1: LIN: DATA: SIZE 1 indicating that the data size is 1 byte.

# TRIGger:A:BUS:B<x>:LIN:DATa:VALue

Sets or returns the binary data string to be used for LIN trigger condition if trigger

condition is ID or IDANDDATA.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax TRIGger:A:BUS:B<x>:LIN:DATa:VALue <QString>

TRIGger:A:BUS:B<x>:LIN:DATa:VALue?

**Arguments** <QString> is a quoted string that is the LIN trigger data value.

**Examples** TRIGGER: A: BUS: B1: LIN: DATA: VALUE "11001101" sets the data value to

11001101.

TRIGGER: A: BUS: B1: LIN: DATA: VALUE? might return

TRIGGER: A:BUS: B1:LIN: DATA: VALUE "XXXXXXXX" indicating

that the data value is don't care.

# TRIGger:A:BUS:B<x>:LIN:ERRTYPE

Sets or returns the error type be used for LIN trigger.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax TRIGger:A:BUS:B<x>:LIN:ERRTYPE {SYNC|PARity|CHecksum}

TRIGger:A:BUS:B<x>:LIN:ERRTYPE?

**Arguments** SYNC sets the LIN error type to SYNC.

PARity sets the LIN error type to parity.

CHecksum sets the LIN error type to checksum.

**Examples** TRIGGER:A:BUS:B1:LIN:ERRTYPE CHECKSUM sets the LIN error type to

checksum.

TRIGGER: A: BUS: B1: LIN: ERRTYPE? might return

TRIGGER: A: BUS: B1: LIN: ERRTYPE SYNC indicating that the LIN error type

is SYNC.

# TRIGger:A:BUS:B<x>:LIN:IDentifier:VALue

Sets or returns the binary address string used for LIN trigger if the trigger

condition is ID or IDANDDATA.

**Conditions** This command requires a DPO2AUTO application module.

**Group** Bus

Syntax TRIGger:A:BUS:B<x>:LIN:IDentifier:VALue <QString>

TRIGger:A:BUS:B<x>:LIN:IDentifier:VALue?

**Arguments** <QString> is the binary address string used for LIN trigger if the trigger

condition is ID or IDANDDATA.

**Examples** TRIGGER:A:BUS:B1:LIN:IDENTIFIER:VALUE "110010" sets the identifier

value to 110010.

TRIGGER:A:BUS:B1:LIN:IDENTIFIER:VALUE? might return

TRIGGER: A:BUS: B1: LIN: IDENTIFIER: VALUE "XXXXXX" indicating that the

identifier value is XXXXXX.

# TRIGger:A:BUS:B<x>:PARallel:VALue

Sets or returns the binary data string to be used for a parallel trigger. Applies to bus  $\langle x \rangle$ , where x is the bus number.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:PARallel:VALue <QString>

TRIGger:A:BUS:B<x>:PARallel:VALue?

**Arguments** <QString> is the binary data string.

## TRIGger:A:BUS:B<x>:RS232C:CONDition

Sets or returns the condition for a RS232C trigger, where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Trigger

**Syntax** TRIGger:A:BUS:B<x>:RS232C:CONDition

{RXSTArt|RXDATA|RXENDPacket|RXPARity|TXSTArt|

TXDATA|TXENDPacket|TXPARity|}

TRIGger:A:BUS:B<x>:RS232C:CONDition?

**Arguments** RXSTArt specifies a search based on the RX Start Bit.

RXDATA specifies a search based on RX Data.

RXENDPacket specifies a search based on the RX End of Packet condition.

RXPARity specifies a search based on the RX parity.

TXSTArt specifies a search base on the TX Start Bit.

TXDATA specifies a search based on TX Data.

TXENDPacket specifies a search based on the TX End of Packet condition.

TXPARity specifies a search based on the TX parity.

# TRIGger:A:BUS:B<x>:RS232C:RX:DATa:SIZe

Sets or returns the length of the data string in Bytes for a RS232 Trigger if the trigger condition is RXDATA. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:RS232C:RX:DATa:SIZe <NR1>

TRIGger:A:BUS:B<x>:RS232C:RX:DATa:SIZe?

**Arguments** <NR1> is the length of the data string in bytes.

# TRIGger:A:BUS:B<x>:RS232C:RX:DATa:VALue

Sets or returns the binary data string for a RS232 trigger if the trigger condition

involves RX. Applies to bus  $\langle x \rangle$ , where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Trigger

**Syntax** TRIGger:A:BUS:B<x>:RS232C:RX:DATa:VALue

TRIGger:A:BUS:B<x>:RS232C:RX:DATa:VALue?

**Arguments** <Qstring> is the binary data string to be used for the trigger.

# TRIGger:A:BUS:B<x>:RS232C:TX:DATa:SIZe

Sets or returns the length of the data string for a RS232 trigger if the trigger condition is TXDATA. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:RS232C:TX:DATa:SIZe <NR1>

TRIGger:A:BUS:B<x>:RS232C:TX:DATa:SIZe?

**Arguments** <NR1> is the length of the data string in Bytes.

# TRIGger:A:BUS:B<x>:RS232C:TX:DATa:VALue

Sets or returns the binary data string for a RS232 trigger if the condition involves TX. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2COMP application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:RS232C:TX:DATa:VALue

TRIGger:A:BUS:B<x>:RS232C:TX:DATa:VALue?

**Arguments** <Qstring> is the binary data string to be used for the trigger.

## TRIGger:A:BUS:B<x>:SPI:CONDition

Sets or returns the trigger condition for a SPI trigger. Applies to bus  $\langle x \rangle$ , where x

is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:SPI:CONDition

{SS|STARTOfframe|MISO|MOSI|MISOMOSI}
TRIGger:A:BUS:B<x>:SPI:CONDition?

**Arguments** SS specifies the Slave Selection condition.

STARTofframe specifies the start of frame condition.

MISO specifies the Master-In Slave-Out condition.

MOSI specifies the Master-Out Slave-In condition.

MISOMOSI specifies the Master-In Slave-Out and Master-Out Slave-In conditions.

# TRIGger:A:BUS:B<x>:SPI:DATa{:IN|:MISO}:VALue

Sets or returns the binary data string to be used for a SPI trigger if the trigger condition is MISO or MISOMOSI. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:SPI:DATa{:IN|:MISO}:VALue <QString>

TRIGger:A:BUS:B<x>:SPI:DATa{:IN|:MISO}:VALue?

**Arguments** <QString> is the binary data string, where the number of bits is 8 times the

number of bytes specified. The only allowed characters in the string are 0, 1,

and X.

# TRIGger:A:BUS:B<x>:SPI:DATa{:OUT|:MOSI}:VALue

Sets or returns the binary data string to be used for a SPI trigger if the trigger condition is MOSI or MISOMOSI. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:SPI:DATa{:OUT|:MOSI}:VALue <QString>

TRIGger:A:BUS:B<x>:SPI:DATa{:OUT|:MOSI}:VALue?

**Arguments** 

<QString> is the binary data string with the number of bits specified by the TRIGger:A:BUS:B<x>:SPI:DATa:SIZe command. The only allowed characters in the QString are 0, 1, and X.

### TRIGger:A:BUS:B<x>:SPI:DATa:SIZe

Sets or returns the length of the data string to be used for a SPI trigger if the trigger condition is MISO, MOSI, or MISOMOSI. Applies to bus <x>, where x is the bus number.

**Conditions** This command requires a DPO2EMBD application module.

**Group** Trigger

Syntax TRIGger:A:BUS:B<x>:SPI:DATa:SIZe <NR1>

TRIGger:A:BUS:B<x>:SPI:DATa:SIZe?

**Arguments** <NR1> is the length of the data string in bytes.

# TRIGger: A:BUS: SOUrce

Sets or returns the source for a Serial bus trigger.

**Conditions** This command requires a DPO2AUTO or DPO2EMBD application module.

**Group** Trigger

**Syntax** TRIGger:A:BUS:SOUrce {B1|B2}

TRIGger: A: BUS: SOUrce?

**Arguments** B1 specifies the Bus 1 source.

B2 specifies the Bus 2 source.

# TRIGger:A:EDGE? (Query Only)

Returns the trigger source, coupling, and slope for the A edge trigger.

**Group** Trigger

**Syntax** TRIGger:A:EDGE?

**Related Commands** TRIGger:A:PULse?, TRIGger:A:LOGIc?

**Examples** TRIGGER:A:EDGE? might return :TRIGGER:A:EDGE:SOURCE CH1;COUPLING

DC; SLOPE RISE indicating that the trigger source, coupling, and slope for

the A edge trigger.

# TRIGger: A: EDGE: COUPling

Sets or returns the type of coupling for the A edge trigger.

**Group** Trigger

Syntax TRIGger:A:EDGE:COUPling {DC|HFRej|LFRej|NOISErej}

TRIGger: A: EDGE: COUPling?

Related Commands TRIGger:A:EDGE:SOUrce, TRIGger:A:EDGE:SLOpe

**Arguments** DC specifies DC trigger coupling, which passes all input signals to the trigger

circuitry.

HFRej specifies high-frequency rejection coupling, which attenuates signals

above 50 kHz before passing the signals to the trigger circuitry.

LFRe j specifies low-frequency rejection coupling, which attenuates signals below

50 kHz before passing the signals to the trigger circuitry.

NOISErej specifies noise-rejection coupling, which provides stable triggering

by increasing the trigger hysteresis. Increased hysteresis reduces the trigger

sensitivity to noise but may require greater trigger signal amplitude.

**Examples** TRIGGER: A: EDGE: COUPLING DC sets the A edge trigger coupling to DC.

TRIGGER: A: EDGE: COUPLING? might return: TRIGGER: A: EDGE: COUPLING

DC indicating that the A edge trigger coupling is set to DC.

# TRIGger: A: EDGE: SLOpe

Sets or returns the slope for the A edge trigger.

**Group** Trigger

Syntax TRIGger:A:EDGE:SLOpe {RISe|FALL}

TRIGger:A:EDGE:SLOpe?

Related Commands TRIGger: A:EDGE: SOUrce, TRIGger: A:EDGE: COUPling

**Arguments** RISe specifies to trigger on the rising or positive edge of a signal.

FALL specifies to trigger on the falling or negative edge of a signal.

**Examples** TRIGGER: A: EDGE: SLOPE RISE sets the A edge trigger slope to positive, which

triggers on the rising edge of the signal.

TRIGGER: A: EDGE: SLOPE? might return: TRIGGER: A: EDGE: SLOPE FALL

indicating that the A edge trigger slope is negative.

# TRIGger:A:EDGE:SOUrce

Sets or returns the source for the A edge trigger.

**Group** Trigger

Syntax TRIGger:A:EDGE:SOUrce {{CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|

D14|D15|EXT|LINE|AUX} TRIGger:A:EDGE:SOUrce?

Related Commands TRIGger: A:EDGE: SLOpe, TRIGger: A:EDGE: COUPling

**Arguments** CH1–CH4 specifies an analog input channel as the A edge trigger source.

D0-D15 specifies a digital input channel as the A edge trigger source.

EXT specifies an external trigger using the Aux In connector located on the front

panel of the oscilloscope.

LINE specifies the AC line as the trigger source.

AUX specifies the Auxiliary Input as the trigger source (if available on your oscilloscope).

The state of the s

**Examples** TRIGGER: A: EDGE: SOURCE CH1 sets channel 1 as the A edge trigger source.

TRIGGER:A:EDGE:SOURCE? might return :TRIGGER:A:EDGE:SOURCE CH1

indicating that channel 1 is the A edge trigger source.

# TRIGger:A:HOLDoff? (Query Only)

Returns the A trigger holdoff parameters. These parameters specify the time period during which the trigger circuitry is not looking to generate a trigger event.

**Group** Trigger

**Syntax** TRIGger:A:HOLDoff?

Related Commands TRIGger: A:HOLDoff: TIMe

**Examples** TRIGGER:A:HOLDOFF? might return :TRIGGER:A:HOLDOFF:TIME

900.0000E-09; BY DEFAULT indicating that the A edge trigger holdoff time

(by default) is 900 ns.

# TRIGger: A: HOLDoff: TIMe

Sets or returns the A trigger holdoff time.

**Group** Trigger

Syntax TRIGger:A:HOLDoff:TIMe <NR3>

TRIGger:A:HOLDoff:TIMe?

**Arguments** <NR3> specifies the holdoff time in seconds. The range is from 20 ns through 8.0 s.

**Examples** TRIGGER: A: HOLDOFF: TIME? might return: TRIGGER: A: HOLDOFFTIME

1.2000E-06 indicating that the A trigger holdoff time is set to 1.2  $\mu$ s.

TRIGGER: A: HOLDOFF: TIME 10 sets the A trigger holdoff time to 10 s.

# TRIGger:A:LEVel

Sets or returns the trigger level for the A trigger.

**Group** Trigger

Syntax TRIGger:A:LEVel {ECL|TTL|<NR3>}

TRIGger:A:LEVel?

**Arguments** ECL specifies a preset ECL high level of -1.3V.

TTL specifies a preset TTL high level of 1.4V.

<NR3> specifies the trigger level in user units (usually volts).

**Examples** TRIGGER:A:LEVEL? might return:TRIGGER:A:LEVel 1.3000E+00

indicating that the A edge trigger is set to 1.3 V.

TRIGGER: A: LEVEL TTL sets the A edge trigger to TTL high level, which is 1.4 V.

### TRIGger: A: LEVel: AUXin

Sets or returns the trigger level for the AUXIN port.

**Group** Trigger

Syntax TRIGger:A:LEVel:AUXin {<NR3>|ECL|TTL}

TRIGger:A:LEVel:AUXin?

**Arguments** <NR3> specifies the trigger level, in volts.

ECL specifies a preset ECL trigger level of -1.3 V.

TTL specifies a preset TTL trigger level of 1.4 V.

**Examples** TRIGGER:A:LEVEL:AUXIN ECL sets the auxiliary input trigger level to -1.3

volts.

TRIGGER:A:LEVEL:AUXIN? might return TRIGGER:A:LEVEL:AUXIN 0.0E+0

indicating that the auxiliary input trigger level is 0.0 volts.

## TRIGger:A:LEVel:CH<x>

Sets or returns the trigger level for the specified channel. Each channel can have an independent level.

**Group** Trigger

Syntax TRIGger:A:LEVel:CH<x> {<NR3>|TTL|ECL}

TRIGger:A:LEVel:CH<x>?

**Arguments** <NR3> specifies the trigger level in user units (usually volts).

TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

**Examples** TRIGGER:A:LEVEL:CH2? might return :TRIGGER:A:LEVEL:CH2

1.3000E+00 indicating that the A edge trigger is set to 1.3 V for channel 2.

TRIGGER:A:LEVEL:CH3 TTL sets the A edge trigger to TTL high level for

channel 3.

### TRIGger:A:LEVel:D<x>

Sets or returns the trigger level for the specified digital channel <x>, where x is the channel number. The digital channels do not have independent trigger levels. Channels D0–D7 share one common trigger level and D8–D15 share another common trigger level. For example: Changing the trigger level for D3 changes the levels for D0–D7.

**Group** Trigger

Syntax TRIGger:A:LEVel:D<x> {<NR3>|ECL|TTL}

TRIGger:A:LEVel:D<x>?

**Arguments** ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

<NR3> specifies the trigger level in volts.

## TRIGger:A:LOGIc? (Query Only)

Returns all of the A logic trigger parameters.

**Group** Trigger

Syntax TRIGger:A:LOGIc?

Related Commands TRIGger:A:LOGIc:CLAss

**Examples** TRIGGER:A:LOGIC? might return :TRIGGER:A:LOGIC:CLASS

SETHOLD; FUNCTION AND; THRESHOLD: CH1 20.0000E-3; CH2 0.0000;

CH3 0.0000;CH4 0.0000;:TRIGGER:A:LOGIC:INPUT:CH1

X;CH2 X;CH3 X;CH4 X;CLOCK:SOURCE NONE;EDGE

RISE;:TRIGGER:A:LOGIC:PATTERN:INPUT:CH1 X;CH2 X;CH3

X;CH4 X;:TRIGGER :A:LOGIC:PATTERN:WHEN TRUE;WHEN:LESSLIMIT 4.0000E-9;LIMIT 4.0000E-9;:TRIGGER:A:LOGIC:PATTERN:DELTATIME

4.0000E-9

## TRIGger: A: LOGIc: CLAss

Sets or returns the class of the Logic Trigger. This command is used in conjunction with the TRIGger:A:TYPe command.

**Group** Trigger

Syntax TRIGger:A:LOGIc:CLAss {LOGIC|SETHold}

TRIGger:A:LOGIc:CLAss?

**Related Commands** TRIGger:A:TYPe, TRIGger:A:PULse:CLAss

**Arguments** LOGIC sets the oscilloscope to trigger on logical combinations of the channels.

When the TRIGger:A:LOGIc:INPut:CLOCk:SOUrce is NONE, LOGIC sets the oscilloscope to trigger when the specified logical combinations of channels 1, 2, 3, and 4 are met on four-channel oscilloscopes. On two-channel oscilloscopes,

only channel 1 and channel 2 are available.

When the TRIGger:A:LOGIc:INPut:CLOCk:SOUrce is set to one of the channels, LOGIC sets the oscilloscope to trigger when the specified logical combinations of the remaining channels is true during a transition on the clock channel.

SETHold sets the oscilloscope to trigger on setup and hold violations between a data source and a clock source. Use one channel input as the clock signal and a second channel input as the data input. The clocking and data levels are used to determine if a clock or data transition has occurred.

Examples

TRIGGER: A: LOGIC: CLASS? might return: TRIGGER: A: LOGIC: CLASS LOGIC

TRIGGER: A: LOGIC: CLASS LOGIC sets the trigger A logic class to LOGIc, which causes the oscilloscope to trigger when the specified logical combinations of channels 1, 2, 3, and 4 are met.

## TRIGger: A:LOGIc: FUNCtion

Sets or returns the logical combination of the input channels for the A pattern and A state logic triggers.

**Group** Trigger

Syntax TRIGger:A:LOGIc:FUNCtion {AND|NANd}

TRIGger:A:LOGIc:FUNCtion?

Related Commands TRIGger:A:LOGIc:INPut:CH<x>

**Arguments** AND specifies to trigger if all conditions are true.

NANd specifies to trigger if any of the conditions is false.

**Examples** TRIGGER:A:LOGIC:FUNCTION? might return:TRIGGER:A:LOGIC:FUNCTION

NAND which indicates that the oscilloscope will trigger if the AND logic conditions

are false.

TRIGGER: A: LOGIC: FUNCTION AND sets the logical combination of channels to

be true when all conditions are true.

## TRIGger:A:LOGIc:INPut? (Query Only)

Returns the logic input values for all channels. If a clock channel is defined, it returns the clock source and edge.

Syntax TRIGger:A:LOGIc:INPut?

**Examples** TRIGGER:A:LOGIC:INPUT? might return :TRIGGER:A:LOGIC:INPUT:CH1

HIGH; CH2 X; CH3 X indicating that a logic high is expected on channel 1 while

channel 2 and channel three are "don't care."

## TRIGger:A:LOGIc:INPut:CH<x>

Sets or returns the logical input condition for the channel specified by  $\langle x \rangle$ .

**Group** Trigger

Syntax TRIGger:A:LOGIc:INPut:CH<x> {HIGH|LOW|X}

TRIGger:A:LOGIc:INPut:CH<x>?

**Arguments** HIGH specifies the logic high.

LOW specifies the logic low.

X specifies a "don't care" state.

**Examples** TRIGGER:A:LOGIC:INPUT:CH1? might return:TRIGGER:LOGIC:INPUT:CH1

X indicating that the setting for the A logic trigger input to channel 1 does not

matter.

TRIGGER: A: LOGIC: INPUT: CH2 HIGH sets the A logic trigger input to logic

HIGH for channel 2.

## TRIGger:A:LOGIc:INPut:CLOCk:EDGE

Sets the polarity of the clock channel.

**Group** Trigger

Syntax TRIGger:A:LOGIc:INPut:CLOCk:EDGE {FALL|RISe|EITher}

TRIGger:A:LOGIc:INPut:CLOCk:EDGE?

**Arguments** RISe specifies to trigger on the rising or positive edge of a signal.

FALL specifies to trigger on the falling or negative edge of a signal.

EITher specifies to trigger either on the falling or rising edge of a signal.

## TRIGger: A:LOGIc: INPut: CLOCk: SOUrce

Sets or returns the channel to use as the clock source. The clock can be selected as NONE. A selection of None implies pattern trigger. Any other selection implies state trigger.

**Group** Trigger

Syntax TRIGger:A:LOGIc:INPut:CLOCk:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15|NONE}

TRIGger:A:LOGIc:INPut:CLOCk:SOUrce?

**Arguments** CH1-CH4 specifies the analog input channel source.

D0-D15 specifies the digital input channel source.

NONE specifies a Pattern trigger.

### TRIGger:A:LOGIc:INPut:D<x>

Sets or returns the logic pattern for a trigger on digital channel  $\langle x \rangle$ , where x is the channel number.

**Group** Trigger

Syntax TRIGger:A:LOGIc:INPut:D<x> {HIGH|LOW|X}

TRIGger:A:LOGIc:INPut:D<x>?

**Arguments** High specifies the logic high state.

Low specifies the logic low state.

X specifies a "don't care" state.

## TRIGger:A:LOGIc:PATtern? (Query Only)

Returns the conditions used for generating an A logic pattern trigger, with respect to the defined input pattern, and identifies the time that the selected pattern may be true and still generate the trigger.

Syntax TRIGger:A:LOGIc:PATtern?

**Examples** TRIGGER:A:LOGIC:PATTERN? might return

:TRIGGER:A:LOGIC:PATTERN:INPUT:CH1 HIGH;CH2 LOW;CH3 X;CH4 X;:TRIGGER:A:LOGIC:PATTERN:WHEN LESSTHAN;WHEN:LESSLIMIT 16.0000E-9;LIMIT

16.0000E-9;:TRIGGER:A:LOGIC:PATTERN:DELTATIME 16.0000E-9

## TRIGger: A:LOGIc: PATtern: DELTatime

Sets or returns the pattern trigger delta time value. The time value is used as part of the pattern trigger condition to determine if the duration of a logic pattern meets the specified time constraints.

**Group** Trigger

Syntax TRIGger:A:LOGIc:PATtern:DELTatime <NR3>

TRIGger: A: LOGIc: PATtern: DELTatime?

**Arguments** <NR3> is a floating point value with exponent that sets the pattern trigger time

value. This argument has a range of 39.6E–9 (39.6 ns) to 10.0E0 (10 s), in increments of 13.2 ns. Values that are not an increment of 13.2 ns are rounded to

the nearest correct value.

**Examples** TRIGGER: A:LOGIC: PATTERN: DELTATIME 71.28E-8 sets the pattern trigger

delta time value to 712.8 ns.

### TRIGger:A:LOGIc:PATtern:INPut:D<x>

Sets or returns the A logic trigger input for the specified digital channel <x>, where x is the channel number. This command species the logic value used when the pattern trigger detects the threshold level.

**Group** Trigger

Syntax TRIGger:A:LOGIc:PATtern:INPut:D<x> {HIGH|LOW|X}

TRIGger:A:LOGIc:PATtern:INPut:D<x>?

**Arguments** HIGH specifies a logic high.

LOW specifies a logic low.

X specifies a "do not care" state.

## TRIGger: A: LOGIc: PATtern: WHEn

Sets or returns the pattern logic condition on which to trigger the oscilloscope.

**Group** Trigger

**Syntax** TRIGger:A:LOGIc:PATtern:WHEn

{TRUe|FALSe|LESSThan|MOREThan|EQUal|UNEQual}

TRIGger:A:LOGIc:PATtern:WHEn?

**Arguments** TRUE triggers the oscilloscope when the pattern becomes true.

FALSE triggers the oscilloscope when the pattern becomes false.

LESSTHAN triggers the oscilloscope when the input pattern is true for a time period less than the time period specified in TRIGGER: A:LOGIC: PATTERN: DELTATIME.

MORETHAN triggers the oscilloscope when the input pattern is true for a time period more (greater) than the time period specified in

TRIGGER: A: LOGIC: PATTERN: DELTATIME.

EQUAL triggers the oscilloscope when the input pattern is true for a time period equal to the time period specified in TRIGGER: A:LOGIC: PATTERN: DELTATIME, within a  $\pm 5\%$  tolerance.

UNEQUAL triggers the oscilloscope when the input pattern is true for a time period greater than or less than (not equal to) the time period specified in TRIGGER:A:LOGIC:PATTERN:DELTATIME, within a  $\pm 5\%$  tolerance.

**Examples** TRIGGER: A: LOGIC: PATTERN: WHEN LESSTHAN sets the oscilloscope to trigger

when the pattern is true for a time period less than the pattern trigger delta time

setting.

### TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit

Sets or returns the maximum time that the selected pattern may be true and still generate an A logic pattern trigger.

Syntax TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit <NR3>

TRIGger:A:LOGIc:PATtern:WHEn:LESSLimit?

**Arguments** <NR3> specifies the maximum amount of time to hold the pattern true.

**Examples** TRIGGER:A:LOGIC:PATTERN:WHEN:LESSLIMIT 10.0E+00 sets the

maximum time that the selected pattern may hold true (and generate an A logic

pattern trigger) to 10 s.

TRIGGER: A: LOGIC: PATTERN: WHEN: LESSLIMIT? might return

TRIGGER:A:LOGIC:PATTERN:WHEN:LESSLIMIT 8.0000E-9 indicating that the selected pattern may hold true for up to 8 ns and still generate an A logic

pattern trigger.

## TRIGger: A: LOGIc: PATtern: WHEn: MORELimit

Sets or returns the minimum time that the selected pattern may be true and still generate an A logic pattern trigger.

**Group** Trigger

Syntax TRIGger:A:LOGIc:PATtern:WHEn:MORELimit <NR3>

TRIGger: A: LOGIc: PATtern: WHEn: MORELimit?

**Arguments** <NR3> specifies the minimum amount of time to hold the pattern true.

**Examples** TRIGGER:A:LOGIC:PATTERN:WHEN:MORELIMIT 10.0E+00 sets the minimum

time that the selected pattern may hold true (and generate an A logic pattern

trigger) to 10 s.

TRIGGER: A: LOGIC: PATTERN: WHEN: MORELIMIT? might return

TRIGGER:A:LOGIC:PATTERN:WHEN:MORELIMIT 8.0000E-9 indicating that the selected pattern must hold true for at least 8 ns to generate an A logic pattern

trigger.

# TRIGger:A:LOGIc:THReshold:(CH<x>|D<x>)

This command sets or queries the logic trigger threshold voltage for both analog and digital channels (for MSO models), specified by x.

Syntax TRIGger:A:LOGIc:THReshold:(CH<x>|D<x>) {<NR3>|ECL|TTL}

TRIGger:A:LOGIc:THReshold:(CH<x>|D<x>)?

**Arguments** <NR3> specifies the threshold voltage, in volts.

ECL specifies a preset ECL high level of -1.3 V. TTL specifies a preset TTL high level of 1.4 V.

voltage for Channel 2 to 3 mV.

TRIGGER: A: LOGIC: THRESHOLD: CH3? might return

:TRIGGER:A:LOGIC:THRESHOLD:CH3 1.2000E+00, indicating that the A

TRIGGER: A: LOGIC: THRESHOLD: CH2 3.0E-3 sets the A logic trigger threshold

logic trigger threshold voltage for Channel 3 is 1.2 V.

## TRIGger:A:LOWerthreshold:CH<x>

**Examples** 

Sets or returns the lower threshold for the channel selected. Each channel can have an independent level. Used in Runt and Slew Rate triggers as the lower threshold. Used for all other trigger types as the single level/threshold.

**Group** Trigger

Syntax TRIGger:A:LOWerthreshold:CH<x> {ECL|TTL|<NR3>}

TRIGger:A:LOWerthreshold:CH<x>?

Related Commands TRIGger:A:LEVel:CH<x>

**Arguments** ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

<NR3> is the clock level, in volts.

**Examples** TRIGGER:A:LOWERTHRESHOLD:CH2 50E-3 sets the lower limit threshold for

CH2 of the pulse runt trigger to 50 mV.

TRIGGER: A: LOWERTHRESHOLD: CH2? might return: TRIGGER: A:

LOWERTHRESHOLD: CH2 1.2000E-01 indicating that the lower limit threshold

for CH2 of the pulse runt trigger is set to 120 mV.

## TRIGger:A:LOWerthreshold{:EXT|:AUX}

Sets or returns the lower threshold for the Auxiliary Input. It is similar to TRIGger: A:LEVel: AUXin.

**Group** Trigger

Syntax TRIGger:A:LOWerthreshold{:EXT|:AUX} {<NR3>|ECL|TTL}

TRIGger:A:LOWerthreshold{:EXT|:AUX}?

**Arguments** ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

<NR3> specifies the threshold level in volts.

## TRIGger: A: MODe

Sets or returns the A trigger mode.

**Group** Trigger

Syntax TRIGger:A:MODe {AUTO|NORMal}

TRIGger:A:MODe?

Related Commands TRIGger: A:LEVel

**Arguments** AUTO generates a trigger if one is not detected within a specified time period.

NORMal waits for a valid trigger event.

**Examples** TRIGGER: A: MODE NORMAL specifies that a valid trigger event must occur before

a trigger is generated.

TRIGGER: A: MODE ? might return : TRIGGER: A: MODE NORMAL indicating that a

valid trigger event must occur before a trigger is generated.

## TRIGger:A:PULse? (Query Only)

Returns the A pulse trigger parameters.

**Group** Trigger

**Syntax** TRIGger:A:PULse?

**Related Commands** TRIGger:A:EDGE?, TRIGger:A:LOGIc?

**Examples** TRIGGER:A:PULSE? might return:TRIGGER:A:PULSE:CLASS TRANSITION

### TRIGger:A:PULse:CLAss

Sets or returns the type of pulse on which to trigger.

**Group** Trigger

Syntax TRIGger:A:PULse:CLAss {RUNt|WIDth|TRANsition}

TRIGger:A:PULse:CLAss?

**Related Commands** TRIGger:A:RUNT?, TRIGger:A:PULSEWIDth?, TRIGger:A {:TRANsition|:

RISEFall}?, TRIGger:A:TYPe

**Arguments** RUNt triggers when a pulse crosses the first preset voltage threshold but does not

cross the second preset threshold before recrossing the first.

WIDth triggers when a pulse is found that has the specified polarity and is either

inside or outside the specified time limits.

TRAnsition triggers when a pulse crosses both thresholds in the same direction

as the specified polarity and the transition time between the two threshold

crossings is greater or less than the specified time delta.

**Examples** TRIGGER:A:PULSE:CLASS WIDTH specifies a width pulse for the A trigger.

TRIGGER:A:PULSE:CLASS? might return :TRIGGER:A:PULSE:CLASS WIDTH

indicating that a pulse was found that is of the specified polarity and width.

## TRIGger:A:PULSEWIDth? (Query Only)

Returns the width parameters for the pulse width trigger.

**Syntax** TRIGger:A:PULSEWIDth?

**Examples** TRIGGER:A:PULSEWIDTH? might return

:TRIGGER:A:PULSEWIDTH:POLARITY POSITIVE;WHEN LESSTHAN;WIDTH

8.0000E-9

### TRIGger:A:PULSEWidth:POLarity

Sets or returns the polarity for the width trigger.

**Group** Trigger

**Syntax** TRIGger:A:PULSEWidth:POLarity {NEGative|POSitive}

TRIGger: A: PULSEWidth: POLarity?

**Arguments** NEGative specifies a negative pulse.

POSitive specifies a positive pulse.

**Examples** TRIGGER: A: PULSEWIDTH: POLARITY NEGATIVE sets the pulse polarity to

negative.

TRIGGER: A: PULSEWIDTH: POLARITY? might return

:TRIGGER:A:WIDTH:POLARITY POSITIVE indicating a positive pulse.

## TRIGger:A:PULSEWidth:SOUrce

Sets or returns the source for the pulse-width trigger.

**Group** Trigger

Syntax TRIGger:A:PULSEWidth:SOUrce {{CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15|LINE|EXT}

TRIGger:A:PULSEWidth:SOUrce?

**Arguments** CH1–CH4 specifies an analog input channel as the A edge trigger source.

D0-D15 specifies an digital input channel as the A edge trigger source.

EXT specifies an external trigger using the Aux In connector located on the front

panel of the oscilloscope.

LINE specifies AC line voltage.

**Examples** TRIGGER: A: PULSEWIDTH: SOURCE CH1 sets channel 1 as the pulse width source.

TRIGGER:A:PULSEWIDTH:SOURCE? might return :TRIGGER:A:PULSEWIDTH:

SOURCE CH1 indicating that channel 1 is the pulse width source.

### TRIGger: A: PULSEWidth: WHEn

Sets or returns whether to trigger on a pulse that meets, falls outside, or within the specified range of limits.

**Group** Trigger

**Syntax** TRIGger:A:PULSEWidth:WHEn {LESSthan|MOREthan|EQual|UNEQual}

TRIGger: A: PULSEWidth: WHEn?

Related Commands TRIGger:A:PULSEWidth:WIDth

**Arguments** LESSthan argument sets the oscilloscope to trigger if a pulse is detected with width less than the time set by the TRIGger:A:PULSEWidth:WIDth command.

MOREthan argument sets the oscilloscope to trigger if a pulse is detected with width more than the time set by the TRIGger:A:PULSEWidth:WIDth command.

EQUal argument sets the oscilloscope to trigger if a pulse is detected with width equal to the time period specified in TRIGger:A:PULSEWidth:WIDth within a  $\pm 5\%$  tolerance.

UNEQual argument sets the oscilloscope to trigger if a pulse is detected with width greater than or less than (but not equal) the time period specified in TRIGger:A:PULSEWidth:WIDth within a  $\pm 5\%$  tolerance.

**Examples** TRIGGER: A: PULSEWIDTH: WHEN LESSTHAN specifies that the duration of the A pulse will fall within defined high and low limits.

TRIGGER: A: PULSEWIDTH: WHEN? might return: TRIGGER: A: PULSEWIDTH: WHEN THAN indicating that the conditions for generating a width trigger.

TRIGger:A:PULSEWidth:WIDth

Sets or returns the width setting for the pulse width trigger.

**Group** Trigger

Syntax TRIGger:A:PULSEWidth:WIDth <NR3>

TRIGger:A:PULSEWidth:WIDth?

Related Commands TRIGger: A:PULSEWidth: WHEn

**Arguments** <NR3> specifies the pulse width in seconds.

**Examples** TRIGGER:A:PULSEWIDTH:WIDTH 5.0E-6 sets the pulse width to 5  $\mu$ s.

TRIGGER: A: PULSEWIDTH: WIDTH? might return: TRIGGER: A: PULSEWIDTH:

WIDTH 2.0000E-9 indicating that the pulse width is set to 2 ns.

## TRIGger: A:RUNT? (Query Only)

Returns the current A runt trigger parameters.

**Group** Trigger

**Syntax** TRIGger:A:RUNT?

**Examples** TRIGGER: A:RUNT? might return: TRIGGER: A:RUNT: SOURCE CH1; POLARITY

POSITIVE; WHEN OCCURS; WIDTH 4.0000E-9.

## TRIGger: A: RUNT: POLarity

Sets or returns the polarity for the runt trigger.

**Group** Trigger

**Syntax** TRIGger:A:RUNT:POLarity {EITher|NEGative|POSitive}

TRIGger: A: RUNT: POLarity?

**Arguments** POSitive indicates that the rising edge crosses the low threshold and the falling

edge recrosses the low threshold without either edge ever crossing the high

threshold.

NEGative indicates that the falling edge crosses the high threshold and the rising edge recrosses the high threshold without either edge ever crossing the low threshold.

EITher triggers on a runt of either polarity.

**Examples** 

TRIGGER: A: RUNT: POLARITY NEGATIVE specifies that the polarity of the A

pulse runt trigger is negative.

TRIGGER:A:RUNT:POLARITY? might return:TRIGGER:A:RUNT:POLARITY POSITIVE indicating that the polarity of the A pulse runt trigger is positive.

## TRIGger: A: RUNT: SOUrce

Sets or returns the source for the A runt trigger.

**Group** Trigger

Syntax TRIGger:A:RUNT:SOUrce {CH1|CH2|CH3|CH4}

TRIGger:A:RUNT:SOUrce?

Arguments CH1-CH4 specifies the input channel number, depending on the model of the

oscilloscope.

**Examples** TRIGGER:A:RUNT:SOURCE CH4 sets channel 4 as the source for the A pulse

trigger.

TRIGGER: A:RUNT: SOURCE? might return: TRIGGER: A:RUNT: SOURCE CH2

indicating that channel 2 is the source for the A pulse trigger.

## TRIGger: A: RUNT: WHEn

Sets or returns the type of pulse width the trigger checks for when it detects a runt.

**Group** Trigger

Syntax TRIGger:A:RUNT:WHEn {LESSthan|MOREthan|EQual|UNEQual|OCCURS}

TRIGger: A: RUNT: WHEn?

Related Commands TRIGger: A:RUNT: WIDth

#### **Arguments**

OCCURS argument specifies a trigger event if a runt of any detectable width occurs.

LESSthan argument sets the oscilloscope to trigger if the a runt pulse is detected with width less than the time set by the TRIGger:A:RUNT:WIDth command.

MOREthan argument sets the oscilloscope to trigger if the a runt pulse is detected with width more than the time set by the TRIGger:A:RUNT:WIDth command.

EQUal argument sets the oscilloscope to trigger if a runt pulse is detected with width equal to the time period specified in TRIGger:A:RUNT:WIDth within a  $\pm 5\%$  tolerance.

UNEQual argument sets the oscilloscope to trigger if a runt pulse is detected with width greater than or less than (but not equal to) the time period specified in TRIGger:A:RUNT:WIDth within a  $\pm 5\%$  tolerance.

### **Examples**

TRIGGER:A:RUNT:WHEN THAN sets the runt trigger to occur when the oscilloscope detects a runt in a pulse wider than the specified width.

TRIGGER:A:RUNT:WHEN? might return :TRIGGER:A:PULSE:RUNT:WHEN OCCURS indicating that a runt trigger will occur if the oscilloscope detects a runt of any detectable width.

## TRIGger: A: RUNT: WIDth

Sets or returns the width for a runt trigger.

**Group** Trigger

Syntax TRIGger:A:RUNT:WIDth <NR3>

TRIGger:A:RUNT:WIDth?

Related Commands TRIGger: A:RUNT: WHEn

**Arguments** <NR3> specifies the minimum width, in seconds.

**Examples** TRIGGER:A:RUNT:WIDTH 15E-6 sets the minimum width of the pulse runt

trigger to 15 µs.

TRIGGER:A:RUNT:WIDTH? might return :TRIGGER:A:PULSE:RUNT:WIDTH 2.0000E-09 indicating that the minimum width of a pulse runt trigger is 2 ns.

## TRIGger: A:SETHold? (Query Only)

Returns the clock edge polarity, voltage threshold and source input; data voltage threshold and source; and both setup and hold times for setup and hold violation triggering.

**Group** Trigger

Syntax TRIGger:A:SETHold?

**Examples** TRIGGER:A:SETHOLD? might return

:TRIGGER:A:SETHOLD:CLOCK:SOURCE CH1;EDGE RISE;THRESHOLD 100.0000E-3;:TRIGGER:A:SETHOLD:DATA:SOURCE CH2;THRESHOLD 80.0000E-3;:TRIGGER:A:SETHOLD:HOLDTIME 20.0000E-9;SETTIME

8.0000E-9

## TRIGger:A:SETHold:CLOCk? (Query Only)

Returns the clock edge polarity, voltage threshold, and source input for setup and hold triggering.

**Group** Trigger

Syntax TRIGger:A:SETHold:CLOCk?

**Examples** TRIGGER:A:SETHOLD:CLOCK? might return

:TRIGGER:A:SETHOLD:CLOCK:SOURCE EXT;EDGE FALL;THRESHOLD

1.4000

## TRIGger:A:SETHold:CLOCk:EDGE

Sets or returns the clock edge polarity for setup and hold triggering.

**Group** Trigger

Syntax TRIGger:A:SETHold:CLOCk:EDGE {FALL|RISe}

TRIGger:A:SETHold:CLOCk:EDGE?

**Arguments** FALL specifies polarity as the clock falling edge.

RISe specifies polarity as the clock rising edge.

**Examples** TRIGGER: A: SETHOLD: CLOCK: EDGE RISE specifies the polarity as the clock

rising edge.

TRIGGER:A:SETHOLD:CLOCK:EDGE? might return:TRIGGER:A:SETHOLD:CLOCK:EDGE RISE indicating that polarity is specified as the clock rising edge.

## TRIGger: A: SETHold: CLOCk: SOUrce

Sets or returns the clock source for the setup and hold triggering.

**Group** Trigger

Syntax TRIGger:A:SETHold:CLOCk:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

TRIGger:A:SETHold:CLOCk:SOurce?

Related Commands TRIGger: A:SETHold: DATa: SOUrce

**Arguments** CH1-CH4 specifies the input channel number.

D0-D15 specifies the input digital channel number.

**Examples** TRIGGER:A:SETHOLD:CLOCK:SOURCE CH1 specifies channel 1 as the clock

input for setup and hold input.

TRIGGER: A: SETHOLD: CLOCK: SOURCE? might return: TRIGGER: A: SETHOLD: CLOCK: SOURCE CH4 indicating that channel 4 is the clock source for the setup

and hold trigger input.

### TRIGger: A: SETHold: CLOCk: THReshold

Sets or returns the clock voltage threshold for the setup and hold trigger.

**Group** Trigger

Syntax TRIGger:A:SETHold:CLOCk:THReshold {<NR3>|TTL|ECL}

TRIGger:A:SETHold:CLOCk:THReshold?

**Arguments** TTL specifies a preset TTL high level of 1.4 V.

ECL specifies a preset ECL high level of -1.3 V.

<NR3> is the clock level, in volts.

**Examples** TRIGGER: A: SETHOLD: CLOCK: THRESHOLD TTL specifies the preset TTL value

of 1.4 V as the clock threshold for the setup and hold trigger.

TRIGGER: A: SETHOLD: CLOCK: THRESHOLD? might return

:TRIGGER:A:LOGIC:SETHOLD:CLOCK:THRESHOLD 1.2000E+00 indicating that the clock threshold for the setup and hold trigger is 1.2 V.

## TRIGger: A: SETHold: DATa? (Query Only)

Returns the voltage threshold and data source for the setup and hold trigger.

**Group** Trigger

**Syntax** TRIGger:A:SETHold:DATa?

**Related Commands** TRIGger:A:SETHold:CLOCk?

**Examples** TRIGGER: A: SETHOLD: DATA? might return

:TRIGGER:A:SETHOLD:DATA:SOURCE CH2;THRESHOLD 80.0000E-3

## TRIGger: A: SETHold: DATa: SOUrce

Sets or returns the data source for the setup and hold trigger. You cannot specify

the same source for both clock and data.

For DPO models, you can specify only a single data source. Data sources for

DPO models may be one of CH1-CH4 or D0-D15.

**Group** Trigger

**Syntax** DPO Models:

TRIGger:A:SETHold:DATa:SOurce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

TRIGger: A: SETHold: DATa: SOurce?

Related Commands TRIGger: A:SETHold: CLOCk: SOUrce

**Arguments** DPO Models:

<wfm> specifies the source channel number and is one of CH1–CH4, and

D0-D15. You can specify only one waveform on a DPO.

**Examples** TRIGGER: A: SETHOLD: DATA: SOURCE CH1 sets channel 1 as the clock source

for the setup and hold trigger.

TRIGGER: A: SETHOLD: DATA: SOURCE? might return

:TRIGGER:A:LOGIC:SETHOLD:DATA:SOURCE CH2 indicating that channel 2 is

the current clock source for the setup and hold trigger.

## TRIGger: A: SETHold: DATa: THReshold

Sets or returns the data voltage threshold for setup and hold trigger. The digital channels do not have independent trigger levels. Channels D0–D7 share one common trigger level and D8–D15 share another common trigger level. For example changing the trigger level for D3 changes the levels for D0–D7.

**Group** Trigger

Syntax TRIGger:A:SETHold:DATa:THReshold {<NR3>|TTL|ECL}

TRIGger:A:SETHold:DATa:THReshold?

**Arguments** TTL specifies the preset TTL high level of 1.4 V.

ECL specifies the preset ECL high level of -1.3 V.

<NR3> is the setup and hold data level, in V.

**Examples** TRIGGER: A: SETHOLD: DATA: THRESHOLD TTL specifies the preset high level of

1.4 V as the current data voltage level for the setup and hold trigger.

TRIGGER: A: SETHOLD: DATA: THRESHOLD? might return

:TRIGGER:A:SETHOLD:DATA:THRESHOLD 1.2000E+00 indicating that 1.2 V is the current data voltage level for the setup and hold trigger.

## TRIGger:A:SETHold:HOLDTime

Sets or returns the hold time for setup and hold violation triggering.

**Group** Trigger

Syntax TRIGger:A:SETHold:HOLDTime <NR3>

TRIGger: A: SETHold: HOLDTime?

**Arguments** <NR3> specifies the hold time setting in seconds. Positive values for hold time

occur after the clock edge. Negative values occur before the clock edge.

**Examples** TRIGGER: A: SETHOLD: HOLDTIME 3.0E-3 sets the hold time for the setup and

hold trigger to 3 ms.

TRIGGER: A: SETHOLD: HOLDTIME? might return

:TRIGGER:A:SETHOLD:HOLDTIME 2.0000E-09 indicating that the current

hold time for the setup and hold trigger is 2 ns.

### TRIGger: A: SETHold: SETTime

Sets or returns the setup time for setup and hold violation triggering.

**Group** Trigger

Syntax TRIGger:A:SETHold:SETTime <NR3>

TRIGger:A:SETHold:SETTime?

**Arguments** <NR3> specifies the setup time for setup and hold violation triggering.

**Examples** TRIGGER:A:SETHOLD:SETTIME 3.0E-6 specifies that the current setup time for

setup and hold trigger is 3 μs.

TRIGGER: A: SETHOLD: SETTIME? might return

:TRIGGER:A:LOGIC:SETHOLD:SETTIME 2.0000E-09 indicating that the

current setup time for setup and hold trigger is 2 ns.

## TRIGger:A:SETHold:THReshold:CH<x>

Sets or queries the threshold for the channel specified by x. Affects all trigger

types using the channel.

Syntax TRIGger:A:SETHold:THReshold:CH<x> {<NR3>|ECL|TTL}

TRIGger:A:SETHold:THReshold:CH<x>?

**Arguments** <NR3> specifies the threshold voltage, in volts.

ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

**Examples** TRIGGER: A: SETHOLD: THRESHOLD: CH1 1.5 sets the channel 1 threshold

to 1.5 volts.

TRIGGER:A:SETHOLD:THRESHOLD:CH1? might return

TRIGGER: A: SETHOLD: THRESHOLD: CH1 0.0E+0 indicating that the

channel 1 threshold is set to 0.0 volts.

## TRIGger:A:SETHold:THReshold:D<x>

Sets the Threshold for the Selected Digital Channel. Affects all trigger types

using the Digital Channel.

Group MSO

Syntax TRIGger:A:SETHold:THReshold:D<x> {<NR3>|ECL|TTL}

TRIGger:A:SETHold:THReshold:D<x>?

**Arguments** <NR3> specifies the threshold voltage, in volts.

ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

**Examples** TRIGGER:A:SETHOLD:THRESHOLD:D1 ECL sets the threshold to ECL levels.

TRIGGER: A: SETHOLD: THRESHOLD: D1? might return

TRIGGER: A: SETHOLD: THRESHOLD: D1 -1.3000 indicating that the

threshold is set to -1.3 volts.

# TRIGger:A{:TRANsition|:RISEFall}? (Query Only)

Returns transition time trigger parameters.

Syntax TRIGger:A{:TRANsition|:RISEFall}?

**Related Commands** TRIGger:A:UPPerthreshold:CH<x>, TRIGger:A:LOWerthreshold:CH<x>

**Examples** TRIGGER:A::TRAnsITION? might return

:TRIGGER:A:TRANSITION:POLARITY POSITIVE;WHEN

SLOWER; DELTATIME 8.0000E-9

## TRIGger:A{:TRANsition|:RISEFall}:DELTatime

Sets or returns the delta time used in calculating the transition value for the transition trigger.

Trigger

Group

Syntax TRIGger:A{:TRANsition|:RISEFall}:DELTatime <NR3>

TRIGger: A{:TRANsition|:RISEFall}:DELTatime?

**Arguments** <NR3> specifies the delta time, in seconds.

**Examples** TRIGGER: A:TRANSITION: DELTATIME 15E-6 sets the delta time of the

transition trigger to 15 µs.

TRIGGER: A: TRANSITION: DELTATIME? might return: TRIGGER: A

:TRANSITION:DELTATIME 2.0000E-09 indicating that the delta time of the

transition trigger is set to 2 ns.

## TRIGger:A{:TRANsition|:RISEFall}:POLarity

Sets or returns the polarity for the transition trigger.

**Group** Trigger

Syntax TRIGger:A{:TRANsition|:RISEFall}:POLarity

{EITher|NEGative|POSitive}

TRIGger:A{:TRANsition|:RISEFall}:POLarity?

**Arguments** POSitive indicates that a pulse edge must traverse from the lower (most

negative) to higher (most positive) level for transition triggering to occur.

NEGative indicates that a pulse edge must traverse from the upper (most positive) to lower (most negative) level for transition triggering to occur.

EITher indicates either positive or negative polarity.

**Examples** 

TRIGGER: A: TRANSITION: POLARITY NEGATIVE sets the transition polarity to negative.

TRIGGER:A:TRANSITION:POLARITY? might return :TRIGGER:A:
TRANSITION:POLARITY EITHER indicating that the polarity can be either

positive or negative.

## TRIGger:A{:TRANsition|:RISEFall}:SOUrce

Sets or returns the source for transition trigger.

**Group** Trigger

Syntax TRIGger:A{:TRANsition|:RISEFall}:SOUrce {CH1|CH2|CH3|CH4|

D0|D1|D2|D3|D4|D5|D6|D7|D8|D9|D10|D11|D12|D13|D14|D15}

TRIGger:A{:TRANsition|:RISEFall}:SOurce?

**Arguments** CH1–CH4 specifies one of the input channels.

D0-D15 specifies one of the input digital channels.

**Examples** TRIGGER:A:TRANSITION:SOURCE CH4 sets channel 4 as the source for the

transition trigger.

TRIGGER:A:TRANSITION:SOURCE? might return:TRIGGER:A:TRANSITION:SOURCE CH2 indicating that channel 2 is the source for the A transition trigger.

## TRIGger:A{:TRANsition|:RISEFall}:WHEn

Sets or returns whether to check for a transitioning signal that is faster or slower than the specified delta time.

**Group** Trigger

**Syntax** TRIGger:A{:TRANsition|:RISEFall}:WHEn

{SLOWer|FASTer|EQual|UNEQual}

TRIGger:A{:TRANsition|:RISEFall}:WHEn?

#### **Arguments**

FASTer sets the trigger to occur when the signal transition time is faster than the time set by TRIGGER:A{TRAnsition|:RISEFall}:DELTatime.

SLOWer sets the trigger to occur when the signal transition time is slower than the time set by.TRIGGer:A{TRAnsition|:RISEFall}:DELTatime.

EQual sets the trigger to occur when the signal transition time is equal to the time set by TRIGGer:A{TRAnsition|:RISEFall}:DELTatime.

UNEQual sets the trigger to occur when the signal transition time is not equal to the time set by TRIGGer:A{TRAnsition|:RISEFall}:DELTatime.

### **Examples**

TRIGGER:A:TRANSITION:WHEN SLOWER sets the trigger to occur when the signal transition time is slower than the time set by.TRIGGEr:A{TRANSITION|:RISEFall}:DELTatime.

TRIGGER:A:TRANSITION:WHEN? might return :TRIGGER:A:TRANSITION: WHEN FASTER

### TRIGger:A:TYPe

Sets or returns the type of A trigger. The five types of triggers are of Edge, Logic, Pulse, Serial, and Video. Logic and Pulse triggers contain classes. Logic triggers consist of State, Pattern, and SetHold classes; Pulse triggers consist of Runt, Width, and Transition logic classes. Once you have set the trigger type, you may also need to identify the associated trigger class. For details on selecting Logic and Pulse trigger classes, see TRIGger:A:LOGIc:CLAss and TRIGger:A:PULse:CLAss respectively.

#### **Group** Trigger

oup 11155C

#### **Syntax**

TRIGger:A:TYPe {EDGe|LOGic|PULSe|BUS|VIDeo}

TRIGger:A:TYPe?

#### **Related Commands**

TRIGger: A:EDGE?, TRIGger: A:LOGIc:CLAss, TRIGger: A:PULse:CLAss

#### Arguments

EDGe is a normal trigger. A trigger event occurs when a signal passes through a specified voltage level in a specified direction and is controlled by the TRIGger:A:EDGE? commands.

LOGic specifies that a trigger occurs when specified conditions are met and is controlled by the TRIGger:A:LOGIc? commands.

PULSe specifies that a trigger occurs when a specified pulse is found and is controlled by the TRIGger:A:PULse? commands.

BUS specifies that a trigger occurs when a communications signal is found.

Supports CAN, I<sup>2</sup>C, SPI, and RS232 communications signals.

VIDeo specifies that the trigger occurs when a video signal is found.

**Examples** TRIGGER:A:TYPE EDGE sets the A trigger type to EDGE.

TRIGGER: A: TYPE? might return: TRIGGER: A: TYPE PULSE indicating that the

A trigger type is a pulse trigger.

## TRIGger:A:UPPerthreshold:CH<x>

Sets the upper threshold for channel <x>, where x is the channel number. Each channel can have an independent level. Used only for runt and slew rate trigger types.

**Group** Trigger

Syntax TRIGger:A:UPPerthreshold:CH<x> {<NR3>|ECL|TTL}

TRIGger:A:UPPerthreshold:CH<x>?

**Arguments** <NR3> is the threshold level in volts.

ECL specifies a preset ECL high level of -1.3 V.

TTL specifies a preset TTL high level of 1.4 V.

**Examples** TRIGGER:A:UPPERTHRESHOLD:CH2 50E-3 sets the upper limit of the pulse

runt trigger to 50 mV for channel 2.

TRIGGER: A: UPPERTHRESHOLD: CH2? might return: TRIGGER: A:

UPPERTHRESHOLD: CH2 1.2000E-01 indicating that the upper limit of the pulse

runt trigger is set to 120 mV.

## TRIGger:A:VIDeo? (Query Only)

Returns the A trigger video parameters.

**Group** Trigger

Syntax TRIGger:A:VIDeo?

**Examples** TRIGGER:A:VIDEO? might return :TRIGGER:A:VIDEO:POLARITY

POSITIVE; SOURCE CH1; STANDARD NTSC; SYNC

ALLLINES; HOLDOFF: FIELD 0.0000; :TRIGGER: A: VIDEO: CUSTOM: FORMAT PROGRESSIVE; SCANRATE 15K; :TRIGGER: A: VIDEO: LINE 1; HDTV: FORMAT

HD1080I60

## TRIGger: A: VIDeo: HOLDoff: FIELD

Sets or returns the video trigger holdoff in terms of video fields.

**Conditions** This command requires a DPO2VID application module.

**Group** Trigger

Syntax TRIGger:A:VIDeo:HOLDoff:FIELD <NR3>

TRIGger:A:VIDeo:HOLDoff:FIELD?

**Arguments** <NR3> argument is a real number from 0.0 to 8.5 in increments of 0.5. The

argument sets the number of fields that the oscilloscope waits before rearming

the video trigger.

**Examples** TRIGGER:A:VIDEO:HOLDOFF:FIELD? might return

:TRIGGER:A:VIDEO:HOLDOFF:FIELD 5 indicating that the oscilloscope is set

to wait 5 video fields before rearming the trigger.

TRIGGER: A: VIDEO: HOLDOFF: FIELD 4.5 sets the oscilloscope to wait 4.5 video

fields before rearming the trigger.

## TRIGger: A: VIDeo: LINE

Sets or returns the video line number on which the oscilloscope triggers. Use the TRIGger:A:VIDeo{:SYNC|:FIELD} command to actually trigger the oscilloscope

on the line that you specify with this command.

**Conditions** This command requires a DPO2VID application module.

**Group** Trigger

Syntax TRIGger:A:VIDeo:LINE <NR1>

TRIGger: A: VIDeo: LINE?

### Related Commands TRIGger: A: VIDeo {:SYNC|:FIELD}

#### **Arguments**

<NR1> argument is an integer that sets the video line number on which the oscilloscope triggers. The following table lists the valid choices, depending on the active video standard.

**Table 2-41: Video Line Numbering Ranges** 

Video Standard	Line Number Range
525/NTSC	1–525
625/PAL, SECAM	1–625
SECAM	1–625

#### **Examples**

TRIGGER: A: VIDEO: LINE 23 sets the oscilloscope to trigger on the line 23.

TRIGGER:A:VIDEO:LINE? might return:TRIGGER:A:VIDEO:LINE 10 indicating that the oscilloscope is set to trigger on line 10.

## TRIGger: A: VIDeo: POLarity

Sets or returns the polarity of the A video trigger.

#### **Conditions**

This command requires a DPO2VID application module.

### Group

Trigger

### **Syntax**

TRIGger:A:VIDeo:POLarity {NEGative|POSitive|NORMal|INVERTed} TRIGger:A:VIDeo:POLarity?

#### TRIEGET TATTE OF

### **Arguments**

POSitive argument sets the oscilloscope to trigger on a positive video sync pulse.

**NEGative** argument sets the oscilloscope to trigger on a negative video sync pulse.

### **Examples**

TRIGGER: A: VIDEO: POLARITY NEGATIVE sets the oscilloscope to trigger on a negative video pulse.

TRIGGER:A:VIDEO:POLARITY? might return:TRIGGER:A:VIDEO:POLARITY POSITIVE indicating that the oscilloscope is set to trigger on a positive video sync pulse.

## TRIGger: A: VIDeo: SOUrce

Sets or returns the source for the A video trigger.

**Group** Trigger

Syntax TRIGger:A:VIDeo:SOUrce {CH1|CH2|CH3|CH4}

TRIGger:A:VIDeo:SOUrce?

**Arguments** CH1-CH4 specifies the input channel to use as the A video trigger.

D0-D15 specifies the input channel to use as the A video trigger.

**Examples** TRIGGER:A:VIDEO:SOURCE CH1 sets the source for A video trigger to Channel 1.

TRIGGER: A: VIDEO: SOURCE? might return: TRIGGER: A: VIDEO: SOURCE CH2

indicating that the source for the A video trigger is set to Channel 2.

## TRIGger: A: VIDeo: STANdard

Sets or returns the standard for the video trigger.

**Group** Trigger

Syntax TRIGger:A:VIDeo:STANdard {NTSc|PAL|SECAM}

TRIGger: A: VIDeo: STANdard?

**Arguments** NTSc sets the oscilloscope to trigger on video signals that meet the NTSC

525/60/2:1 standard (a line rate of 525 lines per frame and a field rate of 60 Hz).

PAL sets the oscilloscope to trigger on video signals that meet the NTSC 625/50/2:1 standard (a line rate of 625 lines per frame and a field rate of 50 Hz).

SECAM sets the oscilloscope to trigger on video signals that meet the SECAM

standard.

**Examples** TRIGGER: A: VIDEO: STANDARD NTSC sets the oscilloscope to trigger on

NTSC-standard video signals.

TRIGGER: A: VIDEO: STANDARD? might return: TRIGGER: A: VIDEO: STANDARD

HDTV indicating that the oscilloscope is set to trigger on an HDTV format.

## TRIGger:A:VIDeo{:SYNC|:FIELD}

Sets or returns the video field or line that the trigger detects.

**Group** Trigger

Syntax TRIGger:A:VIDeo{:SYNC|:FIELD}

{ODD|EVEN|ALLFields|ALLLines|NUMERic}

TRIGger:A:VIDeo{:SYNC|:FIELD}?

**Arguments** ODD argument sets the oscilloscope to trigger on interlaced video odd fields.

EVEN argument sets the oscilloscope to trigger on interlaced video even fields.

ALLFields argument sets the oscilloscope to trigger on all fields.

ALLLines argument sets the oscilloscope to trigger on all video lines.

NUMERic argument sets the oscilloscope to trigger on the video signal line

specified by the TRIGger:A:VIDeo:LINE command.

**Examples** TRIGGER: A: VIDEO: FIELD EVEN sets the A video trigger so that it will trigger

on even fields.

TRIGGER:A:VIDEO:FIELD? might return :TRIGGER:A:VIDEO:FIELD ALLFIELDS indicating that the A video will trigger on all video fields.

## TRIGger:EXTernal? (Query Only)

Returns all external trigger parameters.

**Group** Trigger

**Syntax** TRIGger:EXTernal?

### TRIGger:EXTernal:PRObe

Sets or returns the attenuation factor value of the external probe connector.

Syntax TRIGger:EXTernal:PRObe <NR3>

TRIGger: EXTernal: PRObe?

**Arguments** <NR3> is the attenuation factor of the probe.

**Examples** TRIGGER: EXTERNAL: PROBE? might return: TRIGGER: EXTERNAL: PROBE

1.0E1 for a 10X probe.

## TRIGger:EXTernal:YUNIts? (Query Only)

Returns the external trigger vertical (Y) units value.

**Group** Trigger

**Syntax** TRIGger:EXTernal:YUNIts?

**Examples** TRIGGER: EXTERNAL: YUNITS? might return TRIGGER: EXTERNAL: YUNITS

"V" if the vertical unit is volts.

## TRIGger:FREQuency? (Query Only)

Returns the available trigger frequency in hertz. If the trigger frequency is not currently available, the IEEE Not A Number (NaN = 9.9100E+37) value is returned. The maximum precision of the returned frequency is 6 digits.

**Group** Trigger

**Syntax** TRIGger: FREQuency?

## TRIGger:STATE? (Query Only)

Returns the current state of the triggering system.

**Group** Trigger

**Syntax** TRIGger:STATE?

Related Commands TRIGger:A:MODe

**Returns** ARMED indicates that the oscilloscope is acquiring pretrigger information.

AUTO indicates that the oscilloscope is in the automatic mode and acquires data

even in the absence of a trigger.

READY indicates that all pretrigger information has been acquired and that the

oscilloscope is ready to accept a trigger.

SAVE indicates that the oscilloscope is in save mode and is not acquiring data.

TRIGGER indicates that the oscilloscope triggered and is acquiring the post trigger

information.

**Examples** TRIGGER: STATE? might return: TRIGGER: STATE ARMED indicating that the

pretrigger data is being acquired.

\*TST? (Query Only)

Tests (self-test) the interface and returns a 0.

**Group** Miscellaneous

Syntax \*TST?

**Examples** \*TST? always returns 0.

**UNLock (No Query Form)** 

Unlocks the front panel. The command is equivalent to LOCk NONe.

**Group** Miscellaneous

Syntax UNLock ALL

Related Commands LOCk

**Arguments** ALL specifies that all front-panel buttons and knobs are unlocked.

**Examples** UNLOCK ALL unlocks all front-panel buttons and knobs.

## **USBDevice:CONFigure**

Enables or disables the rear USB port for use with Pictbridge printers.

**Group** PictBridge

Syntax USBDevice:CONFigure {DISabled|IMAge|USBTmc}

USBDevice:CONFigure?

**Arguments** DISabled disables the rear USB port.

IMAge enables the rear USB port as an SIC device.

USBTmc enables the rear USB port as a USBTMC device.

**Examples** USBDEVICE:CONFIGURE? might return USBDEVICE:CONFIGURE USBTMC

indicating a USBTMC device.

USBDEVICE: CONFIGURE IMAGE enables the rear USB port as an SIC device

**USBTMC** 

Returns the USBTMC information used by the USB hosts to determine the

instrument interfaces.

**Group** Misc

Syntax USBTMC?

## **USBTMC:PRODUCTID:DECimal? (Query Only)**

Returns the product ID of the USBTMC device in decimal format.

**Group** Misc

**Syntax** USBTMC:PRODUCTID:DECimal?

**Examples** USBTMC:PRODUCTID:DECIMAL? might return USBTMC:PRODUCTID:DECIMAL

882 indicating that the product ID is 882 in decimal format.

# **USBTMC:PRODUCTID:HEXadecimal? (Query Only)**

Returns the product ID of the USBTMC device in hexadecimal format.

**Group** Misc

**Syntax** USBTMC:PRODUCTID:HEXadecimal?

**Examples** USBTMC:PRODUCTID:HEXADECIMAL? might return

USBTMC: PRODUCTID: HEXADECIMAL 0x0372 indicating that the product ID in

hexadecimal format is 0x0372.

## **USBTMC:SERIALnumber?** (Query Only)

Returns the serial number of the USBTMC device.

**Group** Misc

Syntax USBTMC: SERIAL number?

**Examples** USBTMC:SERIALNUMBER? might return USBTMC:SERAILNUMBER NO\_SERIAL

indicating that there is no serial number for the instrument.

## **USBTMC:VENDORID:DECimal?** (Query Only)

Returns the vendor ID of the USBTMC device in decimal format.

**Group** Misc

**Syntax** USBTMC: VENDORID: DECimal?

Examples USBTMC: VENDORID: DECIMAL? might return USBTMC: VENDORID: DECIMAL

1689 indicating that 1689 is the Vendor ID in decimal format.

## **USBTMC:VENDORID:HEXadecimal? (Query Only)**

Returns the vendor ID of the USBTMC device in hexadecimal format.

Group Misc

**Syntax** USBTMC: VENDORID: HEXadecimal?

**Examples** USBTMC:VENDORID:HEXADECIMAL? might return

USBTMC: VENDORID: HEXADECIMAL 0x0699 indicating that 0x0689 is the

Vendor ID in hexadecimal format.

### **VERBose**

Sets or returns the Verbose state that controls the length of keywords on query responses. Keywords can be both headers and arguments.

**NOTE.** This command does not affect IEEE Std 488.2-1987 Common Commands (those starting with an asterisk). This command does affects the verbose state of both the USBTMC and VXI-11 interfaces. Refer to the Introduction for information.

**Group** Miscellaneous

Syntax VERBose {OFF|ON|<NR1>}

Related Commands HEADer, \*LRN?, SET?

**Arguments** OFF sets the Verbose state to false, which returns minimum-length keywords

for applicable setting queries.

ON sets the Verbose state to true, which returns full-length keywords for applicable

setting queries.

<NR1> a 0 returns minimum-length keywords for applicable setting queries; any

other value returns full-length keywords.

**Examples** VERBOSE ON enables the Verbose state.

VERBOSE? might return: VERB 0 indicating that the Verbose state is disabled.

## \*WAI (No Query Form)

Prevents the oscilloscope from executing further commands or queries until all pending commands that generate an OPC message are complete. This command allows you to synchronize the operation of the oscilloscope with your application program.

**Group** Status and Error

Syntax \*WAI

**Related Commands** BUSY?, \*OPC

**Examples** See the section titled "Using the \*WAI Command" for an example of how to

use this command.

## WAVFrm? (Query Only)

Returns WFMOutpre? and CURVe? data for the waveform as specified by the DATA:SOUrce command. This command is equivalent to sending both WFMOutpre? and CURVe?, with the additional provision that the response to WAVFrm? is guaranteed to provide a synchronized preamble and curve. The source waveform, as specified by :DATA:SOURCE, must be active or the query will not return any data and will generate an error indicator.

**NOTE.** For MSO models, reduced resolution waveform data is not available for the digital channels.

**Group** Waveform Transfer

Syntax WAVFrm?

Related Commands CURVe, DATa:SOUrce, WFMOutpre?

**Examples** WAVFRM? might return the waveform data as: :WFMOUTPRE:BYT\_NR

1;BIT\_NR 8;ENCDG ASCII;BN\_FMT RI;BYT\_OR MSB;WFID

"Ch1, DC coupling, 100.0mV/div, 4.000us/div,

10000 points, Sample mode"; NR\_PT 20; PT\_FMT Y; XUNIT "s"; XINCR 4.0000E-9; XZERO -20.0000E-6; PT\_OFF 0; YUNIT

"V"; YMULT 4.0000E-3; YOFF 0.0000; YZERO 0.0000; :CURVE 2,1,4,2,4,3,0,3,3,3,3,3,3,4,3,5,6,6,7,3

# WFMInpre? (Query Only)

Returns the waveform formatting and scaling specifications to be applied to the next incoming CURVe command data.

**Group** Waveform Transfer

Syntax WFMInpre?

Related Commands WFMOutpre?

**Examples** WFMINPRE? might return the waveform formatting as :WFMINPRE:BIT\_NR

8;BN\_FMT RI;BYT\_NR 1; BYT\_OR MSB;ENCDG BIN;NR\_PT 500;PT\_FMT Y; PT\_OFF 0;XINCR 2.0000E-6;XZERO 1.7536E-6; XUNIT "s";YMULT

1.0000E-3; YOFF 0.0000; YZERO 0.0000; YUNIT "V"

#### WFMInpre:BIT\_Nr

Sets or returns the number of bits per binary waveform point for the incoming waveform. Changing the value of WFMInpre:BIT\_Nr also changes the value of WFMInpre:DNT\_Nr

WFMInpre:BYT Nr.

**Group** Waveform Transfer

Syntax WFMInpre:BIT\_Nr <NR1>

WFMInpre:BIT\_Nr?

Related Commands WFMInpre:BYT\_Nr

**Arguments** <NR1> number of bits per data point can be 8 or 16.

**Examples** WFMINPRE:BIT\_NR 16 sets the number of bits per waveform point to 16, for

incoming data.

WFMINPRE:BIT\_NR? might return: WFMINPRE:BIT\_NR 8 indicating that

incoming waveform data uses 8 bits per waveform point.

### WFMInpre:BN\_Fmt

Sets or returns the format of binary data for incoming waveforms.

**Group** Waveform Transfer

Syntax WFMInpre:BN\_Fmt {RI|RP}

WFMInpre:BN\_Fmt?

Related Commands WFMOutpre:BN Fmt

**Arguments** RI specifies signed integer data point representation.

RP specifies positive integer data point representation.

**Examples** WFMINPRE:BN\_FMT RP specifies positive integer data point representation.

WFMINPRE:BN\_FMT? might return: WFMINPRE:BN\_FMT RI indicating that the

incoming data is currently interpreted as signed integers.

WFMInpre:BYT\_Nr

Sets or returns the data width for the incoming waveform. Changing the value of

WFMInpre:BYT Nr also changes the value of WFMInpre:BIT Nr.

**Group** Waveform Transfer

Syntax WFMInpre:BYT\_Nr <NR1>

WFMInpre:BYT\_Nr?

Related Commands WFMInpre:BIT\_Nr

**Arguments** <NR1> is the number of bytes per data point and can be 1 or 2.

**Examples** WFMINPRE: BYT\_NR 1 sets the number of bytes per incoming waveform data

point to 1, which is the default setting.

WFMINPRE:BYT\_NR? might return: WFMINPRE:BYT\_NR 2 indicating that there

are 2 bytes per incoming waveform data point.

## WFMInpre:BYT\_Or

Sets or returns which byte of binary waveform data is expected first for incoming waveform data when data points require than one byte. This specification only has meaning when WFMInpre:ENCdg is set to BIN and WFMInpre:BYT Nr is 2.

**Group** Waveform Transfer

Syntax WFMInpre:BYT\_Or {LSB|MSB}

WFMInpre:BYT\_Or?

Related Commands WFMInpre:ENCdg, WFMInpre:BYT\_Nr, WFMInpre:FILTERFreq

**Arguments** LSB specifies that the least significant byte will be expected first.

MSB specifies that the most significant byte will be expected first.

**Examples** WFMINPRE:BYT\_OR MSB sets the most significant incoming byte of incoming

waveform data to be expected first.

WFMINPRE:BYT\_OR? might return: WFMINPRE:BYT\_OR LSB indicating that the

least significant incoming CURVe data byte will be expected first.

# WFMInpre:COMPosition

Sets and queries the type of waveform data to be transferred to the instrument with

the CURVe command.

**Group** Waveform Transfer

**Syntax** WFMInpre:COMPosition

{COMPOSITE\_YT|COMPOSITE\_ENV|SINGULAR\_YT}

WFMInpre:COMPosition?

Related Commands DATa: COMPosition

**Arguments** COMPOSITE\_YT uses the sample part of the composite waveform.

COMPOSITE\_ENV uses the peak-detect part of the composite waveform.

SINGULAR\_YT uses the sample part of the singular waveform.

**Examples** WFMINPRE:COMPOSITION? might return:WFMINPRE:COMPOSITION

SINGULAR\_YT indicating that the sample part of singular waveform is transferred

to the instrument.

WFMINPRE: COMPOSITIONCOMPOSITE\_YT sets the sample part of composite

waveform to be transferred to the instrument.

#### WFMInpre: ENCdg

Sets or returns the type of encoding for incoming waveform data.

**Group** Waveform Transfer

**Syntax** WFMInpre:ENCdg {ASCii|BINary}

WFMInpre: ENCdg?

Related Commands WFMOutpre:ENCdg

**Arguments** ASCii specifies that the incoming data is in ASCII format.

BINary specifies that the incoming data is in a binary format whose further interpretation requires knowledge of BYT\_NR, BIT\_NR, BN\_FMT, and

BYT\_OR.

**Examples** WFMINPRE: ENCDG ASC sets the format of incoming waveform data to ASCII

format.

WFMINPRE: ENCDG? might return: WFMINPRE: ENCDG BIN indicating that the

incoming waveform data is in binary format.

# WFMInpre:FILTERFreq

Specifies or returns the FilterVu low pass filter frequency, which was applied to

the waveform being sent to the instrument.

**Group** Waveform Transfer

Syntax WFMInpre:FILTERFreq {NR1}

WFMInpre:FILTERFreq?

**Arguments** <NR1> is an signed integer.

**Examples** 

WFMINPRE: FILTERFREQ? might return: WFMINPRE: FILTERFREQ 200000000

indicating that the FilterVu frequency for the incoming waveform is 200 MHz.

WFMINPRE: FILTERFREQ 3000000000 sets the FilterVu frequency for the

incoming waveform to 300 MHz.

# WFMInpre:NR\_Pt

Sets or returns the number of data points that are in the incoming waveform record.

Waveform Transfer Group

**Syntax** WFMInpre:NR\_Pt <NR1>

WFMInpre:NR\_Pt?

**Related Commands** CURVe, DATa, DATa:STARt, DATa:STOP, SAVe:WAVEform,

SAVe: WAVEform: FILEFormat, WFMOutpre: NR Pt?

**Arguments** <NR1> is the number of data points if WFMInpre:PT Fmt is set to Y. It is the

number of min-max pairs if WFMInpre:PT Fmt is set to ENV.

**Examples** WFMINPRE: NR\_PT 10000 specifies that 10000 data points will be expected.

> WFMINPRE:NR\_PT ? might return :WFMINPRE:NR\_PT 10000 indicating that there are 10000 data points in the expected incoming waveform record.

WFMInpre:PT Fmt

Sets or returns the point format of the incoming waveform data. Regardless of the argument used, the scale, offset, and so on are interpreted similarly. When ENV is used, waveform data is interpreted over the min-max pair; when Y is

used, it is interpreted over a single point.

Waveform Transfer Group

**Syntax** WFMInpre:PT\_Fmt {ENV|Y}

WFMInpre:PT\_Fmt?

**Related Commands** WFMOutpre:PT Fmt?

#### **Arguments**

ENV specifies that the waveform is transmitted in envelope mode as maximum and minimum point pairs. Only Y values are explicitly transmitted. Absolute coordinates are given by:

$$Xn = XZEro + XINcr (n - PT\_Off)$$

$$Ynmax = YZEro + YMUlt (ynmax - YOFf)$$

$$Ynmin = YZEro + YMUlt (ynmin - YOFf)$$

Y specifies a normal waveform where one ASCII or binary data point is transmitted for each point in the waveform record. Only Y values are explicitly transmitted. Absolute coordinates are given by:

$$Xn = XZEro + XINcr (n - PT Off)$$

$$Yn = YZEro + YMUlt (yn - YOFf)$$

#### **Examples**

WFMINPRE: PT\_FMT ENV sets the incoming waveform data point format to enveloped.

WFMINPRE: PT\_FMT? might return: WFMINPRE: PT\_FMT ENV indicating that the waveform is transmitted as maximum and minimum point pairs.

# WFMInpre:PT\_Off

The set form of this command is ignored. The query form always returns a 0. This command is listed for compatibility with other Tektronix oscilloscopes.

**Group** Waveform Transfer

Syntax WFMInpre:PT\_Off <NR1>
 WFMInpre:PT\_Off?

**Arguments** Arguments are ignored.

# WFMInpre:XINcr

Sets or returns the horizontal interval between incoming waveform points in units specified by WFMInpre:XUNit.

**Group** Waveform Transfer

Syntax WFMInpre:XINcr <NR3>

WFMInpre:XINcr?

Related Commands WFMInpre:XUNit, WFMOutpre:XINcr?

**Arguments** <NR3> is the horizontal interval representation.

**Examples** WFMINPRE:XINCR 3E-3 sets the interval between incoming waveform points

to 3 ms.

WFMINPRE:XINCR ? might return :WFMINPRE:XINCR 1.0000E-3 indicating that if WFMInpre:XUNit is set to "s", there is a 1 ms interval between incoming

waveform points.

WFMInpre:XUNit

Sets or returns the horizontal units of the incoming waveform.

Supported units are:

%, /Hz, A, A/A, A/V, A/W, A/dB, A/s, AA, AW, AdB, As, B, Hz, IRE, S/s, V, V/A, V/V, V/W, V/dB, V/s, VV, VW, VdB, Volts, Vs, W, W/A, W/V, W/W, W/dB, W/s, WA, WV, WW, WdB, Ws, dB, dB/A, dB/V, dB/W, dB/dB, dBA, dBV, dBW,

dBdB, day, degrees, div, hr, min, ohms, percent, s

**Group** Waveform Transfer

Syntax WFMInpre:XUNit <QString>

WFMInpre:XUNit?

Related Commands WFMOutpre:XUNit?

**Arguments** <QString> contains a maximum of three alpha characters that represent the

horizontal unit of measure for the incoming waveform.

**Examples** WFMINPRE:XUNIT "HZ" specifies that the horizontal units for the incoming

waveform are hertz.

WFMINPRE:XUNIT? might return: WFMINPRE:XUNIT "s" indicating that the

horizontal units for the incoming waveform are seconds.

# WFMInpre:XZEro

Sets or returns the position value, in XUNits, of the first sample of the incoming

waveform.

**Group** Waveform Transfer

Syntax WFMInpre:XZEro <NR3>

WFMInpre:XZEro?

**Related Commands** WFMInpre:XINcr, WFMInpre:XUNit, WFMOutpre:XZEro?

**Arguments** <NR3> argument is the floating point value of the position, in XUNits, of the first

sample in the incoming waveform. If XUNits is "s", <NR3> is the time of the

first sample in the incoming waveform.

**Examples** WFMINPRE: XZERO 5.7E-6, which indicates the trigger occurred 5.7 μs before the

first sample in the waveform.

WFMINPRE:XZERO? might return:WFMINPRE:XZEro -7.5000E-6 indicating

that the trigger occurs 7.5 µs after the first sample in the waveform.

### WFMInpre:YMUIt

Sets or returns the vertical scale factor of the incoming waveform, expressed in YUNits per waveform data point level. For one byte waveform data, there are 256 data point levels. For two byte waveform data there are 65,536 data point levels.

YMUlt, YOFf, and YZEro are used to convert waveform record values to YUNit values using the following formula (where dl is the data level; curve\_in\_dl is a data point in CURVe):

value in units = ((curve in dl - YOFf in dl) \* YMUlt) + YZEro in units

**NOTE.** For a given waveform record, YMUlt, YOFf, and YZEro have to be a consistent set, otherwise vertical cursor readouts and vertical measurements may give incorrect results.

**Group** Waveform Transfer

Syntax WFMInpre:YMUlt <NR3>

WFMInpre:YMUlt?

Related Commands DATa:DESTination, WFMInpre:BYT\_Nr, WFMInpre:YUNit

**Arguments** <NR3> is the vertical scale factor per digitizing level of the incoming waveform

points.

**Examples** WFMINPRE:YMULT? might return:WFMINPRE:YMULT 40.0000E-3, which (if

YUNit is "V") indicates that the vertical scale is 40 mV/digitizing level (1V/div

for 8-bit data).

WFMINPRE: YMULT 20E-3 specifies that (if WFMInpre: YUNit is "V" and WFMInpre: BYT Nr is 1), the vertical scale is 20 mV/digitizing level

(500 mV/div).

# WFMInpre:YOFf

Sets or returns the vertical position of the incoming waveform in digitizing levels. Variations in this number are analogous to changing the vertical position of the waveform.

YMUlt, YOFf, and YZEro are used to convert waveform record values to YUNit values using the following formula (where dl is the data level; curve\_in\_dl is a data point in CURVe):

value\_in\_units = ((curve\_in\_dl - YOFf\_in\_dl) \* YMUlt) + YZEro\_in\_units

**NOTE.** For a given waveform record, YMUlt, YOFf, and YZEro have to be a consistent set, otherwise vertical cursor readouts and vertical measurements may give incorrect results.

**Group** Waveform Transfer

Syntax WFMInpre:YOFf <NR3>

WFMInpre:YOFf?

Related Commands WFMInpre:BYT Nr, WFMInpre:YMUlt, WFMOutpre:YOFf?

**Arguments** <NR3> is the vertical offset in digitizing levels.

**Examples** WFMINPRE: YOFF 50 specifies that the zero reference point for the incoming

waveform is 50 digitizing levels (2 divisions, for 8-bit data) above the center

of the data range.

WFMINPRE: YOFF? might return: WFMINPRE: YOFF 25 indicating that the vertical position of the incoming waveform in digitizing levels.

#### WFMInpre:YUNit

Sets or returns the vertical units of the incoming waveform.

Supported units are: %, /Hz, A, A/A, A/V, A/W, A/dB, A/s, AA, AW, AdB, As, B, Hz, IRE, S/s, V, V/A, V/V, V/W, V/dB, V/s, VV, VW, VdB, Volts, Vs, W, W/A, W/V, W/W, W/dB, W/s, WA, WV, WW, WdB, Ws, dB, dB/A, dB/V, dB/W, dB/dB, dBA, dBV, dBW, dBdB, day, degrees, div, hr, min, ohms, percent, s

**Group** Waveform Transfer

Syntax WFMInpre:YUNit <QString>

WFMInpre:YUNit?

Related Commands WFMOutpre:YUNit?

**Arguments** <QString> contains a maximum of three alpha characters that represent the

vertical unit of measure for the incoming waveform.

**Examples** WFMINPRE:YUNIT? might return:WFMINPRE:YUNIT "V" indicating that the

vertical units for the incoming waveform are volts.

WFMINPRE: YUNIT "A" specifies that the vertical units for the incoming waveform

are Amperes.

#### WFMInpre:YZEro

Sets or returns the vertical offset of the incoming waveform in units specified by WFMInpre:YUNit. Variations in this number are analogous to changing the vertical offset of the waveform.

YMUlt, YOFf, and YZEro are used to convert waveform record values to YUNit values using the following formula (where dl is the data level; curve\_in\_dl is a data point in CURVe):

value in units = ((curve in dl - YOFf in dl) \* YMUlt) + YZEro in units

**NOTE.** For a given waveform record, YMUlt, YOFf, and YZEro have to be a consistent set, otherwise vertical cursor readouts and vertical measurements may give incorrect results.

**Group** Waveform Transfer

Syntax WFMInpre:YZEro <NR3>

WFMInpre:YZEro?

Related Commands WFMInpre:YUNit, WFMOutpre:YZEro?

**Arguments** <NR3> is the offset in YUNits.

**Examples** WFMINPRE: YZERO 1.5E+0 specifies that the zero reference point for the

incoming waveform is 1.5 V below the center of the data range (given that

WFMInpre:YUNit is set to V).

WFMINPRE:YZERO? might return:WFMINPRE:YZEro 7.5000E-6 indicating that the zero reference for the incoming waveform is 7.5  $\mu$ V below the center of

the data range (given that WFMInpre:YUNit is set to V).

#### WFMOutpre? (Query Only)

Returns waveform transmission and formatting parameters for the waveform specified by DATa:SOUrce command. If the waveform specified by the DATa:SOUrce command is not displayed, the oscilloscope returns only the waveform transmission parameters (BYT\_Nr, BIT\_Nr, ENCdg, BN\_Fmt, BYT\_Or).

For WFMOutpre? queries, first set DATa:RESOlution and DATa:COMPosition appropriately. For MSO/DPO2000 math FFT queries, set them to: DATA:RESOLUTION FULL and DATA:COMPOSITION SINGULAR\_YT.

For more information, see: Appendix B: Waveform Data in DPO/MSO2000 Series Instruments.

(See page 3-1.)

**Group** Waveform Transfer

**Syntax** WFMOutpre?

**Examples** WFMOUTPRE? ? might return the waveform formatting data as:

:WFMOUTPRE:BYT\_NR 2;BIT\_NR 16;ENCDG ASCII;BN\_FMT RI;BYT\_OR MSB;WFID "Ch1, DC coupling, 100.0mV/div, 4.000us/div, 10000 points, Sample mode";NR\_PT 10000;PT\_FMT Y;XUNIT "s";XINCR

4.0000E-9;XZERO - 20.0000E-6;PT\_OFF 0;YUNIT "V";YMULT 15.6250E-6;YOFF : "6.4000E+3;YZERO 0.0000

#### WFMOutpre:BIT\_Nr

Sets and returns the number of bits per waveform point that outgoing waveforms contain, as specified by the DATa:SOUrce command. Changing the value of WFMOutpre:BIT\_Nr also changes the values of WFMInpre:FILTERFreq and DATa:WIDth.

**Group** Waveform Transfer

Syntax WFMOutpre:BIT\_Nr <NR1>
 WFMOutpre:BIT\_Nr?

Related Commands DATa: SOUrce, DATa: WIDth, WFMOutpre: BN Fmt

**Arguments** <NR1> is the number of bits per data point and can be 8 or 16.

**Examples** WFMOUTPRE:BIT\_NR 16 sets the number of bits per waveform point to 16 for

outgoing waveforms.

WFMOUTPRE:BIT\_NR? might return: WFMOUTPRE:BIT\_NR 8 indicating that

outgoing waveforms use 8 bits per waveform point.

WFMOutpre:BN\_Fmt

Sets or returns the format of binary data for outgoing waveforms specified by the DATa: SOUrce command. Changing the value of WFMOutpre: BN Fmt also

changes the value of DATa:ENCdg.

**Group** Waveform Transfer

Syntax WFMOutpre:BN\_Fmt {RI|RP}

WFMOutpre:BN\_Fmt?

Related Commands DATa:ENCdg, DATa:SOUrce

**Arguments** RI specifies signed integer data point representation.

RP specifies positive integer data point representation.

**Examples** WFMOUTPRE: BN\_FMT RP specifies that outgoing waveform data will be in positive

integer format.

WFMOUTPRE:BN\_FMT? might return:WFMOUTPRE:BN\_FMT RI indicating that

the outgoing waveform data is currently in signed integer format.

#### WFMOutpre:BYT\_Nr

Sets or returns the data width for the outgoing waveform specified by the DATa:SOUrce command. Changing WFMOutpre:BYT Nr also changes

WFMOutpre:BIT Nr and DATa:WIDth.

**Group** Waveform Transfer

Syntax WFMOutpre:BYT\_Nr <NR1>

WFMOutpre:BYT\_Nr?

Related Commands DATa: SOUrce, DATa: WIDth, WFMOutpre: BIT Nr

**Arguments** <NR1> is the number of bytes per data point and can be 1 or 2.

**Examples** WFMOUTPRE:BYT\_NR 1 sets the number of bytes per outgoing waveform data

point to 1, which is the default setting.

WFMOUTPRE:BYT\_NR? might return: WFMOUTPRE:BYT\_NR 2 indicating that

there are 2 bytes per outgoing waveform data point.

#### WFMOutpre:BYT\_Or

Sets or returns which byte of binary waveform data is transmitted first, during a waveform data transfer, when data points require than one byte. This specification only has meaning when WFMOutpre:ENCdg is set to BIN and WFMOutpre:BYT\_Nr is 2. Changing WFMInpre:FILTERFreq also changes

DATa:ENCdg (if DATa:ENCdg is not ASCIi).

**Group** Waveform Transfer

**Syntax** WFMOutpre:BYT\_Or {LSB|MSB}

WFMOutpre:BYT\_Or?

Related Commands WFMOutpre:ENCdg, WFMOutpre:BYT\_Nr

**Arguments** LSB specifies that the least significant byte will be transmitted first.

MSB specifies that the most significant byte will be transmitted first.

**Examples** WFMOUTPRE: BYT\_OR MSB sets the most significant outgoing byte of waveform

data to be transmitted first.

WFMOUTPRE:BYT\_OR? might return: WFMOUTPRE:BYT\_OR LSB indicating that

the least significant data byte will be transmitted first.

## WFMOutpre:COMPosition

Controls or indicates the type of data used by the CURVe? query.

**Group** Waveform Transfer

Syntax WFMOutpre:COMPosition

{COMPOSITE\_YT|COMPOSITE\_ENV|SINGULAR\_YT}

WFMOutpre:COMPosition?

**Arguments** COMPOSITE\_YT uses the sample part of the composite waveform.

COMPOSITE\_ENV uses the peak-detect part of the composite waveform.

SINGULAR\_YT uses the sample part of the singular waveform.

**Examples** WFMOUTPRE:COMPOSITION? might return:WFMOUTPRE:COMPOSITION

SINGULAR\_YT indicating that the singular data type is used by the CURVe? query.

WFMOUTPRE: COMPOSITIONCOMPOSITE\_YT sets the data type used by the

**CURVe**? query.

# WFMOutpre: ENCdg

Sets and queries the type of encoding for outgoing waveforms.

**Group** Waveform Transfer

**Syntax** WFMOutpre:ENCdg {ASCii|BINary}

WFMOutpre: ENCdg?

Related Commands DATa:ENCdg, WFMOutpre:BYT Nr, WFMInpre:FILTERFreq,

WFMOutpre:BIT Nr, WFMOutpre:BN Fmt

**Arguments** ASCii specifies that the outgoing data is to be in ASCII format. Waveforms

will be sent as <NR1> numbers.

BINary specifies that outgoing data is to be in a binary format whose further specification is determined by WFMOutpre:BYT Nr, WFMOutpre:BIT Nr,

WFMOutpre:BN\_Fmt and WFMInpre:FILTERFreq.

**Examples** WFMOUTPRE: ENCDG? might return: WFMOUTPRE: ENCDG BIN indicating that

outgoing waveform data will be sent in binary format.

WFMOUTPRE: ENCDG ASC specifies that the outgoing waveform data will be sent

in ASCII format.

# WFMOutpre:FILTERFreq? (Query Only)

Returns the FilterVu low pass filter frequency applied to the LRL waveform record of the source waveform specified by DATa:SOUrce. If the DATa:RESOlution is set to FULL, then this is the filter frequency applied to the full resolution (LRL) waveform. If the DATa:RESOlution is set to REDUced, then this is the filter frequency applied to the reduced resolution (thumbnail) waveform.

**Group** Waveform Transfer

**Syntax** WFMOutpre:FILTERFreq?

**Examples** WFMOUTPRE:FILTERFREQ? might return:WFMOUTPRE:FILTERFREQ

20000000 indicating that the FilterVu frequency for the outgoing waveform

is 200 MHz.

# WFMOutpre:NR\_Pt? (Query Only)

Returns the number of points for the DATa:SOUrce waveform that will be transmitted in response to a CURVe? query. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

**Group** Waveform Transfer

**Syntax** WFMOutpre:NR\_Pt?

Related Commands CURVe, DATa, DATa:STARt, DATa:STOP, SAVe:WAVEform,

SAVe: WAVEform: FILEFormat, WFMInpre: NR Pt

**Examples** WFMOUTPRE:NR\_PT? might return:WFMOUTPRE:NR\_PT 10000 indicating that

there are 10000 data points to be sent.

# WFMOutpre:PT\_Fmt? (Query Only)

Returns the point format for the outgoing waveform specified by the DATa:SOUrce command. Returned values are either ENV, which indicates envelope mode format in which the data is returned as a series of min/max pairs, or Y, which indicates normal waveform points. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

**Group** Waveform Transfer

Syntax WFMOutpre:PT\_Fmt?

Related Commands CURVe, DATa:SOUrce

**Examples** WFMOUTPRE:PT\_FMT? might return:WFMOutpre:PT\_Fmt ENV indicating that

the waveform data is a series of min-max pairs.

### WFMOutpre:PT\_Off? (Query Only)

The set form of this command is ignored. The query form always returns a 0, if the waveform specified by DATA:SOUrce is on or displayed. If the waveform is not displayed, the query form generates an error and returns event code 2244. This command is for compatibility with other Tektronix oscilloscopes.

**Group** Waveform Transfer

**Syntax** WFMOutpre:PT\_Off?

Related Commands DATa:SOUrce

**Arguments** Arguments are ignored.

**Examples** WFMOUTPRE: PT\_OFF? might return WFMOUTPRE: PT\_OFF 0 indicating that the

waveform specified by DATA: SOURCE is on or displayed.

# WFMOutpre:PT\_ORder? (Query Only)

This query is for compatibility with other Tektronix oscilloscopes and always returns LINEAR.

**Group** Waveform Transfer

**Syntax** WFMOutpre:PT\_ORder?

Related Commands DATa: SOUrce

**Examples** WFMOUTPRE:PT\_ORDER? returns:WFMOUTPRE:PT\_ORDER LINEAR.

# WFMOutpre:RECOrdlength? (Query Only)

Group

Returns the record length for the source waveform as specified by the DATa:SOUrce command.

Syntax WFMOutpre: RECOrdlength?

Waveform Transfer

**Examples** WFMOUTPRE:RECORDLENGTH? might return WFMOUTPRE:RECORDLENGTH 6250

indicating that 6250 is the source waveform record length.

# WFMOutpre:WFld? (Query Only)

Returns a string describing several aspects of the acquisition parameters for the waveform specified by the DATa:SOUrce command. The query command will

time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

**Group** Waveform Transfer

Syntax WFMOutpre:WFId?

**Related Commands** DATa:SOUrce

**Returns** <QString> comprises the following comma-separated fields documented in the tables below:

#### **Table 2-42: Waveform Suffixes**

Field	Description	Examples "CH1–4" "Math1 "Ref1–2"		
Source	The source identification string as it appears in the front-panel scale factor readouts.			
Coupling	A string describing the vertical coupling of the waveform (the Source1 waveform in the case of Dual Waveform Math).	"AC coupling" "DC couplng" "GND coupling"		
Vert Scale	A string containing the vertical scale factor of the unzoomed waveform. The numeric portion will always be four digits. The examples cover all known internal units.	"100.0 mV/div" "20.00 dB/div" "45.00 deg/div" "785.4 mrad/div"		
		"500.0 μVs/div" "10.00 kV/s/div" "200.0 mV/div" "50.00 unk/div"		
Horiz Scale  A string containing the horizontal scale factor of the unzoomed waveform. The numeric portion will always be four digits. The examples cover all known internal units.		"100 ms/div" "10.00 kHz/div"		
Record Length	A string containing the number of waveform points available in the entire record. The numeric portion is given as an integer.	"1000 points" "1000000 points"		
Acquisition Mode	A string describing the mode used to acquire the waveform.	"Sample mode" "Pk Detect mode" "Envelope mode" "Average mode"		

**Examples** 

WFMOUTPRE:WFID? might return :WFMOUTPRE:WFID "Ch1, DC coupling,100.0mVolts/div,500.0 $\mu$ s/div, 1000 points, Sample mode"

# WFMOutpre:XINcr? (Query Only)

Returns the horizontal point spacing in units of WFMOutpre:XUNit for the waveform specified by the DATa:SOUrce command. This value corresponds to the sampling interval. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

**Group** Waveform Transfer

Syntax WFMOutpre:XINcr?

Related Commands DATa: SOUrce, WFMOutpre: XUNit?

**Examples** WFMOUTPRE:XINCR? might return:WFMOUTPRE:XINCR 10.0000E-6

indicating that the horizontal sampling interval is 10 µs/point.

# WFMOutpre:XUNit? (Query Only)

Returns the horizontal units for the waveform specified by the DATa:SOUrce command. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

**Group** Waveform Transfer

**Syntax** WFMOutpre:XUNit?

Related Commands DATa:SOUrce

**Examples** WFMOUTPRE:XUNIT? might return:WFMOUTPRE:XUNIT "HZ" indicating that

the horizontal units for the waveform are in Hertz.

# WFMOutpre:XZEro? (Query Only)

Returns the time coordinate of the first point in the outgoing waveform.

This value is in units of WFMOutpre:XUNit?. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

**Group** Waveform Transfer

**Syntax** WFMOutpre:XZEro?

Related Commands DATa:SOUrce, WFMOutpre:XUNit?

**Examples** WFMOUTPRE:XZERO? might return:WFMOUTPRE:XZERO 5.6300E-9 indicating

that the trigger occurred 5.63 ns before the first sample in the waveform record.

# WFMOutpre:YMUIt? (Query Only)

Returns the vertical scale factor per digitizing level in units specified by WFMOutpre:YUNit for the waveform specified by the DATa:SOUrce command. The query command will time out and an error is generated if the waveform specified by DATa:SOUrce is not turned on.

See the description of WFMInpre:YMUlt to see how this scale factor is used to convert waveform sample values to volts.

**Group** Waveform Transfer

**Syntax** WFMOutpre:YMUlt?

Related Commands DATa:SOUrce, WFMInpre:YMUlt

**Examples** WFMOUTPRE:YMULT? might return:WFMOUTPRE:YMULT 4.0000E-3 indicating

that the vertical scale for the corresponding waveform is 100 mV/div (for 8-bit

waveform data).

# WFMOutpre:YOFf? (Query Only)

Returns the vertical position in digitizing levels for the waveform specified by the DATa:SOUrce command. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

See the description of WFMInpre:YOFf to see how this position is used to convert waveform sample values to volts.

**Group** Waveform Transfer

**Syntax** WFMOutpre:YOFf?

Related Commands DATa:SOUrce, WFMOutpre:BYT Nr

**Examples** WFMOUTPRE:YOFF? might return:WFMOUTPRE:YOFF -50.0000E+0 indicating

that the position indicator for the waveform was 50 digitizing levels (2 divisions)

below center screen (for 8-bit waveform data).

# WFMOutpre:YUNit? (Query Only)

Returns the vertical units for the waveform specified by the DATa:SOUrce command. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

**Group** Waveform Transfer

Syntax WFMOutpre:YUNit?

Related Commands DATa:SOUrce

**Examples** WFMOUTPRE:YUNIT? might return:WFMOUTPRE:YUNIT "dB" indicating that

the vertical units for the waveform are measured in decibels.

## WFMOutpre:YZEro? (Query Only)

Returns the vertical offset in units specified by WFMOutpre:YUNit? for the waveform specified by the DATa:SOUrce command. The query command will time out and an error will be generated if the waveform specified by DATa:SOUrce is not turned on.

See the description of WFMInpre:YZEro to see how this offset is used to convert waveform sample values to volts.

**Group** Waveform Transfer

**Syntax** WFMOutpre:YZEro?

Related Commands DATa:SOUrce, WFMOutpre:YUNit?

WFMOUTPRE:YZERO? might return:WFMOUTPRE:YZERO -100.0000E-3 **Examples** 

indicating that vertical offset is set to −100 mV.

# ZOOm? (Query Only)

Returns the current vertical and horizontal positioning and scaling of the display.

Zoom Group

ZOOm? **Syntax** 

ZOOM? might return : ZOOM: MODE 1; GRATICULE: SIZE 80; SPLIT **Examples** 

> EIGHTYTWENTY;:ZOOM:ZOOM1:STATE 1;SCALE 400.0000E-12;POSITION 46.8986; FACTOR 50.0000E+3; HORIZONTAL: POSITION 46.8986; SCALE

400.0000E-12

# ZOOm{:MODe|:STATE}

Turns Zoom mode on or off. The Zoom mode query returns the current state of Zoom mode. This command is equivalent to pressing the zoom button located on the front panel.

Zoom Group

**Syntax** ZOOm{:MODe|:STATE} {ON|OFF|<NR1>}

ZOOm{:MODe|:STATE}

**Arguments** ON turns on Zoom mode.

OFF turns off Zoom mode.

<NR1> = 0 turns off Zoom mode; any other value turns on Zoom mode.

**Examples** ZOOM: MODE OFF turns off Zoom mode.

ZOOM: MODE? might return: ZOOM: MODE 1 indicating that Zoom mode is

currently turned on.

# ZOOm:ZOOM1? (Query Only)

Returns the current horizontal positioning and scaling of the display.

**Group** Zoom

Syntax ZOOm: ZOOM1?

**Examples** ZOOM: ZOOM1? might return : ZOOM: ZOOM1: STATE

1; SCALE 400.0000E-12; POSITION 46.8986; FACTOR

50.0000E+3; HORIZONTAL: POSITION 46.8986; SCALE 400.0000E-12.

# ZOOm:ZOOM1:FACtor? (Query Only)

Returns the zoom factor of a particular zoom box.

**Group** Zoom

**Syntax** ZOOm:ZOOM1:FACtor?

**Returns** <NR1> is the zoom factor of a zoom box.

#### ZOOm:ZOOM1:HORizontal:POSition

Sets or returns the horizontal position for the specified zoom.

Group Zoom

Syntax ZOOm:ZOOM1:HORizontal:POSition <NR3>

ZOOm:ZOOM1:HORizontal:POSition?

**Arguments** <NR3> is a value from 0 to 100.00 and is the percent of the upper window that is

to the left of screen center, when the zoom factor is  $1 \times$  or greater.

**Examples** ZOOM: ZOOM1: HORIZONTAL: POSITION 50 sets the Zoom1 reference pointer at

50% of acquired waveform.

ZOOM:ZOOM1:HORIZONTAL:POSITION? might return

:ZOOM1:HORIZONTAL:POSITION 50.0000 indicating that the Zoom1

reference pointer is currently set at 50% of acquired waveform.

#### ZOOm:ZOOM1:HORizontal:SCAle

Sets or returns the zoom horizontal scale for the specified zoom.

**Group** Zoom

Syntax ZOOm:ZOOM1:HORizontal:SCAle <NR3>

ZOOm: ZOOM1: HORizontal: SCAle?

**Arguments** <NR3> is the amount of expansion in the horizontal direction and ranges from

1.0E-3 to 5.0.

**Examples** ZOOM: ZOOM1: HORIZONTAL: SCALE 5 sets the horizontal scale to 5 seconds.

ZOOM:ZOOM2:HORIZONTAL:SCALE? might return

:ZOOM2:HORIZONTAL:SCALE 1, indicating that the horizontal scale is 1 second.

#### ZOOm:ZOOM1:POSition

Sets or returns the horizontal position for the specified zoom.

Group Zoom

Syntax ZOOm:ZOOM1:POSition <NR3>

ZOOm:ZOOM1:POSition?

**Arguments** <NR3> is a value from 0 to 100.00 and is the percent of the upper window that is

to the left of screen center, when the zoom factor is  $1 \times$  or greater.

### ZOOm:ZOOM1:SCAle

Sets or returns the zoom horizontal scale for the specified zoom.

Group Zoom

Syntax ZOOm:ZOOM1:SCAle <NR3>

ZOOm:ZOOM1:SCAle?

**Arguments** <NR3> is the amount of expansion in the horizontal direction and ranges from

1.0E-3 to 5.0.

#### ZOOm:ZOOM1:STATE

Sets or returns the specified zoom on or off, where x is the integer 1 representing

the single zoom window.

**Group** Zoom

Syntax ZOOm:ZOOM1:STATE {ON|OFF|<NR1>}

ZOOm:ZOOM1:STATE?

**Arguments** ON turns Zoom 1 on.

OFF turns Zoom 1 off.

<NR1> = 0 disables the specified zoom; any other value enables the specified

zoom.

**Examples** ZOOM: ZOOM1: STATE ON turns Zoom1 on.

ZOOM: ZOOM1: STATE? might return: ZOOM: ZOOM1: STATE 1 indicating that

Zoom1 is on.

# **Status and Events**

The oscilloscope provides a status and event reporting system for the Ethernet, GPIB (with the TEK-USB-488 Adapter), and USB interfaces. This system informs you of certain significant events that occur within the oscilloscope.

The oscilloscope status handling system consists of five 8-bit registers and two queues for each interface. The remaining Status subtopics describe these registers and components. They also explain how the event handling system operates.

# Registers

#### Overview

The registers in the event handling system fall into two functional groups:

- Status Registers contain information about the status of the oscilloscope. They include the Standard Event Status Register (SESR).
- Enable Registers determine whether selected types of events are reported to the Status Registers and the Event Queue. They include the Device Event Status Enable Register (DESER), the Event Status Enable Register (ESER), and the Service Request Enable Register (SRER).

#### Status Registers

The Standard Event Status Register (SESR) and the Status Byte Register (SBR) record certain types of events that may occur while the oscilloscope is in use. IEEE Std 488.2-1987 defines these registers.

Each bit in a Status Register records a particular type of event, such as an execution error or message available. When an event of a given type occurs, the oscilloscope sets the bit that represents that type of event to a value of one. (You can disable bits so that they ignore events and remain at zero. See Enable Registers). Reading the status registers tells you what types of events have occurred.

**The Standard Event Status Register (SESR).** The SESR records eight types of events that can occur within the oscilloscope. Use the \*ESR? query to read the SESR register. Reading the register clears the bits of the register so that the register can accumulate information about new events.

**NOTE.** TekVISA applications use SESR bit 6 to respond to any of several events, including some front panel actions.

7	6	5	4	3	2	1	0
PON	URQ	CME	EXE	DDE	QYE	RQC	OPC

Figure 3-1: The Standard Event Status Register (SESR)

Table 3-1: SESR Bit Functions

Bit	Function	
7 (MSB)	PON	Power On. Shows that the oscilloscope was powered on. On completion, the diagnostic self tests also set this bit.
6	URQ	User Request. Indicates that an application event has occurred. *See note.
5	CME	Command Error. Shows that an error occurred while the oscilloscope was parsing a command or query.
4	EXE	Execution Error. Shows that an error executing a command or query.
3	DDE	Device Error. Shows that a device error occurred.
2	QYE	Query Error. Either an attempt was made to read the Output Queue when no data was present or pending, or that data in the Output Queue was lost.
1	RQC	Request Control. This is not used.
0 (LSB)	OPC	Operation Complete. Shows that the operation is complete. This bit is set when all pending operations complete following an *OPC command.

**The Status Byte Register (SBR).** Records whether output is available in the Output Queue, whether the oscilloscope requests service, and whether the SESR has recorded any events.

Use a Serial Poll or the \*STB? query to read the contents of the SBR. The bits in the SBR are set and cleared depending on the contents of the SESR, the Event Status Enable Register (ESER), and the Output Queue. When you use a Serial Poll to obtain the SBR, bit 6 is the RQS bit. When you use the \*STB? query to obtain the SBR, bit 6 is the MSS bit. Reading the SBR does not clear the bits.




Figure 3-2: The Status Byte Register (SBR)

Table 3-2: SBR Bit Functions

Bit	Function	
7 (MSB)		Not used.
6	RQS	Request Service. Obtained from a serial poll. Shows that the oscilloscope requests service from the GPIB controller.
6	MSS	Master Status Summary. Obtained from *STB? query. Summarizes the ESB and MAV bits in the SBR.
5	ESB	Event Status Bit. Shows that status is enabled and present in the SESR.

Table 3-2: SBR Bit Functions (cont.)

Bit	Function	
4	MAV	Message Available. Shows that output is available in the Output Queue.
3		Not used.
2		Not used.
1–0		Not used.

#### **Enable Registers**

DESER, ESER, and SRER allow you to select which events are reported to the Status Registers and the Event Queue. Each Enable Register acts as a filter to a Status Register (the DESER also acts as a filter to the Event Queue) and can prevent information from being recorded in the register or queue.

Each bit in an Enable Register corresponds to a bit in the Status Register it controls. In order for an event to be reported to a bit in the Status Register, the corresponding bit in the Enable Register must be set to one. If the bit in the Enable Register is set to zero, the event is not recorded.

Various commands set the bits in the Enable Registers. The Enable Registers and the commands used to set them are described below.

**The Device Event Status Enable Register (DESER).** This register controls which types of events are reported to the SESR and the Event Queue. The bits in the DESER correspond to those in the SESR.

Use the DESE command to enable and disable the bits in the DESER. Use the DESE? query to read the DESER.

7	6	5	4	3	2	1	0
PON	URQ	CME	EXE	DDE	QYE	RQC	OPC

Figure 3-3: The Device Event Status Enable Register (DESER)

**The Event Status Enable Register (ESER).** This register controls which types of events are summarized by the Event Status Bit (ESB) in the SBR. Use the \*ESE command to set the bits in the ESER. Use the \*ESE? query to read it.

7	6	5	4	3	2	1	0
PON	URQ	CME	EXE	DDE	QYE	RQC	OPC

Figure 3-4: The Event Status Enable Register (ESER)

The Service Request Enable Register (SRER). This register controls which bits in the SBR generate a Service Request and are summarized by the Master Status Summary (MSS) bit.

Use the \*SRE command to set the SRER. Use the \*SRE? query to read the register. The RQS bit remains set to one until either the Status Byte Register is read with a Serial Poll or the MSS bit changes back to a zero.



Figure 3-5: The Service Request Enable Register (SRER)

#### \*PSC Command

The \*PSC command controls the Enable Registers contents at power-on. Sending \*PSC 1 sets the Enable Registers at power on as follows:

- DESER 255 (equivalent to a DESe 255 command)
- ESER 0 (equivalent to an \*ESE 0 command)
- SRER 0 (equivalent to an \*SRE 0 command)

Sending \*PSC 0 lets the Enable Registers maintain their values in nonvolatile memory through a power cycle.

**NOTE.** To enable the PON (Power On) event to generate a Service Request, send \*PSC 0, use the DESe and \*ESE commands to enable PON in the DESER and ESER, and use the \*SRE command to enable bit 5 in the SRER. Subsequent power-on cycles will generate a Service Request.

#### Queues

#### **Output Queue**

The oscilloscope stores query responses in the Output Queue and empties this queue each time it receives a new command or query message after an <EOM>. The controller must read a query response before it sends the next command (or query) or it will lose responses to earlier queries.



**CAUTION.** When a controller sends a query, an <EOM>, and a second query, the oscilloscope normally clears the first response and outputs the second while reporting a Query Error (QYE bit in the ESER) to indicate the lost response. A fast controller, however, may receive a part or all of the first response as well. To avoid this situation, the controller should always read the response immediately after sending any terminated query message or send a DCL (Device Clear) before sending the second query.

#### **Event Queue**

The Event Queue stores detailed information on up to 128 events. If more than 128 events stack up in the Event Queue, the 128th event is replaced by event code 350, "Queue Overflow."

Read the Event Queue with the EVENT? query (which returns only the event number), with the EVMSG? query (which returns the event number and a text description of the event), or with the ALLEV? query (which returns all the event numbers along with a description of the event). Reading an event removes it from the queue.

Before reading an event from the Event Queue, you must use the \*ESR? query to read the summary of the event from the SESR. This makes the events summarized by the \*ESR? read available to the EVENT? and EVMSG? queries, and empties the SESR.

Reading the SESR erases any events that were summarized by previous \*ESR? reads but not read from the Event Queue. Events that follow an \*ESR? read are put in the Event Queue but are not available until \*ESR? is used again.

# **Event Handling Sequence**

The figure below shows how to use the status and event handling system. In the explanation that follows, numbers in parentheses refer to numbers in the figure.




Figure 3-6: Status and Event Handling Process

When an event occurs, a signal is sent to the DESER (1). If that type of event is enabled in the DESER (that is, if the bit for that event type is set to 1), the appropriate bit in the SESR is set to one, and the event is recorded in the Event Queue (2). If the corresponding bit in the ESER is also enabled (3), then the ESB bit in the SBR is set to one (4).

When output is sent to the Output Queue, the MAV bit in the SBR is set to one (5).

When a bit in the SBR is set to one and the corresponding bit in the SRER is enabled (6), the MSS bit in the SBR is set to one and a service request is generated (7).

# **Synchronization Methods**

#### Overview

Although most commands are completed almost immediately after being received by the oscilloscope, some commands start a process that requires time. For example, once a single sequence acquisition command is executed, depending upon the applied signals and trigger settings, it may take an indeterminate amount of time before the acquisition is complete. Rather than remain idle while the operation is in process, the oscilloscope will continue processing other commands. This means that some operations will not be completed in the order that they were sent.

Sometimes the result of an operation depends on the result of an earlier operation. A first operation must complete before the next one is processed. The oscilloscope status and event reporting system is designed to accommodate this process.

The Operation Complete (OPC) bit of the Standard Event Status Register (SESR) can be programmed to indicate when certain oscilloscope operations have completed and, by setting the Event Status Enable Register (ESER) to report OPC in the Event Status Bit (ESB) of the Status Byte Register (SBR) and setting the Service Request Enable Register (SRER) to generate service request upon a positive transition of the ESB, a service request (SRQ) interrupt can be generated when certain operations complete as described in this section.

The following oscilloscope operations can generate an OPC:

- :ACQuire:STATE <non-zero nr1> | ON | RUN only when in single sequence acquisition mode
- :CALibrate:FACtory STARt
  - :CALibrate:FACtory CONTinue
  - :CALibrate:FACtory PREVious
- :HARDCopy
  - :HARDCopy START
- :DIAg:STATE EXECute
- :SAVe:IMAGe <file as quoted string>
- :SAVe:SETUp <file as quoted string>
- :RECAll:SETUp <file as quoted string>
- SAVe: WAVEform < source wwfm>,(<REF1-REF4> | <file as quoted string>
- :RECAll:WAVEform <ISF file as quoted string>,<REF1-REF4>
- :CH<1-4>:PRObe:DEGAUss EXECute
- :CH<1-4>:PRObe:AUTOZero EXECute
- TEKSecure

For example, a typical application might involve acquiring a single-sequence waveform and then taking a measurement on the acquired waveform. You could use the following command sequence to do this:

```
/* Set up conditional acquisition */
ACQUIRE:STATE OFF
SELECT:CH1 ON
ACQUIRE:MODE SAMPLE
ACQUIRE:STOPAFTER SEQUENCE
/* Acquire waveform data */
ACQUIRE:STATE ON
/* Set up the measurement parameters */
MEASUREMENT:IMMED:TYPE AMPLITUDE
MEASUREMENT:IMMED:SOURCE CH1
/* Take amplitude measurement */
MEASUREMENT:IMMED:VALUE
```

The acquisition of the waveform requires extended processing time. It may not finish before the oscilloscope takes an amplitude measurement (see the following figure). This can result in an incorrect amplitude value.




Figure 3-7: Command Processing Without Using Synchronization

To ensure the oscilloscope completes waveform acquisition before taking the measurement on the acquired data, you can synchronize the program.




Figure 3-8: Processing Sequence With Synchronization

You can use four different methods to synchronize the operation of the oscilloscope with your application program: \*WAI, BUSY, \*OPC, and \*OPC?. The \*OPC? query method is the most simple approach.

#### Using the \*WAI Command

The \*WAI command forces completion of previous commands that generate an OPC message. No commands after the \*WAI are processed before the OPC message(s) are generated.

The same command sequence using the \*WAI command for synchronization looks like this:

```
/* Set up conditional acquisition */
ACQUIRE:STATE OFF
SELECT:CH1 ON
ACQUIRE:MODE SAMPLE
ACQUIRE:STOPAFTER SEQUENCE
/* Acquire waveform data */
ACQUIRE:STATE ON
/* Set up the measurement parameters */
MEASUREMENT:IMMED:TYPE AMPLITUDE
MEASUREMENT:IMMED:SOURCE CH1
/* wait until the acquisition is complete before taking the measurement */
*WAI
/* Take amplitude measurement */
MEASUREMENT:IMMED:VALUE?
```

The controller can continue to write commands to the input buffer of the oscilloscope, but the commands will not be processed by the oscilloscope until all in-process OPC operations are complete. If the input buffer becomes full, the controller will be unable to write commands to the buffer. This can cause a time-out.

#### **Using the BUSY Query**

The BUSY? query allows you to find out whether the oscilloscope is busy processing a command that generates OPC.

The same command sequence, using the BUSY? query for synchronization, looks like this:

```
/* Set up conditional acquisition */
ACQUIRE:STATE OFF
SELECT:CH1 ON
ACQUIRE:MODE SAMPLE
ACQUIRE:STOPAFTER SEQUENCE
/* Acquire waveform data */
ACQUIRE:STATE ON
/* Set up the measurement parameters */
MEASUREMENT:IMMED:TYPE AMPLITUDE
MEASUREMENT:IMMED:SOURCE CH1
/* wait until the acquisition is complete before taking the measurement */
While BUSY keep looping
/* Take amplitude measurement */
MEASUREMENT:IMMED:VALUE?
```

This sequence lets you create your own wait loop rather than using the \*WAI command. The BUSY? query helps you avoid time-outs caused by writing too

many commands to the input buffer. The controller is still tied up though, and the repeated BUSY? query will result in bus traffic.

#### **Using the \*OPC Command**

If the corresponding status registers are enabled, the \*OPC command sets the OPC bit in the Standard Event Status Register (SESR) when an operation is complete. You achieve synchronization by using this command with either a serial poll or service request handler.

**Serial Poll Method:** Enable the OPC bit in the Device Event Status Enable Register (DESER) and the Event Status Enable Register (ESER) using the DESE and \*ESE commands.

When the operation is complete, the OPC bit in the Standard Event Status Register (SESR) will be enabled and the Event Status Bit (ESB) in the Status Byte Register will be enabled.

The same command sequence using the \*OPC command for synchronization with serial polling looks like this:

```
/* Set up conditional acquisition */
ACOUIRE:STATE OFF
SELECT: CH1 ON
ACQUIRE: MODE SAMPLE
ACQUIRE:STOPAFTER SEQUENCE
/* Enable the status registers */
DESE 1
*ESE 1
*SRE 0
/* Acquire waveform data */
ACQUIRE:STATE ON
/* Set up the measurement parameters */
MEASUREMENT: IMMED: TYPE AMPLITUDE
MEASUREMENT: IMMED: SOURCE CH1
/* Wait until the acquisition is complete before taking the
measurement.*/
*OPC
while serial poll = 0, keep looping
/* Take amplitude measurement */
MEASUREMENT: IMMED: VALUE?
```

This technique requires less bus traffic than did looping on BUSY.

**Service Request Method:** Enable the OPC bit in the Device Event Status Enable Register (DESER) and the Event Status Enable Register (ESER) using the DESE and \*ESE commands.

You can also enable service requests by setting the ESB bit in the Service Request Enable Register (SRER) using the \*SRE command. When the operation is complete, the oscilloscope will generate a Service Request.

The same command sequence using the \*OPC command for synchronization looks like this

```
/* Set up conditional acquisition */
ACQUIRE:STATE OFF
SELECT: CH1 ON
ACQUIRE: MODE SAMPLE
ACQUIRE:STOPAFTER SEQUENCE
/* Enable the status registers */
DESE 1
*ESE 1
*SRE 32
/* Acquire waveform data */
ACQUIRE: STATE ON
/* Set up the measurement parameters */
MEASUREMENT: IMMED: TYPE AMPLITUDE
MEASUREMENT: IMMED: SOURCE CH1
/* Wait until the acquisition is complete before taking the
measurement*/
*OPC
```

The program can now do different tasks such as talk to other devices. The SRQ, when it comes, interrupts those tasks and returns control to this task.

```
/* Take amplitude measurement */
MEASUREMENT:IMMED:VALUE?
```

This technique is efficient but requires sophisticated programming.

#### Using the \*OPC? Query

The \*OPC? query is the most simple synchronization method. It does not require you to set registers or poll, and it does not change the operation of subsequent commands or queries.

The \*OPC? query places a 1 in the Output Queue once an operation that generates an OPC message is complete. A time out could occur if you try to read the output queue before there is any data in it.

The same command sequence using the \*OPC? query for synchronization looks like this:

```
/* Set up conditional acquisition */
ACQUIRE:STATE OFF
SELECT:CH1 ON
ACQUIRE:MODE SAMPLE
ACQUIRE:STOPAFTER SEQUENCE
/* Acquire waveform data */
ACQUIRE:STATE ON
/* Set up the measurement parameters */
MEASUREMENT:IMMED:TYPE AMPLITUDE
MEASUREMENT:IMMED:SOURCE CH1
```

```
/* Wait until the acquisition is complete */
*OPC?
/* Take amplitude measurement */
MEASUREMENT:IMMED:VALUE?
```

This is the simplest approach. It requires no status handling or loops. However, you must set the controller time-out for longer than the acquisition operation.

## Messages

#### Messages

The information contained in the tables below covers all the programming interface messages the oscilloscope generates in response to commands and queries.

For most messages, a secondary message from the oscilloscope gives detail about the cause of the error or the meaning of the message. This message is part of the message string and is separated from the main message by a semicolon.

Each message is the result of an event. Each type of event sets a specific bit in the SESR and is controlled by the equivalent bit in the DESER. Thus, each message is associated with a specific SESR bit. In the message tables, the associated SESR bit is specified in the table title, with exceptions noted with the error message text.

#### No Event

The following table shows the messages when the system has no events or status to report. These have no associated SESR bit.

**Table 3-3: No Event Messages** 

Code	Message
0	No events to report; queue empty
1	No events to report; new events pending *ESR?

#### **Command Error**

The following table shows the command error messages generated by improper syntax. Check that the command is properly formed and that it follows the rules in the section on command Syntax.

Table 3-4: Command Error Messages (CME Bit 5)

Code	Message
100	Command error
101	Invalid character
102	Syntax error
103	Invalid separator
104	Data type error
105	GET not allowed
	-

Table 3-4: Command Error Messages (CME Bit 5) (cont.)

Message
Parameter not allowed
Missing parameter
Command header error
Program mnemonic too long
Undefined header
Numeric data error
Invalid character in numeric
Exponent too large
Too many digits
Suffix error
Invalid suffix
Suffix too long
Character data error
Invalid character data
Character data too long
String data error
Invalid string data
String data too long
Block data error
Invalid block data
Command expression error
Invalid expression

#### **Execution Error**

The following table lists the execution errors that are detected during execution of a command.

Table 3-5: Execution Error Messages (EXE Bit 4)

Code	Message
200	Execution error
221	Settings conflict
222	Data out of range
224	Illegal parameter value
241	Hardware missing
250	Mass storage error
251	Missing mass storage
252	Missing media

Table 3-5: Execution Error Messages (EXE Bit 4) (cont.)

Code	Message
253	Corrupt media
254	Media full
255	Directory full
256	File name not found
257	File name error
258	Media protected
259	File name too long
270	Hardcopy error
271	Hardcopy device not responding
272	Hardcopy is busy
273	Hardcopy aborted
274	Hardcopy configuration error
280	Program error
282	Insufficient network printer information
283	Network printer not responding
284	Network printer server not responding
286	Program runtime error
287	Print server not found
2200	Measurement error, Measurement system error
2201	Measurement error, Zero period
2202	Measurement error, No period, second waveform
2203	Measurement error, No period, second waveform
2204	Measurement error, Low amplitude, second waveform
2205	Measurement error, Low amplitude, second waveform
2206	Measurement error, Invalid gate
2207	Measurement error, Measurement overflow
2208	Measurement error, No backwards Mid Ref crossing
2209	Measurement error, No second Mid Ref crossing
2210	Measurement error, No Mid Ref crossing, second waveform
2211	Measurement error, No backwards Mid Ref crossing
2212	Measurement error, No negative crossing
2213	Measurement error, No positive crossing
2214	Measurement error, No crossing, target waveform
2215	Measurement error, No crossing, second waveform
2216	Measurement error, No crossing, target waveform
2217	Measurement error, Constant waveform
2219	Measurement error, No valid edge - No arm sample

Table 3-5: Execution Error Messages (EXE Bit 4) (cont.)

Code	Message
2220	Measurement error, No valid edge - No arm cross
2221	Measurement error, No valid edge - No trigger cross
2222	Measurement error, No valid edge - No second cross
2223	Measurement error, Waveform mismatch
2224	Measurement error, WAIT calculating
2225	Measurement error, No waveform to measure
2226	Measurement error, Null Waveform
2227	Measurement error, Positive and Negative Clipping
2228	Measurement error, Positive Clipping
2229	Measurement error, Negative Clipping
2230	Measurement error, High Ref < Low Ref
2231	Measurement error, No statistics available
2233	Requested waveform is temporarily unavailable
2235	Math error, invalid math description
2240	Invalid password
2241	Waveform requested is invalid
2244	Source waveform is not active
2245	Saveref error, selected channel is turned off
2250	Reference error, the reference waveform file is invalid
2253	Reference error, too many points received
2254	Reference error, too few points received
2259	File too big
2270	Alias error
2271	Alias syntax error
2273	Illegal alias label
2276	Alias expansion error
2277	Alias redefinition not allowed
2278	Alias header not found
2285	TekSecure(R) Pass
2286	TekSecure(R) Fail
2500	Setup error, file does not look like a setup file
2501	Setup warning, could not recall all values from external setup
2620	Mask error, too few points received
2760	Mark limit reached
2761	No mark present
2762	Search copy failed

#### **Device Error**

The following table lists the device errors that can occur during oscilloscope operation. These errors may indicate that the oscilloscope needs repair.

Table 3-6: Device Error Messages (DDE Bit 3)

Code	Message
310	System error
311	Memory error
312	PUD memory lost
314	Save/recall memory lost

#### **System Event**

The following table lists the system event messages. These messages are generated whenever certain system conditions occur.

**Table 3-7: System Event Messages** 

Code	Message
400	Query event
401	Power on (PON bit 7 set)
402	Operation complete (OPC bit 0 set)
403	User request (URQ bit 6 set)
404	Power fail (DDE bit 3 set)
405	Request control
410	Query INTERRUPTED (QYE bit 2 set)
420	Query UNTERMINATED (QYE bit 2 set)
430	Query DEADLOCKED (QYE bit 2 set)
440	Query UNTERMINATED after indefinite response (QYE bit 2 set)
468	Knob/Keypad value changed
472	Application variable changed

#### **Execution Warning**

The following table lists warning messages that do not interrupt the flow of command execution. They also notify you of a possible unexpected results.

Table 3-8: Execution Warning Messages (EXE Bit 4)

Code	Message
528	Parameter out of range
532	Curve data too long, Curve truncated
533	Curve error, Preamble values are inconsistent
540	Measurement warning, Uncertain edge
541	Measurement warning, Low signal amplitude
542	Measurement warning, Unstable histogram

Table 3-8: Execution Warning Messages (EXE Bit 4) (cont.)

Code	Message
543	Measurement warning, Low resolution
544	Measurement warning, Uncertain edge
545	Measurement warning, Invalid in minmax
546	Measurement warning, Need 3 edges
547	Measurement warning, Clipping positive/negative
548	Measurement warning, Clipping positive
549	Measurement warning, Clipping negative

Table 3-9: Execution Warning Messages (EXE Bit 4)

Code	Message
540	Measurement warning
541	Measurement warning, Low signal amplitude
542	Measurement warning, Unstable histogram
543	Measurement warning, Low resolution
544	Measurement warning, Uncertain edge
545	Measurement warning, Invalid min max
546	Measurement warning, Need 3 edges
547	Measurement warning, Clipping positive/negative
548	Measurement warning, Clipping positive
549	Measurement warning, Clipping negative

## **Internal Warning**


The following table shows internal errors that indicate an internal fault in the oscilloscope.

**Table 3-10: Internal Warning Messages** 

Code	Message
630	Internal warning, $50\Omega$ overload

# **Appendix A: Character Set**

B6 B1S B1S B1S B1S B1S B4 B3 B2 B1S B1    NUMBERS	B7	0 0	0 0	0 1	0 1	1 0	1 0	1 1	1 1
B	<b>B</b> 5	-	-				-		-
		CON	TROL			UPPER (	CASE	LOWER	CASE
1		-							
	0 0 0 0				-		- 1		
1	0 0 0 1								_
Name	0 0 0 1				-				
	0 0 1 0								
Name	0 0 1 0			l I					
1	0 0 1 1								
0 1 0 0 0 4 EOT 4 14 DC2 0 24 \$ 36 34 \$ 52 44 D 68 54 T 84 64 D 100 74 116  1 0 1 0 1 5 ENQ 5 NAK 5 S 15 21 25 87 87	0 0 1 1				-		٠ ا	-	_
	0 1 0 0								
O	0 1 0 0				-		- 1		-
S	0 1 0 1								
0 1 1 0 0 6 6 6 6 6 6 22 26 38 36 6 54 46 F 70 56 V 86 66 102 76 V 118  7 BEL 7 ETB 47 LA7 67 LA23 107 TA7 127 TA23 147 SA7 167 SA23  0 1 1 1 1 7 T BEL 7 19 S 50 LA8 70 LA8 70 LA24 110 TA8 130 TA24 150 SA8 170 SA24  1 0 0 0 0 1 BS 8 8 8 8 18 24 28 40 38 56 48 72 58 X 8 8 68 104 78 X 120  1 0 0 0 1 1 T TCT 31 SPD 51 LA9 71 LA25 111 TA9 131 TA25 151 SA9 171 SA25  1 0 0 1 0 1 0 LE SUB A LA10 72 LA26 112 TA10 132 TA26 152 SA10 172 SA26  1 0 1 1 1 1 TCT 1 SUB SUB A LA10 72 LA26 112 TA10 132 TA26 152 SA10 172 SA26  1 0 1 1 1 1 CCT SUB SUB A LA11 73 LA27 113 TA11 133 TA27 153 SA11 173 SA27  1 0 0 1 1 C F 1 C SUB A LA11 73 LA27 113 TA11 133 TA27 153 SA11 173 SA27  1 1 0 0 1 0 C F 1 C SUB A LA11 73 LA27 113 TA11 133 TA27 155 SA13 175 SA29  1 1 0 0 1 1 C F 1 C SUB A LA11 73 LA27 113 TA11 133 TA27 155 SA13 175 SA29  1 1 0 1 1 C F 1 C SUB A LA11 75 LA28 114 TA12 134 TA28 154 SA12 174 SA28  1 1 0 0 1 C F 1 C SUB C A LA13 75 LA28 114 TA12 134 TA28 155 SA31 175 SA29  1 1 1 0 1 1 C C SUB C A LA13 75 LA28 114 TA12 134 TA12 134 TA28 155 SA31 175 SA29  1 1 1 1 1 1 C C SUB C A LA14 76 LA30 116 TA11 135 TA29 155 SA13 175 SA29  1 1 1 1 1 1 C C SUB C A LA14 76 LA30 116 TA11 136 TA29 155 SA13 175 SA29  1 1 1 1 1 1 C C SUB C A LA14 76 LA30 116 TA11 136 TA29 155 SA31 175 SA29  1 1 1 1 1 1 C C SUB C A LA14 76 LA30 116 TA11 136 TA11 136 TA29 155 SA31 175 SA29  1 1 1 1 1 1 C C SUB C A LA14 76 LA30 116 TA11 136 TA11 136 TA29 155 SA31 175 SA29  1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	0 1 0 1				-		•	-	
Carlo   Carl	0.1.1.0	-		I I					
0 1 1 1 1	0 1 1 0				•		- 1	-	-
The color of the	0 1 1 1								
1	0 1 1 1				-				
1   0   0   1   11   TCT   31   SPD   51   LA9   71   LA25   111   TA9   131   TA25   151   SA9   171   SA25     1   0   0   1   0   1   0   1   0   1   0   1   0   1   0     1   0   1   0   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1   0     1   1   0   1   0   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   1     1   0   1   1   0   1   0   1   0   0	1 0 0 0			50 <b>LA8</b>					
1 0 0 1 0 1 9 9 19 25 29 41 39 57 49 73 59 89 69 105 79 121  1 0 1 0 1 0	1 0 0 0			28 40	-				
9   9   19   25   29   41   39   57   49   73   59   89   69   105   79   121	1 0 0 1			51 <b>LA9</b>					
1 0 1 0 1 0	1 0 0 1			29 41	•			-	
A 10 1A 26 2A 42 3A 58 4A 74 5A 90 6A 106 7A 122  1 0 1 1	1 0 1 0				72 <b>LA26</b>			152 <b>SA10</b>	
1   1   1   1   1   1   1   1   1   1	1 0 1 0				3A 58			6A 106	
B	1 0 1 1						133 <b>TA27</b>		_
1 1 0 0 0							5B 91		
C 12 1C 28 2C 44 3C 60 4C 76 5C 92 6C 108 7C 124  15 35 GS 55 LA13 75 LA29 115 TA13 135 TA29 155 SA13 175 SA29  1 1 0 1 CR GS 5 -	1 1 0 0			54 <b>LA12</b>			134 <b>TA28</b>	154 <b>SA12</b>	
1 1 0 1	1 1 0 0			2C , 44			5C 92	6C 108	7C 124
D 13 1D 29 2D 45 3D 61 4D 77 5D 93 6D 109 7D 125  16 36 RS 56 LA14 76 LA30 116 TA14 136 TA30 156 SA14 176 SA30  E 14 1E 30 2E 46 3E 62 4E 78 5E 94 6E 110 7E 126  17 37 LA15 77 UNL 117 TA15 137 UNT 157 SA15 177 RUBOUT  F 15 1F 31 2F 47 3F 63 4F 79 5F 95 6F 111 7F (DEL)  ADDRESSED UNIVERSAL LISTEN TALK SECONDARY ADDRESSES	1 1 0 1			55 <b>LA13</b>					
1       1       0       SO E       RS I I I I I I I I I I I I I I I I I I I	1 1 0 1			2D 45					
E   14   1E   30   2E   46   3E   62   4E   78   5E   94   6E   110   7E   126	1 1 1 0			56 <b>LA14</b>			136 <b>TA30</b>		
1         1         1         SI         US         /         2F         47         3F         63         4F         79         5F         95         6F         111         7F         (DEL) 127           ADDRESSED         UNIVERSAL         LISTEN         TALK         SECONDARY ADDRESSES	1 1 1 V			2E 46			5E 94		
F 15 1F 31 2F 47 3F 63 4F 79 5F 95 6F 111 7F (DEL) 127  ADDRESSED UNIVERSAL LISTEN TALK SECONDARY ADDRESSES				57 <b>LA15</b>			137 <b>UNT</b>		
ADDRESSED UNIVERSAL LISTEN TALK SECONDARY ADDRESSES	1111			2F 47	-		5F 95		(DEL)
									ADDRESSES



**Tektronix** 

REF: ANSI STD X3.4-1977 IEEE STD 488.1-1987 ISO STD 646-2973

# Appendix B: Waveform Data in DPO/MSO2000 Series Instruments

An analog channel of an DPO/MSO2000 series instrument has a sample waveform and a peak detect waveform being acquired simultaneously. This combination waveform is referred to as a "composite" waveform. In some cases, for example when averaging is turned on, or for math waveforms, a composite waveform is not available. In these cases, the waveform is termed "singular", and is available only in sample mode.

#### Full Versus Reduced Resolution Waveforms

The DPO/MSO2000 series introduces the concept of reduced resolution waveforms available for curve queries. The DPO/MSO2000 oscilloscopes acquire channel data into "full" resolution records that are nominally 1 million (1M) or 100,000 (100K) points in size (the acquisition record length); these are termed "full resolution", or LRL (long record length) waveforms. These LRL records are "shrunk" (decimated) down to "thumbnail", "short", or "reduced resolution" waveforms; these are what appear on the oscilloscope's display screen. During decimation, a low-pass filter operation may be applied to the LRL sample data that results in a filtered thumbnail waveform. In general, both full and reduced resolution waveforms can be queried from the oscilloscope. The size of the reduced resolution waveform varies from 800 to 6250 points, depending on instrument settings.

Math FFT waveform data is available only in FULL resolution.

For applications which need to query waveform data rapidly for the purpose of displaying it, reduced resolution waveform data will provide a faster display update than a full resolution waveform data.

# Nominal Versus Actual Record Length

The DPO/MSO2000 series also introduces the concept of nominal versus actual acquisition record length. Like other oscilloscopes, the acquisition record length can be set using the HORizontal:RECOrdlength command. However, the actual number of points in the waveform record may differ from the nominal record length established by the HORizontal:RECOrdlength setting, depending on the HORizontal:SCAle in effect at the time of the acquisition. The valid values for setting acquisition record length are 1,000,000 (1M) and 100,000 (100K) points. Depending on the horizontal scale in effect at the time of the acquisition, a nominal 1M point record may be comprised of 1.0M or 1.25M (1,250,000) points and a nominal 100K point record may be comprised of 100K or 125K (125,000) points. The actual number of points in the waveform record for the source waveform (specified by the DATa:SOUrce command) may be obtained using the WFMOutpre:RECOrdlength? query.

## Composition of Waveform Data

The DPO/MSO2000 series introduces the concept of composite waveform data for analog channels. Sample data is always available for acquired analog channel waveforms. Composite waveforms are available in SAMPLE acquisition mode but are not available in AVERAGE acquisition mode. Peak data may be available depending on the instrument bandwidth, acquisition mode, nominal record length, and the horizontal scale settings.

- Sample waveform data which may be a component of a composite waveform is referred to as COMPOSITE\_YT (vertical units versus time) data.
- Peak detect waveform data which may be a component of a composite waveform is referred to as COMPOSITE\_ENV (envelope or peak detect min/max pairs versus time) data.
- Analog channel waveforms acquired in AVERAGE acquisition mode and MATH waveforms are not composite waveforms and are termed SINGULAR\_YT which indicates that the waveform is a single waveform composed of data points representing vertical units versus time. The composition of digital waveform data (:DATa:SOUrce D0 through D15, DIGital) is SINGULAR\_YT only.

The following table lists the various waveform data compositions:

Composition	Description
COMPOSITE_YT (analog channels)	This is sample waveform data in vertical units versus time. Its native width is 8-bits and is written as 8-bit data in saved ISF waveform files and reference waveforms. The data can be queried as 1- or 2-byte data in CURVe? queries by setting the data width to 1 or 2.
COMPOSITE_ENV (analog channels)	This is min/max pair waveform data with the minimum value preceding the maximum value. Its native width is 8-bits and is written as 8-bit data in saved ISF waveform files and reference waveforms. The data can be queried as 1- or 2-byte data in CURVe? queries by setting the data width to 1 or 2.
SINGULAR_YT (analog and math channels)	This is 16-bit waveform data which originates as averaged acquired waveform data or math data. It is written to saved ISF waveform files and reference waveforms as 16- bit data. The data can be queried as 1-or 2- byte data in CURVe? queries by setting the data width to 1 or 2.
SINGULAR_YT (digital channels)	This is sample waveform data in binary vertical units (0 or 1) versus time. Its native width is 8-bits for individual digital channels (D0 through D15) and 32 bits for the digital collection (D0 through D15, digital representation of CH1 through CH4). The only resolution available for digital waveform data is FULL.

The available waveform compositions, which can be obtained using the CURVe? or WAVFrm? queries, can be determined using the DATa:COMPosition:AVAILable? query. This query returns the available waveform compositions for the last acquired waveform for the source specified by the DATa:SOUrce command. The data returned by the DATa:COMPosition:AVAILable? query may be one of the following:

- COMPOSITE\_YT
- COMPOSITE\_YT, COMPOSITE\_ENV
- SINGULAR\_YT

The composition of the waveform data to be queried using the CURVe? or WAVFrm? queries is set using the DATa:COMPosition or WFMOutpre:COMPosition command. The compositions which can be set are:

- COMPOSITE\_YT
- COMPOSITE\_ENV
- SINGULAR\_YT

If the composition set is not available with the current acquisition and horizontal settings, no response is returned for the CURVe? or WAVFrm? query and an event is set.

For example, if COMPOSITE\_ENV data is not available and a CURVe? query is sent with the composition set to COMPOSITE\_ENV, no data will be returned and an error event is set:

```
> :DATA:COMPOSITION:AVAILABLE?
COMPOSITE_YT
> DATA:COMPOSITION?
COMPOSITE_YT
> DATA:COMPOSITION
COMPOSITE_ENV
> *ESR? 0 > CURVE? {no data returned}
> *ESR?
20
> EVMSG?
221, "Settings conflict; Envelope waveform not available; CURVE?" >
```

The composition of the waveform data to be sent to the instrument for transfer to the reference waveform memory using the CURVe command is set using the WFMInpre:COMPosition command. The compositions which can be set are:

- COMPOSITE\_YT
- COMPOSITE\_ENV
- SINGULAR\_YT

## Filtering of Waveform Data with FilterVu

The FilterVu feature uses digital signal processing (DSP) techniques to apply low pass filtering to the acquired waveform data for the analog channels. The FilterVu feature provides filtering of the displayed waveform so that you can see your signal without the effects of noise. This is the reduced resolution waveform. A side effect of filtering the reduced resolution waveform is that the full resolution waveform may be subjected to filtering to achieve the desired filtering of the

reduced resolution waveform. The filtering frequency of the full resolution waveform is not under your direct control. It is a function of the horizontal and acquisition settings and the selected FilterVu frequency. The 3 dB cutoff frequency for this filtering may be different for the LRL record and the thumbnail record. The actual filter frequency applied to the acquired (LRL) and displayed (thumbnail) waveforms are available in the waveform preamble:

#### WFMOutpre:FILTERFreq?

This query returns the 3 dB low pass filter cutoff frequency for:

- The acquired (LRL) waveform when the DATa:RESOlution is set to FULL.
- The displayed (thumbnail) waveform when the DATa:RESOlution is set to REDUCEd.

When waveforms are sent to the instrument using the CURVe command or recalled from ISF files, the filtering frequency is obtained from the waveform preamble:

#### WFMInpre:FILTERFreq

This command sets the 3 dB low pass filter cutoff frequency for the waveform being transferred to the instrument's reference waveform memory.

Only FULL resolution waveforms may be sent to the instrument for storage and display in reference waveform memory.

The filtering of reduced resolution waveforms is controlled using the FILTERVu:FREQuency command. The available low pass frequencies depends on the instrument bandwidth and the horizontal settings (scale and record length) and may be queried for the last acquired waveform, (as specified by the DATa:SOUrce command) using the FILTERVu:FREQuency:AVAILable? query. This query returns a comma separated list of available FilterVu frequencies in decreasing order for the last acquired source waveform. For example, on a 100 MHz bandwidth instrument at a full resolution record length of 1 M points and a horizontal scale of 20 microseconds per division, the query returns these values which apply to the reduced resolution (displayed) waveform: 1000000000, 75000000, 42000000, 21000000, 110000000, 5500000, and 22000000.

The low pass filter frequency in effect can be queried using the FILTERVu:FREQuency? query.

## FilterVu Controls for the Displayed Waveform

The FilterVu feature can be turned on or off using the DISplay:GLITch command and the display intensity of the glitch capture waveform can be controlled using the DISplay:INTENSITy:GLITch command.

# Querying Acquisition Peak Detect Data from the Instrument

- 1. Use the DATa:COMPosition:AVAILable? query to determine if peak detect data (COMPOSITE\_ENV) is available. This query returns a list of waveform data types that are available from the instrument under the current instrument settings:
  - COMPOSITE\_YT for sample data
  - COMPOSITE\_ENV for envelope or peak detect data
  - SINGULAR\_YT for sample data
- 2. If COMPOSITE\_ENV is available, set the data composition to COMPOSITE\_ENV (:DATa:COMPosition COMPOSITE\_ENV). Otherwise, the peak detect data is not available and cannot be queried from the instrument.
- **3.** CURVe? will now return peak detect data.

# Querying Acquisition YT Sample Data from the Instrument

The sequence used to query sample data is nearly identical to the one used for peak detect data. Set the data composition to COMPOSITE\_YT or SINGULAR\_YT (based on results of the DATa:COMPosition:AVAILable? query); CURVe? will now return sample data.

### Selecting Acquisition Record Length

Like other oscilloscopes, the acquisition record length can be set using the HORizontal:RECOrdlength command. However, the actual number of points in the acquired waveform record may differ from the nominal record length established by the HORizontal:RECOrdlength setting, depending on the HORizontal:SCAle in effect at the time of the acquisition. The allowed values for setting the acquisition record length are 1,000,000 (1 million) and 100,000 (100 thousand) points. Depending on the horizontal scale in effect at the time of the acquisition, a nominal 1 million point record may be composed of 1.0 million or 1.25 million points and a nominal 100 thousand point record may be composed of 100 thousand or 125 thousand points. The actual number of points acquired for the source waveform (specified by the DATa:SOUrce command) may be obtained using the WFMOutpre:RECOrdlength? query.

For reduced resolution waveforms, the actual record length depends on the FilterVu frequency in effect in addition to the horizontal settings. The reduced resolution record lengths vary with the FilterVu frequency.

High Resolution and Envelope acquisition modes are not supported in DPO/MSO2000 series instruments.

For the digital waveforms (D0 through D15), the actual record length may differ from the nominal record length established by the HORizontal:RECOrdlength setting, depending on the HORizontal:SCAle in effect at the time of the acquisition and whether digital waveforms are selected from one or both of the digital pods (whether digital channels are turned on for D0 through D7, and for D8 through D15). For faster horizontal scales, the actual record length may be half of the nominal record length when digital waveforms from both digital pods are

turned on. Use the WFMOutpre:RECOrdlength? query to determine the actual record length for digital waveforms.

# Extensions to the DATA Commands

Like the DPO4000 series, the DPO2000 series provides the DATa:WIDth command that allows you to specify the data word width (in bytes) used when querying data from the instrument or when sending data to the instrument with the CURVe command. The following are the extensions to data commands:

- DATa:RESOlution
- DATa:COMPosition:AVAILable?
- DATa:COMPosition

#### **WFMOutpre Parameters**

The WFMOutpre? parameters correspond to the source waveform specified by the DATa:SOUrce command. The following are the extensions to Waveform Outpre commands:

- WFMOutpre:COMPosition
- WFMOutpre:FILTERFreq?
- WFMOutpre:RECOrdlength?

#### **WFMInpre Parameters**

The WFMInpre? parameters correspond to the destination reference waveform specified by the DATa:DESTination command. The following are the extensions to Waveform Inpre commands:

- WFMInpre:FILTERFreq
- WFMInpre:COMPosition

# FilterVu Frequency Control Commands

The following are the FilterVu commands:

- FILTERVu:FREQuency
- FILTERVu:FREQuency:AVAILable?
- DISplay:GLITch
- DISplay:INTENSITy:GLITch

# **Appendix C: Reserved Words**

This is a list of reserved words for your instrument. Capital letters identify the required minimum spelling.

*CAL	ADDRANDDATA	BINary	CMEan
*CLS	ADDRess	BITOrder	COLUMN
*DDT	ADDress	BITRate	COMMAND
*ESE	ALIas	BIT_Nr	COMPOSITE_EN\
*ESR	ALIas[	BLAckmanharris	COMPOSITE_YT
*IDN	ALL	BM	COMPosition
*LRN	ALLEV	ВМР	CONDition
*OPC	ALLFields	BN_Fmt	CONFigure
*PSC	ALLLines	BOTh	CONTRO]
*PUD	ALTERNATE	BOX	CONTinue
*RCL	ALWAYS	BTRIGger	СОРУ
*RST	AMPlitude	BURSt	COUNT
*SAV	AND	BUS	COUPling
*SRE	ANY	BUSY	CPU
*STB	APPKey	BY	CR
*TRG	AREa	BYPass	CRC
*TST	ASCII	BYT_Nr	CRCHeader
*WAI	ASCII	BYT_Or	CRCTrailer
1	ASCII	CALibrate	CREATE
1CH	ASSIgn	CALIDIALE	CREATE
7		CANH	CROSSHair
8	ATRIGger		
9	AUTOS of	CANL	CURSon
	AUTOSet	CARD	CURSors
A	AUTOZero	CARea	CURVe
A0	AUX	CATalog	CURrent
A1	AUXOut	CH	CUSTOM
A2	AUXin	CH1	CWD
A3	AVAILable	CH2	CYCLEcount
A4	AVErage	CH3	D
A5	Auto	CH4	D0
A6	В	CHannel	D1
A7	во	CHecksum	D10
A8	B1	CLASS	D11
A9	В2	CLEAR	D12
ABORt	в3	CLEARMenu	D13
ABOrt	В4	CLEARSNapshot	D14
ABSolute	В5	CLEar	D15
AC	в6	CLOCK	D2
ACKMISS	в7	CLOCk	D3
ACQ	в8	CM10BY15	D4
ACQLENGTH	в9	CM13BY18	D5
ACQuire	BACKLight	CM15BY21	D6
ACTIVeprinter	BACKWards	CM18BY24	D7
ADD	BANdwidth	СМ6ВҮ8	D8
ADDR10	BASe	CM7BY10	D9
ADDR7	BDIFFBP	CM9BY13	DATA

DATABits	ENV	FRAMEtype	HTTPPort
DATE	ENVelope	FRAMING	I2C
DATEPrint	EOF .	FRAme	ID
DATa	EOFTYPE	FREE	IDANDDATA
DAll	EQUal	FREESpace	IDFORmat
DB	EQual	FRENCh	IDLETime
DC	ERROR	FREQuency	IDLEtime
DECimal	ERRTYPE	FULL	IDPrint
DEFLT	ERRlog	FUL1	IDentifier
DEFault	ERROr	FUNCtion	IMAGESize
DEFine	ETHERnet	GAIN	IMAGe
DEGAUSS	EVEN	GATEWay	IMAge
DEGrees	EVENT	GATIng	IMMed
DELEte	EVENTS	GATing	IMPedance
DELIMiter	EVENTtable	GENeralcall	IN
DELTa	EVMsg	GERMan	IN11BY17
DELTatime	EVQty	GLITCh	IN2P5BY3P25
DELay	EXECute	GND	IN4BY6
DELayed	EXT	GPIBUSb	IN8BY10
DELete	EXTended	GRAticule	INDBits
DELta	EXTernal	GRId	INDICators
DESE	FACtor	HAGAKIPC	INDIvidual
DESKew	FACtory	HAGAKIPCARD	INDependent
DESTination	FAIL	HALFgrat	INFInite
DHCPbootp	FALL	HAMming	INIT
DIAg	FALSe	HANning	INKSaver
DIFFerential	FALling	HARDCopy	INPut
DIGItal	FASTPHOTO	HBArs	INTENSITY
DIGital	FASTer	HD1080I50	INTERLACED
DIGtal	FAStest	HD1080I60	INTERNal
DIR	FFT	HD1080P24	INVERTed
DIRection	FIELD	HD1080P25	INVert
DISabled	FIFty	HD1080PSF24	INVerted
DISplay	FILEFormat	HD480P60	INrange
DISplaymode	FILESystem	HD720P60	IO
DNS	FILTERFreq	HDtv	IPADDress
DOMAINname	FILTERVu	HEADER	ISCLOCKed
DPOModels	FINE	HEADer	ITALian
DRAFT	FIRst	HEIght	JAPAnese
DUAL	FIVEdivs	HERTZ	KOREan
DUmp	FLAg	HEXadecimal	L
DYNAMi C	FOCUS	HFRej	L2
E	FOLder	HIGH	L4
ECL	FORCEDRange	HIGHLimit	LABEL
EDGE	FORCe	HIRes	LABel
EDGe	FORMAt	HIStogram	LANGuage
EEPROM	FORMat	HIVALue	LANdscape
EITher	FORWards	HOLDTime	LARge
ENAble	FPAnel	HOLDoff	LAYout
ENCdg	FRACTional	HORZ	LESSEQual
END	FRAMEID	HORizontal	LESSLimit
ENET	FRAMEType	HPOS	LESSThan
ENGLish	FRAMETypeid	HSmode	LESSthan

LETTER	MOREthan	PASS	RATE35K
LEVel	MOSI	PASSWord	RATE50K
LF	MSB	PATtern	RATE800K
LFRej	NAME	PAYLength	RATIO
LIN	NAMe]	PAYLoad	RDELta
LINE	NANd	PERCent	READ
LINE	NEGative	PERIOD	READFile
LINEPeriod		PERSistence	RECATI
LIST	NEWpass NEXT	PERCENT	RECOrdlength
LOCK	NEXT	PHASE	RECTX
LOG	NO NO	PHOTO	RECTY
LOGIC	NOCARE	PictBridge	RECTangular
LOGIC	NOISErej	PING	REDUced
LOGIC	NONE	PK2Pk	REF
LOOP	NONE	PLAIN	REF1
LOW	NOPARity	PNG	REF2
LOWLimit	NORMal	POLARity	REFLevel
LOWETHITE	NOTCOMPuted	POLARTLY	REM
	NR1		REMote
LSB		POLarity PORTRait	
MAG	NRMAL		REName
MAIN	NR_Pt	PORTUguese POSITION	REPEATStart
MAIN	NTIMES		RESET
MAIN]	NTIMes	POSition	RESOlution RESUlt
MARK	NTSC	POSitive POVershoot	
MARKSINCOLumn	NULL		RESistance RESults
MATH	NULLFRDynamic	POWerupstatus	
MATH1	NULLFRStatic	PPULSECount PRESS	RI
MATHVAR	NUL ]		RIBinary RISEFall
MATH[1] MAXSamplerate	NUMACQ	PREVIEW PREViewstate	RISEFAII
MAXSamprerate MAXimum	NUMAVg NUMENTries	PREVIOUS	
MEAN	NUMERIC		RISing RMDir
MEAS	NUMERIC	PRINTQual PRINTer	RMS
MEASUrement			ROLL100MM
MEDium	NUMHORZ NUMVERT	PRODUCT	ROLL127MM
MEG	OCCURS	PRODUCT PRODUCTID	ROLL27MM ROLL210MM
		PROGressive	ROLL89MM
MESSage METHod	ODD OFF	PRObe	ROM
MID	OFFSet	PT_Fmt	ROM RP
MID2	ON	PT_ORder	RPBinary
MINIMUM	ONCE	PT_Off	RS232
MINMax	ONFAIL	PULSEWIDth	RS232C
MISO	OPTion	PULSEWIDTH	RUN
MISOMOSI	OUT	PULSE	RUNSTop
MIXed	OUTrange	PULSE	RUNT
MKDir	OVERLoad	PWIdth	RUNT
MM100BY150	OWNer	QUALifier	RUSSian
MM54BY86	PACKET	RADIUS	RWINClude
MODE	PAL	RATDELta	RX
MODE	PAPERSize	RATE15K	RXDATA
MOREEQual	PAPERType	RATE1M	RXENDPacket
MORELimit	PARallel	RATE20K	RXPARity
MOREThan	PARity	RATE25K	RXSTArt
MONETHAN	IAKICY	IOTI LE JIX	MAIAIL

SAMPLERate SOUrce THETA VAR  SAMPLEpoint SOUrce2 THREshold VBArs  SAMple SPANish THReshold VDELTA  SAVE SPC TIFF VENDORID  SCAN SPECTRAL TIME VERBOSE  SCALE SPI TIME VERT  SCLK SPREADSheet TOTAL VERTICAL  SCREEN SPACE TOTAL VIDEO  SCREEN SRIBINARY TOTALUPTIME VOLTS  SDATA SRPBINARY TRACK WAKEUP  SEARCH SS TRADitionalchinese WAVEform  SEARCHtotrigger STANDard TRANsition WAVFrm	CAMPLED 2+0	COLINGO	THETA	VAR
SAMple SPANish THReshold VDELTA SAVE SPC TIFF VENDORID SCAN SPECTral TIME VERBOSE SCAle SPI TIME VERT SCLK SPREADSheet TOTAL VERTical SCREEN SPace TOTAl VIDEO SCREEN SRIbinary TOTAluptime VOLts SDATA SRPbinary TRACK WAKEUP SEARCH SS TRADitionalchinese WAVEform				
SAVE SPC TIFF VENDORID  SCAN SPECTRA TIME VERBOSE  SCATOR SPI TIME VERT  SCLK SPREADSheet TOTAL VERTICAL  SCREEN SPACE TOTAL VIDEO  SCREEN SRIbinary TOTALUPTIME VOLTS  SDATA SRPbinary TRACK WAKEUP  SEARCH SS TRADitionalchinese WAVEform	•			_
SCAN SPECTRA TIME VERBOSE SCAle SPI TIME VERT SCLK SPREADSheet TOTAL VERTical SCREEN SPace TOTAl VIDEO SCREEN SRIbinary TOTAluptime VOLts SDATA SRPbinary TRACK WAKEUP SEARCH SS TRADitionalchinese WAVEform	-			
SCAle SPI TIME VERT  SCLK SPREADSheet TOTAL VERTical  SCREEN SPace TOTal VIDeo  SCREEN SRIbinary TOTaluptime VOLts  SDATA SRPbinary TRACk WAKEUP  SEARCH SS TRADitionalchinese WAVEform				_
SCLKSPREADSheetTOTALVERTicalSCREENSPaceTOTalVIDeoSCREENSRIbinaryTOTaluptimeVOLtsSDATASRPbinaryTRACkWAKEupSEARCHSSTRADitionalchineseWAVEform			. =: .=	
SCREENSPaceTOTalVIDeoSCREenSRIbinaryTOTaluptimeVOLtsSDATASRPbinaryTRACkWAKEupSEARCHSSTRADitionalchineseWAVEform				
SCREEN SRIbinary TOTaluptime VOLts SDATA SRPbinary TRACk WAKEup SEARCH SS TRADitionalchinese WAVEform			_	
SDATA SRPbinary TRACk WAKEup SEARCH SS TRADitionalchinese WAVEform				
SEARCH SS TRADitionalchinese WAVEform				
	SDATA	<del>-</del>		
SEARCHtotrigger STANDard TRANsition WAVFrm				
SECAM STANdard TRAnsition WEIghting		STANdard		WEIghting
SEConds START TRIGger WFId	SEConds			WFId
SELect STARTofframe TRIGgertosearch WFMInpre	SELect		TRIGgertosearch	WFMInpre
SELected STARTup TRUe WFMOutpre	SELected	STARTup	TRUe	WFMOutpre
SEQuence STARTupnosync TTL WHEn	SEQuence	STARTupnosync	TTL	WHEn
SERIALnumber STARt TURN WIDth	SERIALnumber	STARt	TURN	WIDth
SERnumber STARtbyte TWEnty WINdow	SERnumber	STARtbyte	TWEnty	WINdow
SET STATE TWOfifty WRITE	SET	STATE	TWOfifty	WRITE
SETHOld STATE] TX WRITEFile	SETHold		TX	WRITEFile
SETLEVE TXDATA X	SETLevel	STATIstics	TXDATA	Χ
SETTime STATUS TXENDPacket XDELta	SETTime	STATUS	TXENDPacket	XDELta
SETUP STATE TXPARITY XFF	SETUP	STATe	TXPARity	XFF
SETUP STATic TXRX XINCT	SETUp	STATic	TXRX	XINCr
SEVENTYFive STATUS TXSTART XUNit	SEVENTYFive	STATus	TXSTArt	XUNit
SHOW STDdev TYPE XY	SHOW	STDdev	TYPE	XY
SIGnal STOP TYPE XZEro	SIGnal	STOP	TYPe	XZEro
SIMPlifiedchinese STOPAfter Than Y	SIMPlifiedchinese	STOPAfter	Than	Υ
SINGULAR_YT STRing UNDO YDELta	SINGULAR_YT	STRing	UNDo	YDELta
SIZE STYle UNEQual YES	SIZe		UNEQual	YES
SLEEP STandard UNITS YMUlt	SLEEP	STandard	UNITS	YMUlt
SLEWRate SUBNETMask UNLock YOFf	SLEWRate		UNLock	YOFf
SLOWER SYNC UPPerthreshold YT	SLOWer	SYNC	UPPerthreshold	YT
SLOpe SYNCField USBDevice YUNIts	SLOpe	SYNCField	USBDevice	YUNIts
SMAll SYNCFrame USBTMC YUNit				YUNit
SNAPShot SYNCInterval USBTmc YUNits	SNAPShot	SYNCInterval	USBTmc	YUNits
SNAp TEKSecure USE YZEro				
SOF TEMPerature USER ZOOM		TEMPerature		
SOURCE TERmination V1X Z00m				
SOURCE2 TESTnumber V2X				
SOURCE[1] THDELta VALue				

## Index

A	BUS:B <x>:I2C{:DATA :SDATA}:SOUrce, 2-74</x>
ACQuire:MAXSamplerate?, 2-57	BUS:B <x>:LIN:BITRate, 2-75</x>
ACQuire?, 2-57	BUS:B <x>:LIN:IDFORmat, 2-75</x>
ACQuire:MODe, 2-57	BUS:B <x>:LIN:POLARity, 2-76</x>
ACQuire:NUMACq?, 2-58	BUS:B <x>:LIN:SAMPLEpoint, 2-76</x>
ACQuire:NUMAVg, 2-59	BUS:B <x>:LIN:SOUrce, 2-77</x>
ACQuire:STATE, 2-59	BUS:B <x>:LIN:STANDard, 2-77</x>
ACQuire:STOPAfter, 2-61	BUS:B <x>:PARallel:BIT<x>:SOUrce, 2-78</x></x>
Acquisition Command Group, 2-11	BUS:B <x>:PARallel:CLOCK:EDGE, 2-78</x>
Alias Command Group, 2-12	BUS:B <x>:PARallel:CLOCK:ISCLOCKed, 2-79</x>
ALIas, 2-61	BUS:B <x>:PARallel:CLOCK:SOUrce, 2-79</x>
ALIas[:STATE], 2-64	BUS:B <x>:PARallel:WIDth, 2-79</x>
ALIas:CATalog?, 2-62	BUS:B <x>:POSition, 2-80</x>
ALIas:DEFine, 2-62	BUS:B <x>:RS232C:BITRate, 2-80</x>
ALIas:DELEte, 2-63	BUS:B <x>:RS232C:DATABits, 2-81</x>
ALIas:DELEte[:NAMe], 2-64	BUS:B <x>:RS232C:DELIMiter, 2-81</x>
ALIas:DELEte:ALL, 2-63	BUS:B <x>:RS232C:DISplaymode, 2-81</x>
ALLEv?, 2-65	BUS:B <x>:RS232C:PARity, 2-82</x>
AUTOSet, 2-65	BUS:B <x>:RS232C:POLarity, 2-82</x>
AUTOSet:ENAble, 2-66	BUS:B <x>:RS232C:RX:SOUrce, 2-83</x>
AUXin:PRObe:AUTOZero, 2-67	BUS:B <x>:RS232C:TX:SOUrce, 2-83</x>
AUXin:PRObe:DEGAUss:STATE?, 2-68	BUS:B <x>:SPI:BITOrder, 2-84</x>
AUXin:PRObe:FORCEDRange, 2-68	BUS:B <x>:SPI:DATA:SIZe, 2-86</x>
AUXin:PRObe:ID:SERnumber?, 2-69	BUS:B <x>:SPI:DATA {:IN :MISO}:POLARity, 2-85</x>
AUXin:PRObe:ID:TYPE?, 2-69	BUS:B <x>:SPI:DATA {:IN :MISO}:SOUrce, 2-85</x>
AUXin:PRObe:RESistance?, 2-69	BUS:B <x>:SPI:DATA{:OUT :MOSI}:</x>
AUXin?, 2-66	POLARity, 2-86
AUXin:PRObe, 2-66	BUS:B <x>:SPI:DATA {:OUT :MOSI}:SOUrce, 2-86</x>
AUXin:PRObe:COMMAND, 2-67	BUS:B <x>:SPI:FRAMING, 2-87</x>
AUXin:PRObe:DEGAUss, 2-68	BUS:B <x>:SPI:IDLETime, 2-87</x>
AUXin:PRObe:GAIN, 2-69	BUS:B <x>:SPI{:CLOCK :SCLK}:POLARity, 2-84</x>
AUXin:PRObe:SIGnal, 2-70	BUS:B <x>:SPI{:CLOCK :SCLK}:SOUrce, 2-84</x>
AUXin:PRObe:UNIts?, 2-70	BUS:B <x>:SPI{:SELect :SS}:POLARity, 2-88</x>
	BUS:B <x>:SPI{:SELect :SS}:SOUrce, 2-88</x>
В	BUS:LOWerthreshold:CH <x>, 2-90</x>
	BUS:THReshold:CH <x>, 2-90</x>
BUS, 2-71	BUS:THReshold:D <x>, 2-91</x>
BUS:B <x>:CAN:BITRate, 2-71</x>	BUS:UPPerthreshold:CH <x>, 2-91</x>
BUS:B <x>:CAN:PRObe, 2-71</x>	BUS:B <x>:LABel, 2-75</x>
BUS:B <x>:CAN:SAMPLEpoint, 2-72</x>	BUS:B <x>:STATE, 2-89</x>
BUS:B <x>:CAN:SOUrce, 2-72</x>	BUS:B <x>:TYPE, 2-89</x>
BUS:B <x>:DISplay:FORMAt, 2-73</x>	BUSY?, 2-92
BUS:B <x>:I2C:ADDRess:RWINClude, 2-73</x>	

BUS:B<x>:I2C{:CLOCK|:SCLK}:SOUrce, 2-74

C	CURSor:XY:POLar:RADIUS:DELta?, 2-117
*CAL?, 2-93	CURSor:XY:POLar:RADIUS:POSITION <x>?, 2-117</x>
CALibrate:FACtory:STATus?, 2-94	CURSor:XY:POLar:RADIUS:UNIts?, 2-117
CALibrate:INTERNal:STARt, 2-94	CURSor:XY:POLar:THETA:DELta?, 2-118
CALibrate:INTERNal:STATus?, 2-95	CURSor:XY:POLar:THETA:POSITION <x>?, 2-118</x>
CALibrate:RESults:FACtory?, 2-96	CURSor:XY:POLar:THETA:UNIts?, 2-118
CALibrate:RESults:SPC?, 2-96	CURSor:XY:PRODUCT:DELta?, 2-118
CALibrate:TEMPerature?, 2-96	CURSor:XY:PRODUCT:POSITION <x>?, 2-119</x>
CALibrate:FACtory, 2-93	CURSor:XY:PRODUCT:UNIts?, 2-119
CALibrate:INTERNal, 2-94	CURSor:XY:RATIO:DELta?, 2-119
CALibrate:RESults?, 2-95	CURSor:XY:RATIO:POSITION <x>?, 2-119</x>
Calibration and Diagnostic Command Group, 2-16	CURSor:XY:RATIO:UNIts?, 2-120
CH <x>:PRObe:AUTOZero, 2-101</x>	CURSor:XY:RECTangular:X:DELta?, 2-120
CH <x>:PRObe:COMMAND, 2-102</x>	CURSor:XY:RECTangular:X:POSITION <x>, 2-120</x>
CH <x>:PRObe:DEGAUss, 2-102</x>	CURSor:XY:RECTangular:X:UNIts?, 2-120
CH <x>:PRObe:DEGAUss:STATE?, 2-102</x>	CURSor:XY:RECTangular:Y:DELta?, 2-121
CH <x>:PRObe:FORCEDRange, 2-103</x>	CURSor:XY:RECTangular:Y:POSITION <x>, 2-121</x>
CH <x>:PRObe:ID:SERnumber?, 2-104</x>	CURSor:XY:RECTangular:Y:UNIts?, 2-121
CH <x>:PRObe:ID:TYPE?, 2-105</x>	CURSor?, 2-109
CH <x>:PRObe:RESistance?, 2-105</x>	CURSor:FUNCtion, 2-109
CH <x>:PRObe:SIGnal, 2-105</x>	CURSor:HBArs?, 2-110
CH <x>:PRObe:UNIts?, 2-106</x>	CURSor:HBArs:DELTa?, 2-110
CH <x>:TERmination, 2-107</x>	CURSor:HBArs:UNIts, 2-111
CH <x>?, 2-97</x>	CURSor:HBArs:USE, 2-112
CH <x>:BANdwidth, 2-97</x>	CURSor:MODe, 2-112
CH <x>:COUPling, 2-97</x>	CURSor:VBArs?, 2-113
CH <x>:DESKew, 2-98</x>	CURSor: VBArs: DELTa?, 2-114
CH <x>:IMPedance, 2-98</x>	CURSor:VBArs:UNIts, 2-115
CH <x>:INVert, 2-99</x>	CURSor:VBArs:USE, 2-116
CH <x>:IABel, 2-99</x>	CURVe, 2-121
CH <x>:DFFSet, 2-100</x>	,
CH <x>:POSition, 2-100</x>	D
CH <x>:PRObe?, 2-101</x>	_
CH <x>:PRObe:GAIN, 2-103</x>	D < x > , 2 - 143
CH <x>:PRObe:ID?, 2-104</x>	D <x>:LABel, 2-143</x>
CH <x>:SCAle, 2-106</x>	D <x>:POSition, 2-143</x>
CH <x>: VOLts, 2-107</x>	D <x>:THREshold, 2-144</x>
CH <x>:YUNits, 2-108</x>	DATa, 2-123
CLEARMenu, 2-108	DATa:COMPosition:AVAILable?, 2-124
*CLS, 2-108	DATa:COMPosition, 2-124
Command Groups, 2-11	DATa:DESTination, 2-125
Cursor Command Group, 2-17	DATa:ENCdg, 2-125
CURSor:HBArs:POSITION <x>, 2-111</x>	DATa:RESOlution, 2-127
CURSor:VBArs:ALTERNATE <x>?, 2-111</x>	DATa:SOUrce, 2-127
CURSor:VBArs:HPOS <x>?, 2-114</x>	DATa:STARt, 2-129
CURSor: VBArs: POSITION < x>, 2-114 CURSor: VBArs: POSITION < x>, 2-115	DATa:STOP, 2-130
CURSor: VBArs: VDELTa?, 2-116	DATa:WIDth, 2-131
CONSOL V DAIS. V DELIA!, 2-110	DATE, 2-131

*DDT, 2-132 DESE, 2-133 DIAg:LOOP:OPTion:NTIMes, 2-134 DIAg:SELect: <function>, 2-136 DIAg:LOOP:OPTion, 2-133 DIAg:LOOP:STOP, 2-134 DIAg:RESUlt:FLAg?, 2-135 DIAg:RESUlt:LOG?, 2-135 DIAg:SELect, 2-136 DIAg:STATE, 2-137 Display Command Group, 2-18 DISplay:DIGital:HEIght, 2-138 DISplay:INTENSITy:BACKLight, 2-140 DISplay:INTENSITy:GLITch, 2-141 DISplay:INTENSITy:GRAticule, 2-141 DISplay:INTENSITy:WAVEform, 2-141 DISplay?, 2-137</function>	File System Command Group, 2-20 FILESystem, 2-153 FILESystem:FREESpace?, 2-155 FILESystem:WRITEFile, 2-158 FILESystem:CWD, 2-153 FILESystem:DELEte, 2-154 FILESystem:DIR?, 2-154 FILESystem:FORMat, 2-155 FILESystem:MKDir, 2-156 FILESystem:READFile, 2-156 FILESystem:READFile, 2-157 FILESystem:RMDir, 2-157 FILESystem:RMDir, 2-157 FILTERVu:FREQuency:AVAILable?, 2-159 FILTERVu:FREQuency, 2-158 FPAnel:PRESS, 2-159 FPAnel:TURN, 2-161
DISplay: 7, 2-137 DISplay: CLOCk, 2-137 DISplay: FORMat, 2-138 DISplay: GLITch, 2-139 DISplay: GRAticule, 2-139 DISplay: INTENSITy?, 2-140 DISplay: PERSistence, 2-142	G GPIBUsb:ID?, 2-162  H Hard copy Command Group, 2-22 HARDCopy, 2-162
*ESE, 2-144 *ESR?, 2-145 Ethernet Command Group, 2-19 ETHERnet:DNS:IPADDress, 2-146 ETHERnet:ENET:ADDress?, 2-147 ETHERnet:GATEWay:IPADDress, 2-147 ETHERnet:PING:STATUS?, 2-149 ETHERnet:DHCPbootp, 2-145 ETHERnet:DOMAINname, 2-146 ETHERnet:HTTPPort, 2-147 ETHERnet:IPADDress, 2-148 ETHERnet:NAME, 2-148 ETHERnet:PASSWord, 2-149 ETHERnet:PING, 2-149 ETHERnet:SUBNETMask, 2-150 EVENT?, 2-150	HARDCopy:INKSaver, 2-163 HARDCopy:PREVIEW, 2-163 HEADer, 2-164 Horizontal Command Group, 2-23 HORizontal:ACQLENGTH?, 2-165 HORizontal:DELay:MODe, 2-165 HORizontal:DELay:TIMe, 2-166 HORizontal:DIGital:RECOrdlength:MAIN?, 2-166 HORizontal:DIGital:SAMPLERate:MAIN?, 2-166 HORizontal:PREViewstate?, 2-167 HORizontal:RECOrdlength, 2-167 HORizontal:RESOlution, 2-168 HORizontal:SAMPLERate, 2-168 HORizontal:TRIGger:POSition, 2-169 HORizontal:POSition, 2-167 HORizontal:POSition, 2-167 HORizontal:SCAle, 2-168
EVMsg?, 2-151 EVQty?, 2-151	ID?, 2-169 *IDN?, 2-170

FACtory, 2-152

L	MEASUrement:IMMed:TYPe, 2-189
LANGuage, 2-170	MEASUrement:IMMed:UNIts?, 2-191
LOCk, 2-170	MEASUrement:IMMed:VALue?, 2-192
*LRN?, 2-171	MEASUrement:INDICators:HORZ <x>?, 2-193</x>
ERIV., 2 1/1	MEASUrement:INDICators:NUMHORZ?, 2-193
M	MEASUrement:INDICators:NUMVERT?, 2-193
M	MEASUrement:INDICators:STATE, 2-194
Mark Command Group, 2-23	MEASUrement:INDICators:VERT <x>?, 2-194</x>
MARK, 2-172	MEASUrement:INDICators?, 2-192
MARK:SELected:FOCUS?, 2-174	MEASUrement:MEAS <x>:COUNt?, 2-195</x>
MARK:SELected:MARKSINCOLumn?, 2-174	MEASUrement:MEAS <x>:DELay:DIRection, 2-196</x>
MARK:SELected:OWNer?, 2-174	MEASUrement:MEAS <x>:DELay:EDGE<x>, 2-196</x></x>
MARK:SELected:SOURCE?, 2-175	MEASUrement:MEAS <x>:DELay?, 2-195</x>
MARK:SELected:STARt?, 2-175	MEASUrement:MEAS <x>:MAXimum?, 2-197</x>
MARK:SELected:STATe?, 2-175	MEASUrement:MEAS <x>:MEAN?, 2-197</x>
MARK:SELected:ZOOm:POSition?, 2-175	MEASUrement:MEAS <x>:MINImum?, 2-197</x>
MARK:CREATE, 2-172	MEASUrement:MEAS <x>:SOURCE[1], 2-198</x>
MARK:DELEte, 2-173	MEASUrement:MEAS <x>:SOUrce<x>, 2-199</x></x>
MARK:FREE?, 2-173	MEASUrement:MEAS <x>:SOURCE2, 2-198</x>
MARK:SELected:END?, 2-174	MEASUrement:MEAS <x>:STATE, 2-199</x>
MARK:TOTal?, 2-176	MEASUrement:MEAS <x>:STDdev?, 2-200</x>
Math Command Group, 2-25	MEASUrement:MEAS <x>:TYPe, 2-201</x>
MATH[1]:HORizontal:POSition, 2-178	MEASUrement:MEAS <x>:UNIts?, 2-203</x>
MATH[1]:HORizontal:SCAle, 2-178	MEASUrement:MEAS <x>:VALue?, 2-204</x>
MATH[1]:HORizontal:UNIts, 2-179	MEASUrement: MEAS <x>?, 2-195</x>
MATH[1]:SPECTral:GATing:INDICators, 2-179	MEASUrement:REFLevel:ABSolute:HIGH, 2-205
MATH[1]:SPECTral:GATing:INDICators:	MEASUrement:REFLevel:ABSolute:LOW, 2-206
END?, 2-179	MEASUrement:REFLevel:ABSolute:MID, 2-207
MATH[1]:SPECTral:GATing:INDICators:	MEASUrement:REFLevel:ABSolute:MID <x>, 2-208</x>
STARt?, 2-180	MEASUrement:REFLevel:ABSolute:MID2, 2-207
MATH[1]:SPECTral:MAG, 2-180	MEASUrement:REFLevel:METHod, 2-208
MATH[1]:SPECTral:NYQUISTFreq?, 2-180	MEASUrement:REFLevel:PERCent:HIGH, 2-209
MATH[1]:SPECTral:WINdow, 2-181	MEASUrement:REFLevel:PERCent:LOW, 2-210
MATH[1]:VERTical:POSition, 2-182	MEASUrement:REFLevel:PERCent:MID, 2-210
MATH[1]:VERTical:SCAle, 2-182	MEASUrement:REFLevel:PERCent:MID <x>, 2-212</x>
MATH[1]:VERTical:UNIts?, 2-183	MEASUrement:REFLevel:PERCent:MID2, 2-211
MATH[1]?, 2-176	MEASUrement:REFLevel?, 2-205
MATH[1]:DEFine, 2-177	MEASUrement: SNAPShot, 2-212
MATH[1]:LABel, 2-176	MEASUrement?, 2-183
MATH[1]:TYPe, 2-181	MEASUrement: GATing, 2-184
Measurement Command Group, 2-26	MEASUrement:IMMed?, 2-185
MEASUrement:CLEARSNapshot, 2-184	MEASUrement: METHod, 2-204
MEASUrement:IMMed:DELay:DIRection, 2-185	MESSage, 2-212
MEASUrement:IMMed:DELay:EDGE <x>, 2-186</x>	MESSage:BOX, 2-212
MEASUrement:IMMed:DELay?, 2-185	MESSage:CLEAR, 2-213
MEASUrement:IMMed:SOUrce <x>, 2-188</x>	MESSage:SHOW, 2-214
MEASUrement:IMMed:SOUrce1, 2-187	MESSage:STATE, 2-216
MEASUrement:IMMed:SOUrce2, 2-188	

Miscellaneous Command Group, 2-29 SAVe: ASSIgn: TYPe, 2-233 SAVe:IMAGe, 2-234 SAVe:IMAGe:LAYout, 2-235 Ν SAVe:SETUp, 2-235 NEWpass, 2-217 SAVe: WAVEform, 2-236 Search Commands Group, 2-33 SEARCH:SEARCH<x>:COPy, 2-242 SEARCH:SEARCH<x>:STATE, 2-242 \*OPC, 2-217 SEARCH:SEARCH<x>:TOTAL?, 2-242 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: P CAN:CONDition, 2-245 PASSWord, 2-218 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: PICTBridge: DATEPrint, 2-219 CAN:DATa:DIRection, 2-245 PICTBridge:IMAGESize, 2-220 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: PICTBridge:PAPERSize, 2-221 CAN:DATa:QUALifier, 2-246 PICTBridge:PAPERType, 2-223 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: PICTBridge:PRINTQual, 2-223 CAN:DATa:SIZe, 2-247 PICTBridge:DEFault, 2-219 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: PICTBridge:IDPrint, 2-220 CAN:DATa:VALue, 2-247 \*PSC, 2-224 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: \*PUD, 2-224 CAN:FRAMEtype, 2-248 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: R CAN{:IDentifier|:ADDRess}:MODe, 2-248 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: \*RCL, 2-225 CAN{:IDentifier|:ADDRess}:VALue, 2-249 RECAll:SETUp, 2-225 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C: RECAll: WAVEform, 2-226 ADDRess:MODe, 2-249 REF<x>:HORizontal:DELay:TIMe, 2-227 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C: REF<x>:HORizontal:SCAle, 2-228 ADDRess:TYPe, 2-249 REF<x>:VERTical:POSition, 2-229 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C: REF<x>:VERTical:SCAle, 2-230 ADDRess: VALue, 2-250 REF<x>?, 2-227 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C: REF<x>:DATE?, 2-227 CONDition, 2-250 REF<x>:LABel, 2-228 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C: REF<x>:POSition, 2-228 DATa:DIRection, 2-251 REF<x>:SCAle, 2-229 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C: REF<x>:TIMe?, 2-229 DATa:SIZe, 2-251 REM, 2-231 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:I2C: \*RST, 2-232 DATa: VALue, 2-252 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN: S CONDition, 2-252 \*SAV, 2-232 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN: Save and Recall Command Group, 2-31 DATa:HIVALue, 2-253 SAVe:EVENTtable:BUS<x>, 2-233 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN: SAVe:IMAGe:FILEFormat, 2-234 DATa:QUALifier, 2-253 SAVe: WAVEform: FILEFormat, 2-237 SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN: SAVe: WAVEform: GATIng, 2-238 DATa:SIZe, 2-254

SAVe: WAVEform: SPREADSheet: RESOlution, 2-238

- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN: DATa:VALue, 2-255
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN: ERRTYPE, 2-255
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:LIN: IDentifier:VALue, 2-256
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: PARallel:VALue, 2-256
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: RS232C:CONDition, 2-257
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: RS232C:RX:DATa:SIZe, 2-257
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: RS232C:RX:DATa:VALue, 2-258
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: RS232C:TX:DATa:SIZe, 2-258
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>: RS232C:TX:DATa:VALue, 2-258
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI: CONDition, 2-259
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI: DATa:SIZe, 2-260
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI: DATa{:MISO|:IN}:VALue, 2-259
- SEARCH:SEARCH<x>:TRIGger:A:BUS:B<x>:SPI: DATa{:MOSI|:OUT}:VALue, 2-260
- SEARCH:SEARCH<x>:TRIGger:A:BUS: SOUrce, 2-260
- SEARCH:SEARCH<x>:TRIGger:A:BUS?, 2-243
- SEARCH:SEARCH<x>:TRIGger:A:EDGE: SLOpe, 2-261
- SEARCH:SEARCH<x>:TRIGger:A:EDGE: SOUrce, 2-261
- SEARCH:SEARCH<x>:TRIGger:A:LEVel, 2-262
- SEARCH:SEARCH<x>:TRIGger:A:LEVel: CH<x>, 2-262
- SEARCH:SEARCH<x>:TRIGger:A:LEVel: MATH, 2-262
- SEARCH:SEARCH<x>:TRIGger:A:LEVel: REF<x>, 2-263
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc: FUNCtion, 2-263
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut: CH<x>, 2-263
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut: CLOCk:EDGE, 2-264

- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut: CLOCk:SOUrce, 2-264
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut: D<x>, 2-265
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut: MATH, 2-265
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:INPut: REF<x>, 2-266
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern: INPut:CH<x>, 2-266
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern: INPut:D<x>, 2-266
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern: INPut:MATH, 2-267
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern: INPut:REF<x>, 2-267
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern: WHEn, 2-268
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern: WHEn:LESSLimit, 2-268
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc:PATtern: WHEn:MORELimit, 2-269
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc: THReshold:CH<x>, 2-269
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc: THReshold:MATH, 2-269
- SEARCH:SEARCH<x>:TRIGger:A:LOGIc: THReshold:REF<x>, 2-270
- SEARCH:SEARCH<x>:TRIGger:A: LOWerthreshold:CH<x>, 2-270
- SEARCH:SEARCH<x>:TRIGger:A: LOWerthreshold:MATH, 2-270
- SEARCH:SEARCH<x>:TRIGger:A: LOWerthreshold:REF<x>, 2-271
- SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth: POLarity, 2-271
- SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth: SOUrce, 2-272
- SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth: WHEn, 2-272
- SEARCH:SEARCH<x>:TRIGger:A:PULSEWidth: WIDth, 2-273
- SEARCH:SEARCH<x>:TRIGger:A:RUNT: POLarity, 2-273
- SEARCH:SEARCH<x>:TRIGger:A:RUNT: SOUrce, 2-273

SEARCH:SEARCH <x>:TRIGger:A:RUNT:</x>	SET?, 2-286
WHEn, 2-274	SETUP <x>:DATE?, 2-287</x>
SEARCH:SEARCH <x>:TRIGger:A:RUNT:</x>	SETUP <x>:LABEL, 2-287</x>
WIDth, 2-274	SETUP <x>:TIME?, 2-288</x>
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	*SRE, 2-288
CLOCk:EDGE, 2-275	Status and Error Command Group, 2-37
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	*STB?, 2-289
CLOCk:SOUrce, 2-275	515.,2 20
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	т
CLOCk:THReshold, 2-276	Т
SEARCH:SEARCH <x>:TRIGger:A:SETHold:DATa:</x>	TEKSecure, 2-289
SOUrce, 2-276	TIME, 2-290
SEARCH:SEARCH <x>:TRIGger:A:SETHold:DATa:</x>	TOTaluptime?, 2-291
	*TRG, 2-291
THReshold, 2-277 SEADCH-SEADCH-YNTDIGGGYA-SETHOLD	Trigger Command Group, 2-38
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	TRIGger, 2-291
HOLDTime, 2-277	TRIGger:A:BUS:B <x>:CAN:CONDition, 2-294</x>
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	TRIGger:A:BUS:B <x>:CAN:DATa:DIRection, 2-294</x>
SETTime, 2-277	TRIGger:A:BUS:B <x>:CAN:DATa:QUALifier, 2-295</x>
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	TRIGger: A:BUS:B <x>:CAN:DATa:SIZe, 2-296</x>
THReshold:CH <x>, 2-278</x>	TRIGger: A:BUS:B <x>:CAN:DATa:VALue, 2-296</x>
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	TRIGger:A:BUS:B <x>:CAN:FRAMEtype, 2-297</x>
THReshold:REF <x>, 2-278</x>	TRIGger:A:BUS:B <x>:CAN{:IDentifier :ADDRess}:</x>
SEARCH:SEARCH <x>:TRIGger:A:SETHold:</x>	MODe, 2-297
THReshold{:MATH :MATH1}, 2-278	TRIGger:A:BUS:B <x>:CAN{:IDentifier :ADDRess}:</x>
SEARCH:SEARCH <x>:TRIGger:A:TYPe, 2-280</x>	VALue, 2-298
SEARCH:SEARCH <x>:TRIGger:A:UPPerthreshold:</x>	TRIGger:A:BUS:B <x>:I2C:ADDRess:MODe, 2-298</x>
CH < x > , 2-281	TRIGger: A:BUS:B <x>:I2C:ADDRess:TYPe, 2-299</x>
SEARCH:SEARCH <x>:TRIGger:A:UPPerthreshold:</x>	TRIGger: A:BUS:B <x>:I2C:ADDRess:VALue, 2-299</x>
MATH, 2-281	TRIGger: A:BUS:B <x>:I2C:ADDRess: VALue, 2-299 TRIGger: A:BUS:B<x>:I2C:CONDition, 2-300</x></x>
SEARCH:SEARCH <x>:TRIGger:A:UPPerthreshold:</x>	TRIGger: A:BUS:B <x>:I2C:CONDition, 2-300 TRIGger: A:BUS:B<x>:I2C:DATa:DIRection, 2-300</x></x>
REF <x>, 2-282</x>	TRIGger: A:BUS:B <x>:I2C:DATa:BIRection, 2-300</x>
SEARCH:SEARCH <x>:TRIGger:A{:TRANsition :</x>	
RISEFall}:DELTatime, 2-279	TRIGger: A:BUS:B <x>:I2C:DATa:VALue, 2-301</x>
SEARCH:SEARCH <x>:TRIGger:A{:TRANsition :</x>	TRIGger: A:BUS:B <x>:LIN:CONDition, 2-302</x>
RISEFall}:POLarity, 2-279	TRIGger: A:BUS:B <x>:LIN:DATa:HIVALue, 2-302</x>
SEARCH:SEARCH <x>:TRIGger:A{:TRANsition :</x>	TRIGger: A:BUS:B <x>:LIN:DATa:QUALifier, 2-303</x>
RISEFall}:SOUrce, 2-280	TRIGger: A:BUS:B <x>:LIN:DATa:SIZe, 2-304</x>
SEARCH:SEARCH <x>:TRIGger:A{:TRANsition :</x>	TRIGger: A:BUS:B <x>:LIN:DATa:VALue, 2-304</x>
RISEFall}:WHEn, 2-280	TRIGger:A:BUS:B <x>:LIN:ERRTYPE, 2-305</x>
SEARCH?, 2-239	TRIGger:A:BUS:B <x>:LIN:IDentifier:VALue, 2-305</x>
SELect, 2-282	TRIGger:A:BUS:B <x>:PARallel:VALue, 2-306</x>
SELect:BUS <x>, 2-283</x>	TRIGger:A:BUS:B <x>:RS232C:CONDition, 2-306</x>
SELect:CH <x>, 2-283</x>	TRIGger:A:BUS:B <x>:RS232C:RX:DATa:</x>
SELect:CONTROl, 2-284	SIZe, 2-307
SELect: D <x>, 2-284</x>	TRIGger:A:BUS:B <x>:RS232C:RX:DATa:</x>
SELect:MATH[1], 2-285	VALue, 2-307
SELect:REF <x>, 2-285</x>	TRIGger:A:BUS:B <x>:RS232C:TX:DATa:</x>
DELCOLICEI A. , 2-203	SIZe, 2-308

TRIGger:A:BUS:B <x>:RS232C:TX:DATa:</x>	TRIGger: A:SETHold: CLOCk?, 2-331
VALue, 2-308	TRIGger: A:SETHold:DATa:SOUrce, 2-333
TRIGger:A:BUS:B <x>:SPI:CONDition, 2-308</x>	TRIGger: A:SETHold:DATa:THReshold, 2-334
TRIGger:A:BUS:B <x>:SPI:DATa:SIZe, 2-310</x>	TRIGger: A:SETHold:DATa?, 2-333
TRIGger:A:BUS:B <x>:SPI:DATa{:IN :MISO}:</x>	TRIGger: A:SETHold: HOLDTime, 2-334
VALue, 2-309	TRIGger: A:SETHold:SETTime, 2-335
TRIGger:A:BUS:B <x>:SPI:DATa{:OUT :MOSI}:</x>	TRIGger: A:SETHold:THReshold:CH <x>, 2-335</x>
VALue, 2-309	TRIGger:A:SETHold:THReshold:D <x>, 2-336</x>
TRIGger:A:BUS:SOUrce, 2-310	TRIGger:A:UPPerthreshold:CH <x>, 2-340</x>
TRIGger: A:EDGE: COUPling, 2-311	TRIGger:A:VIDeo:HOLDoff:FIELD, 2-341
TRIGger:A:EDGE:SLOpe, 2-312	TRIGger: A: VIDeo: LINE, 2-341
TRIGger: A:EDGE: SOUrce, 2-312	TRIGger: A: VIDeo: POLarity, 2-342
TRIGger: A:HOLDoff: TIMe, 2-313	TRIGger: A: VIDeo: SOUrce, 2-343
TRIGger: A:LEVel: AUXin, 2-314	TRIGger: A: VIDeo: STANdard, 2-343
TRIGger: A:LEVel:CH <x>, 2-315</x>	TRIGger:A:VIDeo{:SYNC :FIELD}, 2-344
TRIGger:A:LEVel:D <x>, 2-315</x>	TRIGger:A{:TRANsition :RISEFall}:
TRIGger: A:LOGIc: CLAss, 2-316	DELTatime, 2-337
TRIGger: A:LOGIc:FUNCtion, 2-317	TRIGger:A {:TRANsition :RISEFall}:POLarity, 2-33
TRIGger:A:LOGIc:INPut:CH <x>, 2-318</x>	TRIGger:A{:TRANsition :RISEFall}:SOUrce, 2-338
TRIGger:A:LOGIc:INPut:CLOCk:EDGE, 2-318	TRIGger:A{:TRANsition :RISEFall}:WHEn, 2-338
TRIGger:A:LOGIc:INPut:CLOCk:SOUrce, 2-319	TRIGger:A{:TRANsition :RISEFall}?, 2-336
TRIGger:A:LOGIc:INPut:D <x>, 2-319</x>	TRIGger:EXTernal:PRObe, 2-344
TRIGger: A:LOGIc:INPut?, 2-317	TRIGger:EXTernal:YUNIts?, 2-345
TRIGger: A:LOGIc: PATtern: DELTatime, 2-320	TRIGger:A, 2-292
TRIGger:A:LOGIc:PATtern:INPut:D <x>, 2-320</x>	TRIGger:A:BUS, 2-293
TRIGger: A:LOGIc: PATtern: WHEn, 2-321	TRIGger:A:EDGE?, 2-310
TRIGger: A:LOGIc: PATtern: WHEn:	TRIGger:A:HOLDoff?, 2-313
LESSLimit, 2-321	TRIGger:A:LEVel, 2-314
TRIGger: A:LOGIc: PATtern: WHEn:	TRIGger:A:LOGIc?, 2-316
MORELimit, 2-322	TRIGger:A:MODe, 2-324
TRIGger: A:LOGIc: PATtern?, 2-319	TRIGger:A:PULse?, 2-324
TRIGger:A:LOGIc:THReshold:	TRIGger:A:RUNT?, 2-328
(CH < x >   D < x >), 2-322	TRIGger:A:RUNT:WHEn, 2-329
TRIGger:A:LOWerthreshold:CH <x>, 2-323</x>	TRIGger:A:SETHold?, 2-331
TRIGger:A:LOWerthreshold{:EXT :AUX}, 2-324	TRIGger:A:TYPe, 2-339
TRIGger:A:PULse:CLAss, 2-325	TRIGger:A:VIDeo?, 2-340
TRIGger: A: PULSEWidth: POLarity, 2-326	TRIGger:EXTernal?, 2-344
TRIGger: A:PULSEWidth: SOUrce, 2-326	TRIGger:FREQuency?, 2-345
TRIGger: A: PULSEWidth: WHEn, 2-327	TRIGger:STATE?, 2-345
TRIGger: A:PULSEWidth: WIDth, 2-327	*TST?, 2-346
TRIGger: A:PULSEWIDth?, 2-325	
TRIGger: A:RUNT: POLarity, 2-328	U
TRIGger:A:RUNT:SOUrce, 2-329	UNLock, 2-346
TRIGger:A:RUNT:WIDth, 2-330	USBDevice:CONFigure, 2-347
TRIGger:A:SETHold:CLOCk:EDGE, 2-331	USBTMC, 2-347
TRIGger:A:SETHold:CLOCk:SOUrce, 2-332	USBTMC; 2-347 USBTMC:PRODUCTID:DECimal?, 2-347
TRIGger: A:SETHold: CLOCk: THReshold, 2-332	USBTMC:PRODUCTID:HEXadecimal?, 2-347
	ODD INIC.I RODUCTID.IIE/Addccilliai!, 2-340

USBTMC:SERIALnumber?, 2-348 USBTMC:VENDORID:DECimal?, 2-348 USBTMC:VENDORID:HEXadecimal?, 2-349

### V

VERBose, 2-349 Vertical Command Group, 2-45

### W

\*WAI, 2-350
Waveform Transfer Command Group, 2-48
WAVFrm?, 2-350
WFMInpre:COMPosition, 2-353
WFMInpre?, 2-351
WFMInpre:BIT\_Nr, 2-351
WFMInpre:BN\_Fmt, 2-352
WFMInpre:BYT\_Nr, 2-352
WFMInpre:BYT\_Or, 2-353
WFMInpre:ENCdg, 2-354
WFMInpre:FILTERFreq, 2-354
WFMInpre:NR\_Pt, 2-355
WFMInpre:PT\_Fmt, 2-355

WFMInpre:FILTERFreq, 2-352 WFMInpre:NR\_Pt, 2-355 WFMInpre:PT\_Fmt, 2-355 WFMInpre:PT\_Off, 2-356 WFMInpre:XINcr, 2-356 WFMInpre:XUNit, 2-357 WFMInpre:XZEro, 2-358 WFMInpre:YMUlt, 2-358 WFMInpre:YOFf, 2-359 WFMInpre:YUNit, 2-360 WFMInpre:YZEro, 2-360

WFMOutpre:COMPosition, 2-364 WFMOutpre:FILTERFreq?, 2-365

WFMOutpre: RECOrdlength?, 2-367 WFMOutpre?, 2-361 WFMOutpre:BIT Nr, 2-362 WFMOutpre:BN Fmt, 2-362 WFMOutpre:BYT Nr, 2-363 WFMOutpre:BYT Or, 2-363 WFMOutpre: ENCdg, 2-364 WFMOutpre:NR Pt?, 2-365 WFMOutpre:PT Fmt?, 2-366 WFMOutpre:PT Off?, 2-366 WFMOutpre:PT ORder?, 2-367 WFMOutpre: WFId?, 2-367 WFMOutpre:XINcr?, 2-369 WFMOutpre:XUNit?, 2-369 WFMOutpre: XZEro?, 2-369 WFMOutpre:YMUlt?, 2-370 WFMOutpre: YOFf?, 2-370 WFMOutpre: YUNit?, 2-371 WFMOutpre: YZEro?, 2-371

#### Z

Zoom Command Group, 2-55
ZOOm:ZOOM1:HORizontal:POSition, 2-373
ZOOm:ZOOM1:HORizontal:SCAle, 2-374
ZOOm?, 2-372
ZOOm{:MODe|:STATE}, 2-372
ZOOm:ZOOM1?, 2-373
ZOOm:ZOOM1:FACtor?, 2-373
ZOOm:ZOOM1:POSition, 2-374
ZOOm:ZOOM1:SCAle, 2-374
ZOOm:ZOOM1:STATE, 2-375